Personal Communications
AS/400 and 3270 for Windows

IBM

Reference

Version 4.1

SC31-8264-00

Personal Communications
AS/400 and 3270 for Windows

IBM

Reference

Version 4.1

© ODBC is copyrighted by Microsoft Corporation.

SC31-8264-00

Note

Before using this information and the product it supports, be sure to read the general information under “Notices” on page xiii.

First Edition (March 1996)

This edition applies to Version 4.1 of Personal Communications and to all subsequent releases and modifications until otherwise indicated in new editions or technical newsletters. This edition is a major revision of *S20H-1773* and *S20H-1642*, which still apply to Version 4.0 of this product. Make sure you are using the correct edition for the level of the product.

Order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

IBM welcomes your comments. A form for readers' comments may be provided at the back of this publication, or you may address your comments to the following address:

International Business Machines Corporation
Department CGMD
P.O. Box 12195
Research Triangle Park, North Carolina
27709-2195

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© **Copyright International Business Machines Corporation 1989, 1996. All rights reserved.**
Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

General Information

Chapter 1. Personal Communications Highlights 1-1

Chapter 2. Where to Get More Information 2-1
Online Help 2-1
How to Use Online Help 2-1
Messages 2-1
OIA Messages 2-1
Personal Communications Library 2-2

Chapter 3. Problem Determination and Reporting 3-1
Problem Determination (PD) 3-1
Problem-Source Identification (PSI) 3-2
Problem Reporting (PR) 3-3
Contacting IBM 3-3
Other Ways to Contact IBM 3-4

Chapter 4. Printing 4-1
Setting Up the Printer 4-1
Defining the Windows Printer for a Session 4-1
Using PDT Files 4-2
PDT Files 4-2
Setting Printer Control Parameters (Windows Driver Only) 4-5
Setting Printer Control Items (Windows Driver Only) 4-8
Printing to Disk 4-9

Chapter 5. Transferring Files 5-1
Sending Files to the Host System 5-2
Receiving Files from the Host System 5-3
Using List Files 5-4
Creating a Template 5-5
Import/Export (3270 Sessions Only) 5-7
Transferring Files Using Import/Export 5-7
Defining Transfer Types 5-7
Explanation of Items to Be Defined 5-7
Defining Transfer Types 5-9
Setting Transfer Options 5-10
File-Transfer Timeout 5-10
Clearing Sessions before Transfer (3270 only) 5-10
File Transfer Packet Size (3270 only) 5-10
Extension for List Files 5-10
Status Window 5-10
PC Code Page 5-10
Enhanced Protocol (IBM Global Network Connection only) 5-11
Default Host Command 5-11
Default Directory for File Transfer 5-11
Changing Settings 5-11

© Copyright IBM Corp. 1989, 1996

Setting Translation Tables 5-11
Changing Translation Tables 5-11
Customizing Translation Tables 5-12
Creating IDP Files 5-13

Chapter 6. Modems 6-1
Asynchronous Modem Information 6-1
US Robotics Sportster 14.4 External Modem 6-1
IBM ASYNC/SDLC V.32 Modem/A Modem 6-1
Synchronous Modem Information 6-1
Command and Indication 6-1
Dial Character 6-2
NEC ITM2400mkII Modem 6-2
Hitachi High-Speed Hybrid Telephone 6-2
IBM7855-10 Modem 6-3

Chapter 7. Country Codes, Code Pages, and Character Sets 7-1
Country Codes 7-2
Keyboard Country ID and Shift Support 7-3
Code Pages and Character Sets 7-5
Host Code Page Tables 7-6

Chapter 8. Keyboard Layouts 8-1
Keyboard Layouts for Windows Mode 8-2
APL Keyboard Layouts for Windows Mode (3270 Only) 8-15
Key Map for Home3270 8-18

Chapter 9. Messages 9-1
File Transfer Messages 9-88

Personal Communications/3270

Chapter 10. Building a Printer Definition Table (PDT) for PC/3270 10-1
Customizing the Printer Definition Table 10-1
Printer Definition File Format 10-1
Printer Definition Tables 10-2
Example Printer Definition File 10-2
Supplemental Explanation of PDF Statements 10-9
SCS TAB Setting 10-10
Printer Definition File Field Names and Symbols 10-10
Printer Color Mixing 10-13
Printer Session Data Stream Support 10-14
3270 Data Stream 10-14
SCS Data Stream 10-15
Delimiting Print Jobs 10-17
Structured Fields 10-17

Chapter 11. File Transfer Commands for PC/3270 11-1
File Transfer Methods 11-1
Requirements and Restrictions 11-1
Sending and Receiving Files from the DOS Command Prompt 11-2
Using the VM/CMS SEND Command 11-3
Using the VM/CMS RECEIVE Command 11-6

Using the MVS/TSO SEND Command 11-9
Using the MVS/TSO RECEIVE Command 11-14
Using the CICS SEND Command 11-17
Using the CICS RECEIVE Command 11-20
Configuring File-Transfer Code Translation 11-22

Chapter 12. Considerations for Installation and Use of PC/3270 Sessions 12-1
Host-Session Window Operations 12-1
Cursor Color 12-1
Releasing Insert Mode with the Attention Key 12-1
Scroll Bar 12-1
Scroll-Lock Key 12-2
3270-Session Screen-Size Control 12-2
Customizing a Display Translation Table 12-3
Edit Function 12-4
File Transfer Function in a DOS Box 12-5
Graphic Functions 12-6
Graphic Protocol 12-6
Print Processing 12-10
Using a Printer in Non-SNA Coax Attachment 12-10
Print Job Control Using SNA Timeout 12-10
Using ZipPrint 12-13

Personal Communications AS/400

Chapter 13. Using Virtual Printers 13-1
Starting Virtual Printers 13-1

Chapter 14. Building a Printer Definition Table (PDT) for PC400 14-1
Creating and Changing the Printer Definition Table (PDT File) 14-1
Printer Definition File (PDF File) Format 14-1
Example of Printer Definition Files 14-2
Field Names of Printer Definition Files 14-21
Parameter Definition of Printer Control Codes 14-26
Symbols of Printer Definition Files 14-26
Using Printer Control Codes 14-29
Printer Control Code Format 14-29
Supported Control Codes 14-29
Printer Control Codes 14-31
Programming Notes 14-35
Restrictions and Notes for AS/400 Printer Commands and Printer Setup 14-35
PFT Migration Utility 14-38
How to Use the PFT Migration Utility 14-38
Details of Migration 14-39

Chapter 15. Field Attribute Codes 15-1

Chapter 16. AS/400 Utilities 16-1
About the AS/400 Utilities 16-1
Buttons on the Utilities Window 16-1
AS/400 Utilities Control Panel 16-2

Chapter 17. Data Transfer for PC400 17-1
Data Transfer Function Overview 17-1
Transferring Files from an AS/400 System to a Workstation 17-2
Transferring Files from a Workstation to an AS/400 System 17-2
Preparing for Data Transfer 17-5
Required Software Products 17-5
Transfer Function 17-5
Data Transfer Program 17-6
Data Concepts of AS/400 and Your Workstation 17-7
Creating a Workstation-to-AS/400 Transfer Request 17-8
Items to Be Specified 17-8
Saving, Opening, Changing, and Executing a Transfer Request 17-15
Creating an AS/400-to-Workstation Transfer Request 17-17
Items to Be Specified 17-19
Saving, Opening, Changing, and Executing a Transfer Request 17-34
Limited Usage of File Names and Field Names 17-36
Examples of Transfer Requests for Receiving 17-36
Receiving Part of an AS/400 File 17-37
Receiving Records Joined from Several AS/400 Files 17-38
Receiving Records Using File Qualifiers 17-39
Receiving with Field Missing Records Joined 17-39
Receiving with Records in a Same File Joined 17-40
Specifying Records to Be Included in a Group 17-40
Specifying Summary Records to Be Transferred 17-41
Functions Available from Pull-Down Menu 17-42
File Description Files 17-45
Creating a File Description File 17-46
Example 17-53
Data Conversions 17-53
Record Size 17-53
Data Types 17-53
Personal Computer File Types 17-57
AS/400 System-to-Personal Computer Performance Considerations 17-76

Chapter 18. File Transfer for PC400 18-1
PC File Transfer with the CRLF Option 18-1
Transfer to a Physical Source File 18-2
Transfer to a Physical File 18-2
Use of the DSPMBRLST Command 18-2
Restrictions for Transferred File Size 18-3

Chapter 19. ODBC Driver for PC400 Database Access 19-1
Supported CCSIDs 19-1
Connecting With Earlier Versions of AS/400 19-2
APPC Data Compression 19-2
Attribute Keywords for SQLDriverConnect() 19-2
Considerations and Limitations 19-4
Auto Logon 19-4
Logon Timeout 19-4
Using Lotus 1-2-3 19-4
Using Microsoft Access 19-4
Maximum Number of Columns in a Table 19-4

Chapter 20. Considerations for Installation and Use of PC400 Sessions 20-1

General Workstation Window Operations: Scroll Bar 20-1
Print Processing 20-1

Glossary X-1

Index X-5

Figures

8-1. Type-1 APL Keyboard 8-16
8-2. Type-2 APL Keyboard 8-16
8-3. Type-3 APL Keyboard 8-17
8-4. Type-4 APL Keyboard 8-17
8-5. Common Control Code of Keyboard Core Segment for 122-Key Keyboard 8-18
8-6. Common Control Code of Keyboard Core Segment for Enhanced Keyboard 8-19
8-7. Common Control Code of Keyboard Core Segment for Japanese Keyboard 8-19
8-8. Other Control Code Map of Key Segment B 8-20
8-9. Control Code Map of Keyboard Core Segment for U.S. 122-Key Keyboard 8-21
8-10. Control Code Map of Keyboard Core Segment for U.S. Enhanced Keyboard 8-21
11-1. VM/CMS SEND Command Syntax 11-3
11-2. VM/CMS RECEIVE Command Syntax 11-6
11-3. MVS/TSO SEND Command Syntax 11-9
11-4. MVS/TSO RECEIVE Command Syntax 11-14
11-5. CICS SEND Command Syntax 11-17
11-6. CICS RECEIVE Command Syntax 11-20

© Copyright IBM Corp. 1989, 1996

Tables

4-1. Print Control Parameters (Text) 4-5
4-2. Print-Control Options 4-6
4-3. Print Control (PC400 only) 4-7
4-4. Page Control (PC400 only) 4-7
4-5. Print Control Parameters (Graphics) 4-8
5-1. Transfer File Options 5-7
7-1. Keyboard Type 7-1
7-2. Country Codes 7-2
7-3. Keyboard Country ID and Shift Support 7-3
7-4. Code Pages and Character Sets 7-5
10-1. Printer Symbol Definitions 10-10
10-2. Color Mixes 10-13
10-3. 3270 Data Stream Commands 10-14
10-4. 3270 Data Stream Orders 10-14
10-5. 3270 Data Stream Control Codes 10-15
10-6. Supported SCS Control Codes 10-15
10-7. Begin/End of File Query Reply Format 10-17
10-8. Begin/End of File Structured Field Format 10-18
14-1. Field Names of PDF Files 14-21
14-2. Effective Values for PDF File Field Names 14-25
14-3. Printer Control Code Parameters 14-26
14-4. Printer Symbol Definitions 14-26
14-5. Supported Control Codes 14-29
14-6. Printer Control Codes 14-31
14-7. PDF File Name 14-39
14-8. Migration from the Printer Function Table to the Printer Definition File 14-39
15-1. Meanings of Field Attribute Codes 15-1
17-1. File Type Indicators 17-46
17-2. Time Formats 17-47
17-3. Time Separators 17-47
17-4. Date Formats 17-47
17-5. Date Separators 17-48
17-6. Decimal Separators 17-48
17-7. Data Type Indicators 17-49
17-8. Valid SBCS Data Types for File Types 17-49
17-9. Allowable Data Length Limits for Personal Computer SBCS Data Types 17-50
17-10. Allowable Data Length Limits for AS/400 Data Types 17-51
17-11. Binary-to-ASCII Field Length Mapping 17-58

© Copyright IBM Corp. 1989, 1996

Notices

References in this publication to IBM products, programs, or services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program or service is not intended to state or imply that only IBM's product, program, or service may be used. Subject to IBM's valid intellectual property or other legally protectable rights, any functionally equivalent product, program, or service may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, programs, or services, except those expressly designated by IBM, are the user's responsibility.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, 500 Columbus Avenue, Thornwood, NY 10594, U.S.A.

For license inquiries regarding double-byte character set (DBCS) information, contact:

IBM World Trade Asia Corporation Commercial Relations
IBM Kamiya-cho Building, 4-3-9 Toranomon, Minato-ku
Tokyo, Japan

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Site Counsel
IBM Corporation
P.O. Box 12195
3039 Cornwallis
Research Triangle Park, NC 27709-2195
USA

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement.

This document is not intended for production use and is furnished as is without any warranty of any kind, and all warranties are hereby disclaimed including the warranties of merchantability and fitness for a particular purpose.

© Copyright IBM Corp. 1989, 1996

Trademarks

The following terms are trademarks of the IBM Corporation in the United States or other countries or both:

ACF/VTAM
Advantis
Advantis Passport
AnyNet
APPN
AS/400
AT
CICS
CICS/MVS
CICS/VSE
COBOL/2
DisplayWrite
ES/9000
ExecJet
Extended Services
GDDM
IBM
IBMLink
IIN
IMS
InfoWindow
Micro Channel
MVS/ESA
NetView
OfficeVision
OfficeVision/MVS
OS/2
OS/400
Personal Computer AT
Personal System/2
Proprinter
PSF
PS/2
Quickwriter
Quietwriter
SAA
Series/1
S/390
Systems Application Architecture
ThinkPad
VM/ESA
VM/XA
VTAM
XGA
XT

Windows is a trademark of Microsoft Corporation.

PC Direct is a trademark of Ziff Communications Company and is used by IBM Corporation under license.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names, which may be denoted by a double asterisk (**), may be trademarks or service marks of others.

About This Book

This book provides information related to *Personal Communications/3270* and *Personal Communications AS/400 for Windows*. The product is available in a combined (3270 and 5250) package and a 5250-only package. In this manual, Personal Communications/3270 and PC/3270 refer to the 3270 portion of the combined package; Personal Communications AS/400 and PC400 refer to the PC400 version of the package. Throughout this book, PC (or workstation) means all supported IBM personal computers and IBM Personal System/2 (PS/2) computers. When only one model or architecture of the personal computer is referred to, only that type is specified.

Who Should Read This Book

This book is intended for the person who installs and uses Personal Communications.

How to Use This Book

This book contains reference information that you might need to refer to during installation and operation of Personal Communications.

The Personal Communications package is designed to use various communications adapters, workstations, and host systems. These packages are not fully described here. Refer to the appropriate documentation for the products you use.

Organization

This book has the following chapters:

Part 1: General Information

Chapter 1, Personal Communications Highlights describes the functions of Personal Communications.

Chapter 2, Where to Get More Information describes where to find more information on Personal Communications.

Chapter 3, Problem Determination and Reporting describes problem determination and how to report problems to IBM.

Chapter 4, Printing describes how to set up printers.

Chapter 5, Transferring Files describes how to transfer files between a host and a workstation.

Chapter 6, Modems provides information on modems.

Chapter 7, Country Codes, Code Pages, and Character Sets describes the country codes, code pages, and character sets.

Chapter 8, Keyboard Layouts describes keyboards supported by Personal Communications.

Chapter 9, Messages explains Personal Communications error messages and required user actions for the errors.

© Copyright IBM Corp. 1989, 1996

Part 2: Personal Communications/3270

Chapter 10, Building a Printer Definition Table (PDT) for PC/3270 describes how to modify or build a printer definition table for use by PC/3270.

Chapter 11, File Transfer Commands for PC/3270 describes the syntax of file transfer using PC/3270.

Chapter 12, Considerations for Installation and Use of PC/3270 Sessions provides technical information, considerations, and restrictions for PC/3270.

Part 3: Personal Communications AS/400

Chapter 13, Using Virtual Printers describes the virtual printer function.

Chapter 14, Building a Printer Definition Table (PDT) for PC400 describes how to modify or build a printer definition table for use by PC400.

Chapter 15, Field Attribute Codes describes the field attribute codes.

Chapter 16, AS/400 Utilities describes the use of the AS/400 utilities.

Chapter 17, Data Transfer for PC400 describes the use of data transfer using PC400.

Chapter 18, File Transfer for PC400 describes the syntax of file transfer using PC400.

Chapter 19, ODBC Driver for PC400 Database Access describes how to access AS/400 data through the ODBC driver.

Chapter 20, Considerations for Installation and Use of PC400 Sessions provides technical information, considerations, and restrictions for PC400.

This book also contains a glossary and an index.

Highlighting Conventions

This book uses the following highlighting conventions:

UPPERCASE	Uppercase type indicates DOS and host programs, commands, and options.
Bold	Bold type indicates items you can select, like the names of buttons, options, checkboxes, menus, commands, and keytops.
Bold Monospace	Bold monospace type indicates text that you enter to accomplish the actions stated for the example. Lowercase bold monospace used in example text generally indicates a variable. On example screens, bold monospace type indicates the literal text displayed. Bold monospace is also used for file and directory names.
Monospace	Monospace type is used for examples.
Italics	Italic type indicates a reference citation or a term that is defined in the immediate context of its use. It also indicates variables for placeholders, parameters, and file names. When you enter a command, replace all variables with the appropriate file name, number, or option. On an example

display screen, italic type indicates a variable quantity other than a default value.

Bold Italics Bold italic type is used for emphasis.

Command Syntax Special Characters

In this book, special characters used in showing the command syntax have the following meanings or uses:

( ) Parentheses enclose operands that govern the action of certain command options. Type the parentheses as part of the command.

[ ] Brackets indicate an optional command argument. If you do not use the optional item, the program selects a default action.

... Ellipsis after an argument indicates that you can repeat the preceding item any number of times. Do not type the ellipsis.

[ ] Brackets are used to enclose function names. Less-than and greater-than signs are used to indicate optional items.

/ A slash must precede the TSO (host time share option) password. A slash must also precede parameters of PC DOS commands entered from the command line.

\ A backslash is included as part of any DOS directory name. An initial backslash indicates the first-level directory and an additional backslash is inserted in the directory name to indicate another level.

All directives, operands, and other syntax are typed in uppercase or lowercase, unless otherwise indicated.

Related Publications

Although it is assumed that you are familiar with the operation of the workstation and the related languages, you might want to refer to the following publications. Ask your IBM representative for ordering information.

IBM Personal Communications Version 4.1 Up and Running for Windows

IBM Personal Communications Version 4.1 Programmer's Guide for Windows

Microsoft Windows User's Guide

IBM Personal System/2 National Language Supplement

IBM PC DOS User's Guide, Version 3.30 and 4.01

IBM PC 3270 Emulation Program, Version 3.00, Systems Planner and User's Reference

IBM 3270 Information Display System: IBM 3274 Control Unit Description and Programmer's Guide

IBM 3270 Information Display System: Data Stream Programmer's Reference

IBM 3270 Information Display System: Reference Summary

IBM Local Area Network Technical Reference

IBM PC Network Technical Reference

General Information

© Copyright IBM Corp. 1989, 1996

Chapter 1. Personal Communications Highlights

Personal Communications provides the following functions and features:

Attachment type

Personal Communications supports a wide range of attachments for connecting to host systems.

- **System/390 Connections**

LAN	LAN via IEEE 802.2
	LAN via 3270 Emulation Gateway
	LAN via NetWare** for SAA
	Telnet3270
	Windows NT – SNA Client
	AnyNet
	LAN via AS/400
	APPC3270 via LAN
COAX	SNA Distributed Function Terminal
	Non-SNA Distributed Function Terminal
	Control Unit Terminal (CUT)
	3174 Peer Communication
COM port	Hayes** AutoSync
	SNA-over-Async
	IBM Global Network Connection
	Home3270
	Advantis (IIN)
SDLC	Synchronous Data Link Control
	3270 via AS/400 (passthru)
	APPC3270 via SDLC
5250	TDLC via AS/400 (passthru)

- **AS/400 Connections**

LAN	LAN via IEEE 802.2
	PC Support/400 Router
	Telnet5250
	AnyNet
	NS Windows

© Copyright IBM Corp. 1989, 1996

SDLC	Synchronous Data Link Control
	PC Support/400 Router
	NS Windows
5250	Twinaxial Data Link Control (APPC)
	Twinaxial Data Link Control (Console)
	PC Support/400 Router
	NS Windows
COM port	SNA-over-ASYNC
	SNA-over-ASYNC (TSR)
	SNA-over-Async (Console)
	Hayes AutoSync
	NS Windows

– **System/3X Connections**

5250	Twinaxial Data Link Control (CUT)

Installation and Configuration

- Partial installation option
- Removal of Personal Communications already installed
- Program sharing on a network server
- Configuration free start of DFT connection
- Automatic detection of installed communication adapters
- Dynamic change of communication configurations
- Automatic-dial function for Asynchronous and SDLC

Host Session Function

- Up to 26 3270 sessions
- Up to 16 5250 sessions
- Variable screen size and automatic font scaling
- Host code page setup for each session
- Selectable host code page and keyboard layout for each session

Graphics Function

- Built-in GDDM Graphics in 3270 sessions (OS2-LINK protocol)
- Native Graphics (GOCA protocol)
- Vector Graphics (GOCA protocol)
- Programmed Symbols

File Transfer Function

- Easy operation through windows
- Batch transfer of multiple files
- Concurrent file transfer through multiple sessions
- OfficeVision/MVS Import/Export functions in 3270 sessions
- File transfer invocation by macro
- DOS-compatible file transfer from Windows DOS prompt
- Data transfer (APVAFILE)

Edit (Cut and Paste)

You can use the Windows clipboard to cut, copy, and paste a selected area. In addition, you can paste data in other Windows applications, such as spreadsheet programs, that support the PasteLink function.

- Support of spreadsheet data format (Sylk, Biff3, Wk3 formats)
- Copy Append
- Paste Next
- Paste to Trim Rectangle
- Paste Stop at Protected Line

Graphical User Interface

- Customizable 3D iconic tool bar
- 3D hotspots
- Pop-up keypad
- Macro function, including record and play
- Keyboard function setup
- Mouse button function setup
- Display color setup
- Automatic font size adjustment
- Fixed font size function
- Display and window appearance setup
- Menu-bar customization
- Online help

Print Function

- Multiple host print
- Printing with Windows printer drivers
- Printing with printer definitions tables (PDTs)
- PC400 Print function by OS/400 Host Print Transform (HPT)
- PFT to PDT conversion tool

Display Function (PC400 only)

- Text assist feature
- Enhanced non-programmable terminal user interface (ENPTUI)
- PC Organizer

Administration Tools

- Menu Bar Customization Utility
- Configuration and Program Options (PCSSETUP)
- Maintenance Aid
- Trace Capture Program (PCSMON)
- LAN Adapter Status Reporter (TOKSTAT)
- Trace Setup Utility (PCSTRSET)

Programming Interface

- EHLLAPI
- DDE
- Personal Communications API (PCSAPI)
- Server-Requester Programming Interface (SRPI) (PC/3270 only)

Highlights

Client Functions (PC400 only)

- Shared Folders
- Data Transfer
- Virtual Printers
- ODBC (Open Data Base Connectivity)

Programming Tool

- Personal Communications Toolkit for Visual Basic

Chapter 2. Where to Get More Information

This chapter discusses getting help when you are installing, configuring, or using Personal Communications.

Online Help

The online help describes how to install, configure, and use Personal Communications, but it does not provide all the details about every function. The online help includes information about all aspects of configuring and using Personal Communications.

Use help to obtain the following information:

- Menu command contents
- Operation procedures
- Operations in windows
- Meanings of the terms displayed in windows
- Causes of errors and the corresponding actions to take
- Mouse-based operations
- Operation without a mouse
- Detailed explanations of specific terms
- Further technical information about Personal Communications

How to Use Online Help

To display online help, click on the Help menu or the **Help** button on the tool bar.

Personal Communications online help can be used in the same way as that for Microsoft Windows. Refer to the Microsoft Windows documentation for details.

Messages

This section describes the Personal Communications online messages. Online messages are displayed during Personal Communications sessions. A message does not always mean an error occurred. For example, a message might tell you that an operation is in progress or has been completed. A message can also prompt you to wait for the completion of an operation.

Detailed descriptions of the Personal Communications messages are available in Chapter 9, “Messages” on page 9-1 or in the online help.

OIA Messages

These messages are displayed in the operator information area (OIA) or in the message window. Messages from Personal Communications are displayed in the message window; messages from the host system are displayed in the OIA of the session window.

The bottom line of the session window is the OIA. The OIA indicator indicates the status of Personal Communications as well as information about the workstation, host system, and attachment.

© Copyright IBM Corp. 1989, 1996

All of the OIA messages are described in the online help. To view this information:

1. Select **Index** from the Help menu.
2. When the help window appears, double-click on **When You Encounter A Problem**.
3. Select choices from the list of hypertext links.

See Up and Running for specific information on the OIA indicators and reminders.

Personal Communications Library

The Personal Communications library includes the following publications:

Personal Communications AS/400 and 3270 for Windows Version 4.1 Up and Running

Personal Communications AS/400 and 3270 for Windows Version 4.1 Reference

Personal Communications for Windows and DOS (Full-Function Mode) Version 4.1 Programmer's Guide

Chapter 3. Problem Determination and Reporting

This chapter describes the information that will help you to solve a problem yourself, to recognize a problem accurately before reporting it to your system administrator, or to report a problem to IBM.

These are the processes that you should follow:

1. Problem determination (PD)
2. Problem-source identification (PSI)
3. Problem reporting (PR)

Problem Determination (PD)

Problem determination (PD) is the first stage in solving your problem.

Symptoms

Recognize the differences between what you expect to see and what you do see.

Environment

Recognize the environment in which the problem occurs:

Personal Communications configuration

- Personal Communications version and CSD level
- The name of the workstation profile

Workstation configuration

- The machine type and model, the system memory, the video adapter
- The communication adapter you are using
- Other adapters (especially communication adapters) installed
- The printer type and model
- Other devices installed, such as sound cards, modems, or fax machines

Software configuration

- Windows version (Windows 3.1, Windows NT 3.5, or Windows for Workgroup 3.11) and level
- Communication device-driver version and level
- Other communication programs (such as LSP, Netware, or Microsoft Data Link Control) that are running and using resources
- Printer driver version and level.

Host configuration

- The upstream host connection and configuration

Problem Type

Categorize your problem into one of the following types:

1. **Installation Problem**. Note the error message and take the required action by consulting Chapter 9.
2. **Configuration or Setup Problem**. If Personal Communications did not connect to the host (that is, if the host screen did not appear) verify that your

© Copyright IBM Corp. 1989, 1996

hardware, software, and Personal Communications configurations are correctly set up for your host environment. To help you to isolate what is wrong, look up any OIA messages in the online helps, or any error messages in Chapter 9 or in the online help. You might also need to ask your system administrator to verify that your Personal Communications setup values are correctly configured for your host system.

3. **Operational Problem**. Although you were able to connect to the host, you might have difficulty in doing some operations or in using a certain Personal Communications function. Look up any OIA messages in the online helps, or any error messages in Chapter 9, and study the help and *Up and Running* to see how the operation should be performed.

Problem Area

You also need to identify where the problem is:

1. Installation and configuration
2. Printer
3. API
4. Other Personal Communications functional area

Problem Re-Creation

As the final step of the problem determination process, try to re-create the problem; the problem-re-creation procedure and the probability of the recurrence of the problem are key factors in isolating it. If the problem is intermittent, any factor that you think is related to it becomes important information.

Problem-Source Identification (PSI)

The second stage is to try to identify the real cause of the problem; this depends largely on the problem area:

1. **Installation and Configuration**. Make sure that your workstation hardware and software are configured correctly. You might also need to contact your system administrator to verify that your Personal Communications setup values are correct for your host system.
2. **Printer**. Identify the operation you are having the problem with:

   Local print
   Host-directed print (LU 1)
   Host-directed print (LU 2)
   Host-directed print (LU 3)
   Host-directed print (non-SNA)

   Also identify which printer mode you are using:

   PDT mode: Personal Communications-proprietary printer-driver mode
   PD mode: Windows printer-driver mode

   Then check that you have installed the correct printer driver and make sure that you have configured the driver appropriately. If you are using PDT mode, check the content of your PDF file, especially if you have customized it. Depending on the problem you are having, you might need to run a link-line trace as described in the Administration Tools online help.
3. **API**. The cause could be in an application that uses an API, or the problem could be in Personal Communications. Identify which of these is causing the

problem. The API trace, described in the Administration Tools online help, might also help you to identify the source of the problem.

4. **Other Personal Communications Functional Area**. Make sure that you can explain why you think that the source of the problem is in Personal Communications.

Problem Reporting (PR)

If your problem still persists even at this stage, and if you think that the source is in Personal Communications, report the problem to IBM.

When you do this, you need to provide the information you obtained through the problem determination (PD) and problem-source identification (PSI) processes:

1. PD information includes:

   Symptoms
   Environment
   Type of problem
   Problem area
   Problem re-creatability and re-creation procedure

2. PSI information includes:

   OIA messages or error messages (if any)

   Key factors related to the problem

   PCSUSER.INF

   PCSMON trace

   Printer trace (if the problem is printer-related)

   API trace if the problem is API-related (See the Administration Tools online help for more details.)

   PCSDIAL.LOG if the problem occurred while dialing. This log can be created by re-creating the problem after adding "-p" following parameter **Adffilename=** in the workstation profile.

   PDF file (for printer problems in PDT mode)

   Spool file (for printer problems)

Contacting IBM

This section lists a number of ways you can reach IBM for various reasons. Depending on the nature of your problem or concern, we will ask you to be prepared to provide us with some information to allow us to serve you better.

If you have a technical problem, please take the time to review and carry out the actions suggested by the online helps and the License Information booklet. Use your local support personnel before contacting IBM. Only persons with in-depth knowledge of the problem should contact IBM; therefore, support personnel should act as the interface with IBM.

If you determine that you need to contact IBM, refer to your License Information booklet for a detailed description of the services IBM provides. This booklet also contains information on how to contact IBM.

Other Ways to Contact IBM

Information about Personal Communications is available from the following sources:

The PCOMM CFORUM

This forum is monitored by Personal Communications Development.

- In the U.S., access the PCOMM CFORUM on the OS2BBS bulletin board via TalkLink.

  If you do not have access to TalkLink/OS2BBS, call 1-800-547-1283 (U.S.A. only). TalkLink administration personnel will send you a registration package that lists the available features and the current subscription rates. You should receive the registration package approximately 2 weeks after calling. Return the necessary documents and TalkLink administration personnel will send you a welcome package that contains the software you need to access TalkLink/OS2BBS.

  IBMLink* customers can register via SMARTLink's new TalkLink selection.

- In Canada, access the PCOMM CFORUM via IBMLink.
- In Australia, to access the PCOMM CFORUM:

  1. Type NEWMENU to access the pilot menus.
  2. Select FORUMS.

- In Europe, the Middle East, and Africa, use DIAL-IBM to access the PCOMM CFORUM via the CONFER application on OS2BBS.

  If you do not have access to OS2BBS, contact your country DIAL-IBM help desk.

Internet

IBM Personal Software Services has a home page on the Internet which has general product information as well as service information about APAR fixes. Using an Internet browser, go to the following URL: http://ps.software.ibm.com/

IBM Networking Software has a home page on the Internet that also has general product information and service information. Using an Internet browser, go to the following URL: http://www.raleigh.ibm.com/

IBM Personal Communications Online Customer Support

Access this electronic bulletin board to view information APARs and to obtain APAR fixes. To request that an APAR fix be made available, call 1-800-992-4777 (U.S.A. only).

To access the electronic bulletin board:

- Dial 919-543-8200 (country code: 001 from outside the U.S.A.).
- Use protocol N81.
- Follow the instructions. Entering your first name and last name registers you the first time you use the facility.

The IBM Software Solutions Center

From the U.S.A., call 800-992-4777. From Canada, call 800-465-2222.
Outside the U.S.A., call IBM International Information at 800-426-1774.

Problem Determination and Reporting

Chapter 4. Printing

You can use Personal Communications to print from display or printer sessions.

From display sessions, you can print all (**Print Screen**) or part (**Trim Print**) of the screen of your session window on a workstation printer.

From printer sessions, you can direct printing from an S/390, AS/400, or S/3X system to a workstation printer.

Configure a printer session to designate a workstation printer as a system printer that will use either the printer definition tables (PDTs) provided with Personal Communications or the Windows printer drivers.

Use PDT files for Personal Communications to print files based on printer control information, such as control codes and the printer output format, defined in the PDT.

Use Windows printer drivers for Personal Communications to print files based on printer setup parameters, such as scaling, duplex options, and page orientation, that you define in **Printer Setup**.

When you configure a printer session, refer to the online help for detailed information for each parameter.

From a PC/3270 session, you can also use the ZipPrint utility provided in the Productivity Tools folder to print PROFS or OfficeVision (OV) notes, calendars, documents, CMS files, XEDIT workspaces, and host session screens. See the online help for more information.

For considerations and restrictions on printing, refer to Chapter 12 and Chapter 20.

Setting Up the Printer

Following is a description of how to set up the printer that you want to use, with either a Windows printer driver or a PDT file.

For an explanation of how to customize a PDT, refer to Chapter 10 (for PC/3270) and Chapter 14 (for PC400).

Defining the Windows Printer for a Session

To choose or change the printer to be used, follow these steps:

1. Select **File - Printer Setup** from the menu bar of the session window.

   The Printer Setup window lists the available printers.

2. Select the printer driver to be used from the *Printer* list box.
3. Confirm that **Use PDT file** is not selected.
4. Select **OK**.

   Once the printer to be used has been changed, the **Printer Setup** window is closed.

© Copyright IBM Corp. 1989, 1996

Using PDT Files

To use PDT files:

1. Select **File - Printer Setup** from the menu bar of the session window.

   The *Printer Setup* window appears.

2. Select the port to be used from the *Printer* list box.

   Selected PDT files are available for the port selected here.

3. Select **Setup** button; specify the paper size of the selected printer driver.

4. Select the **Use PDT file** check box; then select **Select PDT**.

   The *Select PDT file* window appears.

5. To use the existing PDT file, select a PDT file to be used; then select **OK**.

   To use a PDF file converted to a PDT file:

   a. Select **Convert PDF**.

   b. Select a PDF file to be converted from the list in the *Convert PDF to PDT* window; then select **Convert**.

      The *PDF File Converter* window displays the result of PDF conversion. If there are any errors during the conversion, they are listed in the window.

   c. When you select **Save List**, the window list is saved in **.LST** file in the **PDFPDT** subdirectory.

      To close without saving the list, select **Close**.

      After the file is converted, control returns to the *Select PDT file* window and the converted PDT file appears in the list.

   d. Select the PDT file; then select **OK**.

6. Select **OK** in the *Printer Setup* window.

   After the printer is set, the *Printer Setup* window is closed.

PDT Files

PDT files define the transfer of characters and control codes to a printer, and the printer output format. If the printer definition table (PDT) file is used, the Windows printer driver is not used. Instead, Personal Communications generates print outputs based on printer control information defined in the PDT file.

If the **Use PDT file** option is used, the PDT file to be used at printing can be selected.

The PDT files provided by Personal Communications and the corresponding printers are as shown in the following table:

PDT Name	Printer Name/Model
IBM3812.PDT	IBM 3812 Page Printer, Model 2
IBM3816.PDT	IBM 3816 Page Printer II
IBM38521.PDT	IBM 3852 Color Printer
IBM38522.PDT	IBM 3852 Color Jetprinter, Model 2

PDT Name	Printer Name/Model
IBM4019.PDT	IBM 4019 LaserPrinter IBM 4019 LaserPrinter E IBM 4029 LaserPrinter
IBM4070.PDT[1]	IBM 4070 IJ
IBM4070E.PDT[1]	IBM 4070 IJ - Epson Mode
IBM4212.PDT	IBM 4212 Pro Printer
IBM4072.PDT	IBM 4072 ExecJet Printer
IBM4201.PDT	IBM 4201 Proprinter IBM 4201 Proprinter II IBM 4201 Proprinter III, Model 3 IBM 2381 Personal Printer Series 2
IBM4202.PDT	IBM 4202 Proprinter XL, Model 1 IBM 4202 Proprinter XL, Model 2 IBM 4202 Proprinter III XL, Model 3 IBM 4216 Personal Pageprinter IBM 2380 Personal Printer Series
IBM4207.PDT	IBM 4207 Proprinter XL24 IBM 4207 Proprinter XL24E IBM 2390 Personal Printer Series 2
IBM4208.PDT	IBM 4208 Proprinter X24 IBM 4208 Proprinter X24E IBM 2391 Personal Printer Series 2
IBM4226.PDT[1]	IBM 4226-302 Printer
IBM5152.PDT	IBM 5152 Graphics Printer, Model 2
IBM5182.PDT	IBM 5182 Color Printer
IBM5201.PDT	IBM 5201 Quietwriter Printer, Model 1 IBM 5201 Quietwriter Printer, Model 2
IBM5202.PDT	IBM 5202 Quietwriter III IBM 5204 Quickwriter Printer
IBM5216.PDT	IBM 5216 Wheelprinter
IBM5223.PDT	IBM 5223 Wheelprinter E
CPQPM20.PDT[1]	Compaq PageMarq 15 - HP Mode Compaq PageMarq 20 - HP Mode
ACTLZR2.PDT	Epson Action Laser2 LQ2500 mode
EAP2250.PDT	Epson AP2250
EAP3250.PDT[1]	Epson AP3250
EAP5500.PDT[1]	Epson AP5000 Epson AP5500
EFX1170.PDT[1]	Epson FX1170
EFX5000.PDT[1]	Epson DFX5000 Epson DFX8000
EFX850.PDT[1]	Epson FX850
ELQ1070.PDT[1]	Epson LQ570 Epson LQ1070
ELQ2550.PDT[1]	Epson LQ2550

PDT Name	Printer Name/Model
ELQ510.PDT[1]	Epson LQ510
ELQ860.PDT[1]	Epson LQ860
ELX810.PDT[1]	Epson LX810
EPLPCL4.PDT[1]	Epson EPL7000 - HP Mode
EPLPCL5.PDT[1]	Epson EPL8000 - HP Mode
ESQ1170.PDT[1]	Epson SQ1170
LQ870.PDT	Epson LQ870/1170
HPLJII.PDT	HP LaserJet Series II
HPLJIII.PDT[1]	HP LaserJet Series III HP LaserJet Series IIIP HP LaserJet Series IIISi
HPLJIIID.PDT[1]	HP LaserJet Series IIID IBM 4039 LaserPrinter - HP Mode
HPLJ4.PDT[1]	HP LaserJet 4
HPDJ550C.PDT[1]	HP Desk Jet 550C
HPDSKJT.PDT[1]	HP Desk Jet 500
BJ300.PDT	CANON BJ300 CAPSL mode
LBP4.PDT	CANON LBP4 ISO mode
NEC6300.PDT[1]	NEC P6200 Pinwriter NEC P6300 Pinwriter
PANLBP4.PDT[1]	Panasonic KX-P4410 - HP Mode Panasonic KX-P4420 - HP Mode Panasonic KX-P4450i - HP Mode
PANLBP5.PDT[1]	Panasonic KX-P4430 - HP Mode Panasonic KX-P4451 - HP Mode
PAN1123.PDT[1]	Panasonic KX-P1123 - Epson Mode
PAN1124.PDT[1]	Panasonic KX-P1124 - Epson Mode Panasonic KX-P1624 - Epson Mode
PAN1180.PDT[1]	Panasonic KX-P1180 - Epson Mode Panasonic KX-P1180i - Epson Mode Panasonic KX-P1191 - Epson Mode
PAN1695.PDT[1]	Panasonic KX-P1695 - Epson Mode
PAN2123.PDT[1]	Panasonic KX-P2123 - Epson Mode
PAN2124.PDT[1]	Panasonic KX-P2124 - Epson Mode
PAN2180.PDT[1]	Panasonic KX-P2180 - Epson Mode
PAN2624.PDT[1]	Panasonic KX-P1124i - Epson Mode Panasonic KX-P1654 - Epson Mode Panasonic KX-P2624 - Epson Mode
1: For 5250 sessions only.	

When the PDT files for the printer being used do not exist, users can create their own PDT files. To create PDT files, first create printer definition (PDF) files and convert them into PDT files. PDF files are saved in the **PDFPDT** directory under the directory Personal Communications has been installed.

PFT Migration

You can migrate a PC Support/400 Workstation Feature (PFT) to a PDF for PC400. Refer to “PFT Migration Utility” on page 14-38 for more information.

Setting Printer Control Parameters (Windows Driver Only)

You can set Printer Control parameters, such as the maximum number of lines per page, the maximum number of columns, and fonts. These parameters are initially set to the defaults. Therefore, you can perform printing by selecting the printer used for Print Screen. Use this function to change specific control items.

Note: When a PDT file is used, this function cannot be used.

You can set the following parameters.

Table 4-1. Print Control Parameters (Text)

Parameter	Description
CPI	Specifies the number of characters to be printed per inch. If CPI was not set previously, a CPI value suitable for the font selected from the *Font* list box is assumed as the default.
LPI	Specifies the number of lines to be printed per inch. If LPI was not set previously, an LPI value suitable for the font selected from the *Font* list box is assumed as the default.
Maximum Number of Lines Per Page	Specifies the maximum number of lines per page. A number 1–255 can be specified. The default is **66**.
Maximum Number of Columns to be Printed	Specifies the maximum number of characters per line. A number 1–255 can be specified. The default is **132**.
Font	Lists, in the list box, the fonts that can be used with the currently selected printer. The fonts in brackets [ ] are device fonts specific to the printer driver. The other fonts are graphics display interface (GDI) fonts printed in bit map formats.
Print Options	The options listed in the following table can be selected as print options. These options are not available for the printer session.

When you use a PC/3270 or PC400 display session, you can set additional parameters by selecting the **Options** button, as follows:

Table 4-2 (Page 1 of 2). Print-Control Options

Option	Item to be set
Suppress null lines	Determines whether to delete lines containing only null or non print characters (null or non print field characters, and field attributes) or to print them as null lines. **Selected** Null lines are not printed. **Not selected** Null lines are printed. This option can be used when: The **Print Screen** command is selected LU type 3 printing, or non-SNA HAP printing is done The combination of bits 2 and 3 of WCC is not 00.
Print nulls as spaces	Determines whether to print NULL control codes as null characters. **Selected** The codes are printed as null characters. **Not selected** The codes are not printed as null characters. This option can be used when: The **Print Screen** command is selected LU type 1 or 3 printing, or non-SNA HAP printing is done.
Suppress auto new line when:	**CR at maximum print position +1** Determines whether to perform automatic new line when CR is the maximum number of columns to be printed away from the first column. **Selected** Automatic new line is not done. The characters after the CR code are printed on the same line. **Not selected** Automatic new line is done. **NL at maximum print position +1** Determines whether to perform automatic new line/carriage return before new line/carriage return (NL) is done when NL is the maximum number of columns to be printed away from the first column. **Selected** Automatic new line/carriage return is not done. **Not selected** After automatic new line/carriage return is done, new line/carriage return is done again. This option can be used when LU type 3 printing or non-SNA direct printing is done and the combination of bits 2 and 3 of WCC is 00. This option cannot be used in 5250 sessions.
Ignore FF when at first print position	Determines whether to ignore the FF code at the beginning of the buffer address. **Selected** The FF code is ignored and not executed. **Not selected** The FF code is executed. This option can be used when: The **Print Screen** command is selected LU type 1 printing, LU type 3 printing, or non-SNA HAP printing is done.

Table 4-2 (Page 2 of 2). Print-Control Options

Option	Item to be set
FF takes a print position if followed by data	Determines whether to print null characters if data follows the FF code. **Selected** FF is executed, and null characters are printed at the beginning of the next page. Therefore, the next data is printed in the second column of the line. **Not selected** The FF code is not executed. Therefore, the next data is printed at the beginning of the first line on the next page. This option can be used when: The **Print Screen** command is selected Host initiated local copy, LU type 1 and LU type 3 printing, or non-SNA direct printing is done. This option cannot be used in 5250 sessions.

When you use a PC400 printer session, you can set additional parameters by selecting the **Options** button, as follows.

Table 4-3. Print Control (PC400 only)

Parameter	Description
Page Orientation	Allows you to change default page orientation to specify how to print a document on the workstation printer. If the orientation is explicitly set by AS/400 printer control code, the explicit orientation is used. The options are listed in the following table.

Table 4-4 (Page 1 of 2). Page Control (PC400 only)

Option	Item to be set
Drawer 1 orientation[1]	The default page orientation for the paper from drawer 1. **Computer output reduction** If selected, the document is printed in landscape. The font, pitch, and margins are set to appropriate values to fit on a page. **Portrait** If selected, the document is printed in portrait. **Landscape** If selected, the document is printed in landscape.
Drawer 2 orientation[1]	The default page orientation for the paper from drawer 2. **Computer output reduction** If selected, the document is printed in landscape. The font, pitch, and margins are set to appropriate values to fit on a page. **Portrait** If selected, the document is printed in portrait. **Landscape** If selected, the document is printed in landscape.

Table 4-4 (Page 2 of 2). Page Control (PC400 only)

Option	Item to be set
Automatic Page Orientation[1]	Determines whether to calculate the page orientation when the page orientation is currently **Default**. **Selected** The page orientation is calculated as follows: 1. If the output exceeds the current page size, **Drawer 1 orientation** or **Drawer 2 orientation** is used. 2. If the output fits the current page size, the dimensions are compared. If the shorter dimension is specified as depth; then **Landscape** is used, otherwise **Portrait** is used. **Not selected** **Drawer 1 orientation** or **Drawer 2 orientation** option is used.
Timeout Value	Specifies the time value for the automatic termination of a print job. A number for 0 to 255 seconds can be specified: 0 means No Automatic Termination. The default value is 60 seconds. This option is effective only for a System/36 session.

1: This option is available only for PC400 or System/36 5219 sessions.

Table 4-5. Print Control Parameters (Graphics)

Parameter	Description
Scaling	The screen image is printed with the resolution that is calculated as the actual screen resolution multiplied by the following parameters. **x1** Same resolution as screen **x2** Double the resolution in each dimension **x3** Triple the resolution in each dimension **x4** Four times the resolution in each dimension
Black-on-White	This option allows you to determine how the black pixels on the screen are printed. **Yes** Black pixels are printed as while pixels. Pixels other than black are printed as black pixels when you use a monochrome printer. When you use a color printer, they are printed in the same color as on the screen. **No** Black pixels are printed in black. Pixels other than black are printed as white pixels when you use a monochrome printer. When you use a color printer, they are printed in the same color as on the screen.

Setting Printer Control Items (Windows Driver Only)

To set or change control items:

1. Select **File - Printer Control** from the menu bar of the session window.
2. Select **Text** or **Graphics**.

   The Printer Control window appears.
3. Change the items to be set by referring to Table 4-1 on page 4-5, Table 4-2 on page 4-6, or Table 4-5.

To switch from the current settings back to the defaults, select **Default**.

4. If PC400, when you use the printer session, the **Advanced** button is displayed at the bottom right of the screen.

   If you want to set up the following items, select **Advanced**. The Printer Control window appears.

5. Set each option by referring to Table 4-3 on page 4-7 and Table 4-4 on page 4-7.
6. When all the items have been set, select **OK**.

   The Printer Control window closes.

Printing to Disk

You can save a host print-job or the contents of the session window (Print Screen) to a PC file instead of printing it.

Two types of Print-to-Disk functions are provided by Personal Communications:

Print-to-Disk Append:

Appends multiple host print jobs or print screen jobs to single PC file.

Print-to-Disk Separate:

Saves separately each host print job or screen to a single PC file. You can specify a PC file name, however, the extension of the file name is automatically assigned as a decimal number from 000 to 999 in ascending order.

Notes:

1. Print-to-Disk is not available for the Print-Graphics function.
2. Print-to-Disk can be used only when you select to use printer definition table (PDT) file.

To set up Print-to-Disk:

1. Select **File - Printer Setup** from the menu bar in the session window.

   The *Printer Setup* window lists the supported printers.

2. Select **Print to Disk - Append** or **Print to Disk - Separate** from the list box and check the option **Use PDT file**.
3. Push the **Select PDT** button.

   The *Select PDT File* window appears.

4. Select a PDT file from the list; then push the **OK** button.

   The *Printer Setup* window re-appears.

5. Select **Setup** button.

   The *Print to Disk* window appears.

6. Specify a file name (without an extension when **Print to Disk - Separate**), drive, and path; select **OK**. The printed contents are saved to the specified file.

   Note: When you specify the name of an existing file, subsequent print jobs are appended to the data in the original file.

Printing

Chapter 5. Transferring Files

Personal Communications File Transfer enables one or more files to be transferred between a host system and workstation at the same time. Transfer types and translation tables can be defined in advance.

5250 File Transfer Transfer is quite different from the PC400 function, Data Transfer, which is described in Chapter 17. The main differences are listed here:

Type of Transfer	Products required on an AS/400 system	Access Method	Sending and receiving unit	Type of connection to an AS/400 system
File Transfer	Personal Communications Tools (APVAFILE)	Transfer menu in session window	Entire file	Display session
Data Transfer	PC Support/400 V2R2 or V2R3 or OS/400 V3R1 or later[1]	AS/400 Utilities or the Data Transfer Function choice on the Transfer menu	Field, record, or file in a database	No display or printer session required
Note 1: OS/400 provides the host transaction program for Data Transfer.				

Note

When you first configure a PC400 session, the Transfer menu and the corresponding tool bar icons let you do **file** transfer as defined in the preceding table. You can change the function to **data** transfer by selecting **Data Transfer Function** from the Transfer → Setup menu.

Host Requirements

Before you can send or receive files, one of the following file transfer programs must be installed on the host system:

IBM 3270-PC File Transfer Program, 5665-311 (MVS/TSO)
IBM 3270-PC File Transfer Program, 5664-281 (VM/SP)
IBM 3270-PC File Transfer Program, 5798-DQH (CICS/MVS)
Personal Communications Tools Program Package (APVAFILE)
- 1/4-inch tape 85G9969
- 1/2-inch tape 85G9973
- 8-mm tape 46H8353

With Personal Communications, you can perform the following file transfer functions:

Send files to the host system
Receive files from the host system

© Copyright IBM Corp. 1989, 1996

Use list files
Create a template
Import or export files (PC/3270 only)
Define transfer types
Set transfer options
Set translation tables
Create interactive document profile (IDP) files (PC/3270 only)

Sending Files to the Host System

To send a file from your workstation to the host system:

1. Sign on to the host system.
2. Select **Transfer** from the menu bar of the session window.
3. Select **Send File To Host**. (You can also select the Send button on the tool bar.)

   The Send File To Host window appears.



4. Specify the name of the PC file to be sent to the host system. Select the name from the list box or enter the file name in the **PC File** text box.
5. Enter a host file name assigned after the transfer; then select the transfer type.

   If a template is provided, the host file name and the generated transfer types appear automatically.

   Using List Files

   Select **Open List-File**; then select the list to be used for transfer. For the details of how to create list files, see page 5-4.

   Easy Mouse Operation

   Move the cursor to the name of the file to be transferred in the **PC File** list box. Double-click the left mouse button. Your workstation automatically starts transferring the selected file to the host system. At the same time, the host file name and transfer type are automatically assigned by means of a template.

6. Select **Send**.

   The file is sent to the host system. The send status appears in the Send a File Status window. After the file has been sent, the session window appears.

Receiving Files from the Host System

To transfer a file from the host system to your workstation:

1. Sign on to the host system.
2. Select **Transfer** from the session window menu bar.
3. Select **Receive File From Host**. (You can also select the Receive button from the tool bar.)

   The Receive File From Host window appears.



4. Specify the name of the host file to be transferred. Enter the name in the **Host File** text box, or specify it as follows:

   Using the Paste button

   Select **Paste** after copying the host file names into the Windows clipboard displays the file name in the **Host File Names** list. Select the desired file from the list.

   Using the Load button

   If a Windows application program that uses dynamic data exchange (DDE) is designed to provide file lists to the workstation, the program can be used for loading the file lists. Select **Load**; then select the desired file from the file list provided by the application program.

5. Enter a PC file name assigned after the transfer in the text box, and select the transfer type.

   Using List Files

   Select **Open List-File**, and select the list to be used for transfer. (For an explanation of how to create list files, see page 5-4.)

   If a template is provided, the PC file name and the generated transfer type appear automatically.

6. Select **Receive**.

   The file is received. The receive status appears in the **Receive a File Status** box. After the file has been received, the session window appears.

Using List Files

If the same files are transmitted frequently, the file list can be saved to a send/receive list file for reuse.

A list file is common to both transmission and reception. The default list file extension is .SRL. (To change the extension, see page 5-10.)

Creating List Files

To create a list file:

1. Select **Transfer** from the menu bar of the session window.
2. Select **Send File To Host** or **Receive File From Host** .

   The Send File to Host or Receive File from Host window appears.
3. Select a file to be transferred from the **Host File Name** or **PC File Name** list box using either of the following two methods:

   Move the mouse cursor to the name of a file to be selected. While holding down the Ctrl key, click the left mouse button.

   Move the mouse cursor to the name of a file to be selected, then drag the mouse.

   Information on the selected file appears in the lower part of the window.
4. After all desired files have been selected, select **Save List**.

   The Save File-Transfer List File As window appears.
5. Enter a list name, and select **OK**.

   The list file is saved, and the window is closed.

Editing Lists

To edit the contents of a previously created list:

1. As explained on page 5-4, display the Send File to Host or Receive File from Host window.
2. Select **Open List-File**.

   The Open File-Transfer List File window appears.
3. Select the name corresponding to the list file to be edited; then select **OK**.
4. The contents of the selected list appear in the *Send File to Host* or Receive File From Host window.
5. Edit the contents of the list file.

   Changing the contents of a list

   Select a file to be changed from the list, and overwrite the items to be changed in the text box.

   Deleting a file from the list

   Select a file to be deleted, and select **Delete from List**.

   Adding a file to the list

   Select a file to be added from the list of host or PC files.

   Enter the name of the file to be added in the text box.

6. After the contents are edited, select **Save List**.

   The Save File-Transfer List File As window appears.

7. Enter a list name and then select **OK**.

   The list file is saved and the window is closed.

Creating a Template

A *template* is a rule used by the workstation to automatically generate a PC or host file name and transfer type when a file to be sent or received is selected.

Up to 32 templates can be created. They are automatically numbered, from 1 to 32.

When the user specifies a file to be transferred, the workstation retrieves the templates, starting from template 1. It uses the first matched template to generate a name for the transferred file.

To use a template:

1. Select **Transfer** from the menu bar of the session window.
2. Select **Send File To Host** or **Receive File From Host**.

   The Send File to Host or Receive File from Host window appears.

3. Select **Template**.

   The Template window appears. The contents of the window depend on the connected host system.



Adding Templates

The list box for the Template window lists the currently registered templates. The numbers running down the left side of the list are the template numbers.

To add a template:

1. Select a template, to be used for generation, from the list box. (Template 1 is selected first.)

   The contents of the selected template appear under the list box.

2. Change the PC and host file names by overwriting them; then select the transfer type. (For details of the transfer types, see “Defining Transfer Types” on page 5-7.)
3. Select **Add**.

   The window for determining where in the list to display a template to be added appears.
4. Select a template number. Determine whether to display the template to be added before or after the template having that number. Select **OK**.

   The generated template added to the list appears.

Replacing and Deleting Templates

To change the contents of a currently registered template, or to delete a template:

1. Select the template to be changed or deleted from the template list box.

   The contents of the selected template appear under the list box.
2. To change the contents, overwrite the appropriate part and then select **Replace**.

   To delete a template, select **Delete**.

   The selected template is changed or deleted, and the contents of the template list box are changed.

Testing Templates

To test the contents of an added or changed template:

1. Select a template to be tested from the template list box.

   The number of the selected template appears in the **Test Templates** box in the lower part of the window.
2. Select or enter data for the following items:

   Test mode Determine which mode is to be used for the test; the mode in which a file is transmitted from a workstation to the host system, or the mode in which a file is transmitted from the host system to a workstation.

   Templates Determine which templates to test: only the template selected in one or all registered templates.

   Source file Enter the name of the file to be tested.
3. Select **Test**.

   Using the selected template for **Target File** displays an automatically created file name assigned after the transfer.

Note: Testing templates does not transfer the actual files.

Import/Export (3270 Sessions Only)

Import/Export is an office system communication program and an application program executed under the IBM Customer Information Control System (CICS).

Executing the **Import/Export** command loads a module to be transferred into memory. Afterward, Import or Export can be called from the menu on the host screen, and executed.

The workstation receives two files using Export. One is the received file, and the other is the interchange document profile (IDP) file. An IDP file contains document header information. An IDP file containing transmission information is required to send a file using Import. Before importing a file created using DOS, create an IDP file. (For an explanation of how to create IDP files, see page 5-13.)

Transferring Files Using Import/Export

To transmit files using Import/Export:

1. Verify that the window of the host session, during which files are to be transferred, is active and ready for file transfer.
2. Select **Transfer - Import/Export** from the menu bar of the session window.

   The minimized Import/Export Status window appears.
3. Select **Import** or **Export** from the host application menu.
4. Specify the host and workstation file names of the file to be transferred. Run Import or Export.

   When Import or Export starts, the Import/Export Status window is maximized.

   After the file is transferred, the window is closed.

Defining Transfer Types

Transfer types define the option information used for controlling file transfer. Up to 16 transfer types can be defined for each host system. Text, binary, and append (excluding CICS) are initially set as the transfer types.

Explanation of Items to Be Defined

Choosing the **Transfer-Type Definition** command enables setting of the following items:

File Options

The file options that can be used depend on the type of the connected host system and the host code page selected when the workstation is configured. Table 5-1 lists the file options and the host systems and modes in which the options can be used.

File Option	Host System	Conversion Details
	VM/CMS MVS/TSO	Converts 1-byte workstation codes to EBCDIC codes when a file is sent.
ASCII	CICS	Converts EBCDIC codes to 1-byte workstation codes when a file is received.

File Option	Host System	Conversion Details
		Converts codes as follows when a file is sent:
		Does not remove CRLF (X'0D0A') from the end of each line. The code is treated as a delimiter for each record. Removes EOF (X'1A') from the end of the file.
		Converts codes as follows when a file is received:
	VM/CMS MVS/TSO	Adds CRLF (X'0D0A') to the end of each line. Adds EOF (X'1A') to the end of the file. Removes EOF from the existing file,
CRLF	CICS	and appends EOF to the end of the added file when APPEND is specified.
	VM/CMS	Appends the sent file to the existing host file.
APPEND	MVS/TSO	Appends the received file to the existing workstation file.

Table 5-1. Transfer File Options

Record Format

Valid only for VM/CMS and MVS/TSO if APPEND is not specified for file transmission. Any of the these can be selected:

Default value
Fixed (fixed length)
Variable (variable)
Undefined mode (for MVS/TSO only)

If the default value is selected, the record format is selected automatically by the host system.

Specifying **Variable** for VM file transfer enables host disk space to be used efficiently.

Logical Record Length (LRECL)

Valid only for VM/CMS and MVS/TSO if APPEND is not specified for file transmission.

Enter the **logical record length** to be used (host record byte count) in the **LRECL** text box. If **Variable** and **Undefined Mode** are specified as the record format, the logical record length is the maximum record length within a file. The maximum value is 32767.

The record length of a file sent from a workstation to the host system might exceed the logical record length specified here. If so, the host file transfer program divides the file by the logical record length.

To send a file containing long records to the host system, specify a sufficiently logical record length.

Because the record length of a workstation file exceeds the logical record length, a message does not appear normally if each record is divided. To display a message, add the following specification to the [Transfer] item of the workstation profile:

```
DisplayTruncateMessage = Y
```

TSO Allocation Parameter (MVS/TSO)

Valid only for MVS/TSO when **APPEND** is not specified for file transmission. The following items can be specified:

[Allocation Amounts]

Primary	Enter the number of tracks or cylinders allocated to this file transfer.
Secondary	If the primary allocation is not sufficient for the entire file transfer, enter additional storage capacity allocated to the file transfer.

[Allocation Units]

TRACKS	Specify this parameter to allocate a host file by track. Ask your system manager whether to use tracks or cylinders as the unit.
CYLINDERS	Specify this parameter to allocate a host file in units of cylinders.
AVBLOCK	Specify this parameter to allocate a host file in units of blocks.

[Block size]

This item is used only to create a new data set. Enter the block size of a new host data set, in bytes, in the text box. If this item is omitted, the workstation assumes the value that appears in the **Logical Record Length** box. The maximum value is 32767. If **AVBLOCK** is selected, the block size is the block size of the new data set.

Additional Options

The required host command options can be entered in the **Additional Options** text box.

Defining Transfer Types

To add or change transfer types:

1. Select **Transfer - Setup** from the menu bar of the session window.
2. Select **Define Transfer Types** from the submenu.

   The Transfer-Type Definition window appears. (The items that appear depend on the selected host system.)
3. Enter transfer-type names in the **Transfer-Type Names** text box, or select them from the list.
4. Select or enter the required items.

   To add transfer types, select **Add**. To replace them, select **Replace**. To delete transfer types, after selecting them from the transfer-type name list, select **Delete**.
5. After the transfer types have been added, replaced, or deleted; select **OK**.

   After the transfer types have been specified, the Transfer-Type Definition window is closed.

Setting Transfer Options

The following information can be defined for file transfer options:

File-Transfer Timeout

The time the workstation waits for a response from the host system, can be entered (in seconds). If the host system does not respond, the transfer is canceled, and an error message appears. A number from 20 to 65535 can be specified. The default is 20. Specify an appropriate value such that the error message does not appear too early.

If a packet or block size is relatively large for low-speed lines, such as SDLC or asynchronous communication or other lines, it is recommended that 150 seconds be specified.

Clearing Sessions before Transfer (3270 only)

Before a file is transferred, whether to transfer a Clear command to the host system can be specified. Select any of these option buttons:

Default value A Clear command is sent before a file is transferred for VM/CMS or CICS only.

Yes Before a file is transferred, a Clear command is sent.

No The Clear command is not sent.

File Transfer Packet Size (3270 only)

The amount of memory (in bytes) used by the workstation for transmission and reception. If a large value is entered, a file is transferred more quickly, but the memory overhead is larger. The default value is 2500.

Extension for List Files

The default extension for *List* used for file transfer can be specified. Up to three alphanumeric characters can be entered. The default value is .SRL.

Status Window

The method of displaying the file transfer progress status can be selected. Select any of the following option buttons. The default value is **Show in Session**.

Show in Session
When file transfer starts, the status window appears. The name of the file being transferred and the transfer progress appear.

Show in icon When file transfer starts, the status icon appears on the screen. When the status icon is restored, the status window appears.

PC Code Page

When a file is transferred, EBCDIC codes are converted to 1-byte workstation codes, and vice versa. A valid value is automatically selected from among 437, 819, 850, 860, 861, 863, and 865, according to the host code page specified when the workstation is configured. (For an explanation of how to select host code pages, see the online help for the Host Code Page.)

Enhanced Protocol (IBM Global Network Connection only)

This option enables faster file transfer in most cases. The packet size for Enhanced Protocol is fixed value so the File Transfer Packet Size setting is ignored.

Default Host Command

The host command to be called when file transfer starts can be entered. If nothing is entered in this text box, IND*x*$FILE is used for 3270 sessions; APVAFILE is used for 5250 sessions.

Default Directory for File Transfer

The directory that appears first in the Send File to Host or Receive File From Host window can be specified.

Changing Settings

To change miscellaneous items:

1. Select **Transfer - Setup** from the menu bar of the session window.
2. Select **Miscellaneous Settings** from the submenu.

   The Miscellaneous Settings window appears.
3. Change the required settings.
4. Select **OK**.

   After all the settings have been changed, the Miscellaneous Settings window is closed.

Setting Translation Tables

The translation tables used for sending or receiving files can be created and edited.

Changing Translation Tables

To change a translation table:

1. Select **Transfer - Setup** from the menu bar of the session window.
2. Select **Translation Table** from the submenu.

   The Translation-Table Setup window appears.



3. The table currently being used for file transfer appears in the selection status. Select either **IBM Default** or **User-Defined**.

4. If **User-Defined** is chosen, enter a translation table name in the text box, or select a file name by selecting **Browse**.
5. Select **OK**.

   After the translation table is set, the Translation Table window is closed.

Customizing Translation Tables

A user-specific translation table for transmission or reception can be created, or an existing translation table can be edited.

To create or edit a translation table:

1. Select **Customize** for transmitting or receiving a translation table in the Translation-Table Setup window.

   The Customize Translation window appears.



	0-	1-	2-	3-	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	00	10	40	F0	7C	D7	79	97	68	71	45	3C	76	2B	36	E1
-1	01	11	5A	F1	C1	D8	81	98	DC	9C	55	3D	77	2C	59	8F
-2	02	12	7F	F2	C2	D9	82	99	51	9E	CE	62	78	09	08	46
-3	03	13	7B	F3	C3	E2	83	A2	42	CB	DE	4F	80	0A	38	75
-4	37	B6	5B	F4	C4	E3	84	A3	43	CC	49	64	24	AC	BC	FD
-5	2D	B5	6C	F5	C5	E4	85	A4	44	CD	69	65	15	AD	39	EB
-6	2E	32	50	F6	C6	E5	86	A5	47	DB	9A	66	8C	AE	A0	EE
-7	2F	26	7D	F7	C7	E6	87	A6	48	DD	9B	20	8D	AF	BF	ED
-8	16	18	4D	F8	C8	E7	88	A7	52	DF	AB	21	8E	1B	CA	90
-9	05	19	5D	F9	C9	E8	89	A8	53	EC	0F	22	41	30	3A	EF
-A	25	3F	5C	7A	D1	E9	91	A9	54	FC	5F	70	06	31	FE	B3
-B	0B	27	4E	5E	D2	BA	92	C0	57	4A	B8	23	17	FA	3B	FB
-C	0C	1C	6B	4C	D3	E0	93	6A	56	B1	B7	72	28	1A	04	B9
-D	0D	1D	60	7E	D4	BB	94	D0	58	B2	AA	73	29	33	CF	EA
-E	0E	1E	4B	6E	D5	B0	95	A1	63	3E	8A	74	9D	34	DA	BD
-F	9F	1F	61	6F	D6	6D	96	07	67	B4	8B	BE	2A	35	14	FF

   If a translation table is not selected or **New** is chosen from the File menu, the default values appear in the table.

   Translation source codes
   PC code point codes when an upload translation table is edited. Host code point codes when a download translation table is edited.

   Translation target codes
   Host code point codes when an upload translation table is edited. PC code point codes when a download translation table is edited.

2. Double-click on the code to be changed in the table, and change the value in the entry field that subsequently appears.
3. Select **Save** for editing, or **Save As** for creation from the File menu.
4. If **New** is chosen, enter a translation table name in the *Save Translation File as* and select **OK**.

   The translation table is saved, and the Save Translation File As window is closed.

5. Select **Exit** from the File menu of the *Customize Translation* window.

   The window is closed, and control is returned to the Translation Table.

Creating IDP Files

To send a file to the host system using Import, an IDP file having information on the file is required. To import a file created by DOS, create an IDP with **Create IDP File**.

To create an IDP file:

1. Select **Transfer - Setup** from the menu bar of the session window.
2. Select **Create IDP File** from the submenu.

   The Create IDP File window appears.
3. Enter the name of an IDP file to be created in the text box, or select it from the list.
4. Select **OK**.

   The specified value is saved to an IDP file, and the Create IDP File window is closed.

The IDP file has the same name as the file to be transferred, and the extension (.IDP).

Transferring Files

Chapter 6. Modems

This chapter contains information about modems that the Auto-Dial Utility supports.

Asynchronous Modem Information

Modems must have certain characteristics to work properly with asynchronous communications. You can change the characteristics of most modems by switch settings, commands from the workstation, or both:

The modem must break the connection to the remote system ("hang up") and return to its initial state when the 'data terminal ready (DTR)' line is turned off and then turned back on.

The modem must turn off the 'carrier detect (CD)' line when it loses the connection to the remote system.

An autodial modem must send result codes to the workstation.

US Robotics Sportster 14.4 External Modem

When specifying the line speed in the link parameters of Personal Communications, use a speed other than 14,400 bps, due to a hardware limitation.

IBM ASYNC/SDLC V.32 Modem/A Modem

If you connect to AS/400 via SNA-over-Async when using this modem, the connection might fail. If this happens, save the Personal Communications default configuration command for this modem to the modem's profile-0.

Synchronous Modem Information

To use the Automatic Dial Facility with SDLC attachment, you need a synchronous modem that is based on ITU-T recommendation V.25bis and has the Automatic Dial Facility.

Command and Indication

For V.25bis, *command* means the data that is transferred from data terminal equipment, or terminal (DTE) to data circuit-terminating equipment, or modem (DCE), and *indication* means the data transferred from a modem to a terminal.

3270 and 5250 sessions support the following commands and indications:

Command

CRN Automatic transmission by specifying a telephone number.

Format: **CRN**xxx...xxx
(xxx...xxx is a telephone number.)

CRS Automatic transmission by specifying a shortened dial number.

Format: **CRS**xxx...xxx
(xxx...xxx is a shortened dial number.)

© Copyright IBM Corp. 1989, 1996

CRI Automatic transmission by specifying a telephone number and an ID number.

Format: **CRI**xxx...xxx
(xxx...xxx is a telephone number and an ID number.)

Indication

INV Shows that the modem received a command that is not valid.

VAL Shows that the modem sent a valid command.

CFI Shows that the automatic transmission failed.

CNX Shows that the connection is successful.

Dial Character

A character used for dialing is called the *dial character*. The following characters can be used as the dial character:

Any number from 0 to 9
; / * # : = < > – ( )
space
F, N, V

Note: You can use the dial characters only when they are supported by the modems you use.

NEC ITM2400mkII Modem

The memory switch settings for the NEC** ITM2400mkII modems are:

AUTODIAL On
HDLC

The modem dial command designed for the NEC ITM2400mkII modem is:

CRN/tn

where /**tn** is the value you entered for the **Telephone number** option. For example, if you enter **123456** for the telephone number, the command designed is **CRN123456**.

You need not specify dial answering. The Automatic Dial Facility identifies the modem signal and then confirms the connection.

Hitachi High-Speed Hybrid Telephone

The settings for the Hitachi** high-speed hybrid telephone modems are:

AA mode
V.25bis synchronous HDLC

The setting for synchronous data format of the automatic send/receive procedure should be same as that for data bit and parity of the Automatic Dial Facility.

The modem dial command designed for the Hitachi high-speed hybrid telephone modem is:

CRN/tn

where /**tn** is the value you entered for the **Telephone number** option. For example, if you enter **123456** for the telephone number, the command designed is **CRN123456**.

You need not specify the dial answering indication. The Automatic Dial Facility identifies the modem signal and then confirms the connection.

IBM7855-10 Modem

The setting for the IBM7855-10 modems is:

Synchronous

The modem dial command designed for the IBM7855-10 modem is:

CRN/tn

where /**tn** is the value you entered for the **Telephone number** option. For example, if you enter **123456** for the telephone number, the command designed is **CRN123456**.

You need not specify the dial answering. The Automatic Dial Facility identifies the modem signal and then confirms the connection.

Note: When the 1988 indicator is selected for the V.25bis extended function, **CNX** (which indicates that the connection is established) is returned. Specify **CNX** as the dial answering indication.

Modems

Chapter 7. Country Codes, Code Pages, and Character Sets

This chapter contains information useful in providing national language support for a network station or a gateway.

The **Country** option defaults to the current DOS country code. The countries are listed in “Country Codes” on page 7-2; the actual list available to you might be different.

The **PC code page** option defaults to the current active code page. The **Host code page** option defaults to the one for the keyboard country. The PC and Host code page options are listed in “Code Pages and Character Sets” on page 7-5.

For the **Keyboard type** option, the following choices are available:

Host-connected Host-connected keyboard (122-key)
Enhanced Enhanced keyboard

Table 7-1. Keyboard Type

Keyboard Type (Characteristics)	Figure
Host Connected (dual-row functions keys)	
Enhanced (single row of function keys)	

Personal Communications matches the keyboard type that you are using by interrogating the BIOS of the workstation. If the keyboard type setting does not match what is actually used, the key mapping will be incorrect.

Note: If you are using one type of keyboard to configure an installation for use on systems with another keyboard type, select the keyboard type of the *target* system.

© Copyright IBM Corp. 1989, 1996

Country Codes

The following table shows the country codes.

Table 7-2. Country Codes

Country	Country Code
Austria	043
Belgium	032
Bosnia / Herzegovina	387
Brazil	055
Bulgaria	035
Canada (French-speaking)	002
Croatia	384
Czech	042
Denmark	045
Finland	358
France	033
FYR Macedonia	389
Germany	049
Greece	030
Hungary	036
Iceland	354
Italy	039
Japan	081
Latin America	003
Netherlands	031
Norway	047
Poland	048
Portugal	351
Romania	040
Russia	007
Serbia / Montenegro	381
Slovakia	042
Slovenia	386
Spain	034
Sweden	046
Switzerland	041
Turkey	090
United Kingdom	044
U.S.	001

Keyboard Country ID and Shift Support

The following table shows the keyboard country ID and shift support for each country.

Table 7-3 (Page 1 of 2). Keyboard Country ID and Shift Support

Keyboard Country	Enhanced Keyboard ID	Enhanced Keyboard-Lock Mode	Host-Connected Keyboard ID	Host-Connected Keyboard Lock Mode
Austria	129	S	129	S
Belgium	120	S	120	S
Brazil	275	C	–	–
Canada (Bilingual)	058	C	277	S
Cyrillic				
Bulgaria	442	C	–	–
FYR Macedonia	449	C	–	–
Russia (441)	441	C	–	–
Russia (443)	443	C	–	–
Serbia / Montenegro	450	C	–	–
Denmark	159	C	281	S
Finland	153	C	285	S
France (120)	120	S	–	–
France	189	S	251	S
Germany	129	S	129	S
Greece	319	C	–	–
Iceland	197	C	197	S
Italy (141)	141	C	–	–
Italy (142/293)	142	C	293	S
Japan	–	C	–	C
Latin America (Spanish)	171	C	309	S
Latin 2				
Bosnia / Herzegovina (Latin)	234	C	234	S
Croatia	234	C	234	S
Czech	243	C	–	–
Hungary	208	C	–	–
Poland	214	C	–	–
Romania (Moldavia)	446	C	–	–
Slovakia	245	C	–	–
Slovenia	234	C	–	–
Netherlands	143	C	101	S
Norway	155	C	281	S
Portugal	163	C	163	S
Spain	173	C	071	S
Sweden	153	C	285	S
Switzerland (French)	150F	C	150F	S
Switzerland (German)	150G	C	150G	S
Turkey (179/402)	179	C	402	S
Turkey (440)	440	C	–	–
U.K. (166)	166	C	166	C
U.K. (168)	168	C	–	–

Table 7-3 (Page 2 of 2). Keyboard Country ID and Shift Support

Keyboard Country	Enhanced Keyboard ID	Enhanced Keyboard-Lock Mode	Host-Connected Keyboard ID	Host-Connected Keyboard Lock Mode
U.S. (English)	101G	C	101	S

Note:

–	Not selectable
S	Shift lock on key 30
C	Caps lock on key 30

Code Pages and Character Sets

The following table shows the code pages and character sets.

Table 7-4. Code Pages and Character Sets

Country	Host CPGID[1]/GCSGID[2]	PC CPGID/GCSGID
Austria	273-1/697-1 or 500-1/697-1	437/919 or 850/980
Belgium	500-1/697-1	437/919 or 850/980
Brazil	037-1/697-1	437/919 or 850/980
Canada (French)	500-1/697-1	863/993 or 850/980
Cyrillic		
Bulgaria	1025/1150	855/985 or 915
FYR Macedonia	1025/1150	855/985 or 915
Serbia	1025/1150	855/985 or 915
Russia	1025/1150	866/966
Denmark	277-1/697-1 or 500-1/697-1	865/996 or 850/980
Finland	278-1/697-1 or 500-1/697-1	437/919 or 850/980
France	297-1/697-1 or 500-1/697-1	437/919 or 850/980
Germany	273-1/697-1 or 500-1/697-1	437/919 or 850/980
Greece	875/925	869/998 or 737
Iceland	871-1/697-1	861/991 or 850/980
Italy	280-1/697-1 or 500-1/697-1	437/919 or 850/980
Latin America (Spanish)	284-1/697-1	437/919 or 850/980
Latin 2 (Multilingual)		
Bosnia / Herzegovina (Latin)	870/959	852/982 or 912/959
Croatia	870/959	852/982 or 912/959
Czech	870/959	852/982 or 912/959
Hungary	870/959	852/982 or 912/959
Poland	870/959	852/982 or 912/959
Romania (Moldavia)	870/959	852/982 or 912/959
Slovakia	870/959	852/982 or 912/959
Slovenia	870/959	852/982 or 912/959
Netherlands	037-1/697-1 or 500-1/697-1	437/919 or 850/980
Norway	277-1/697-1 or 500-1/697-1	865/995 or 850/980
Portugal	037-1/697-1 or 500-1/697-1	860/990 or 850/980
Spain	284-1/697-1 or 500-1/697-1	437/919 or 850/980
Sweden	278-1/697-1 or 500-1/697-1	437/919 or 850/980
Switzerland (French)	500-1/697-1	437/919 or 850/980
Switzerland (German)	500-1/697-1	437/919 or 850/980
Turkey	1026/1152	857/983
U.K.	285-1/697-1 or 500-1/697-1	437/919 or 850/980
U.S.	037-1/697-1 or 500-1/697-1	437/919 or 850/980

1 Code Page Global Identifier

2 Graphic Character Set Global Identifier

Host Code Page Tables

The following tables show the host code page for each country.

Host Code Page 037-1/697-1 Brazil, Canada, Netherlands, Portugal, U.S.

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	^	{	}	\	0
-1	(RSP)	é	/	É	a	j	~	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	`	i	r	z	¾	I	R	Z	9
-A	¢	!	¦	:	«	ª	¡	[	¯ (SHY)	¹	²	³
-B	.	$	,	#	»	º	¿	]	ô	û	Ô	Û
-C	<	*	%	@	ð	æ	Ð	¯	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	|	¬	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 273-1/697-1 Austria, Germany

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	ä	ü	Ö	0
-1	(RSP)	é	/	É	a	j	ß	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	{	ë	[	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	@	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	~	Ñ	`	i	r	z	¾	I	R	Z	9
-A	Ä	Ü	ö	:	«	ª	¡	¬	(SHY)	¹	²	³
-B	.	$	,	#	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	§	ð	æ	Ð	¯	¦	}	\	]
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 277-1/697-1 Denmark, Norway

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	¦	@	°	µ	¢	æ	å	\	0
-1	(RSP)	é	/	É	a	j	ü	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	}	ï	$	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	`	i	r	z	¾	I	R	Z	9
-A	#	¤	ø	:	«	ª	¡	¬	¯ (SHY)	¹	²	³
-B	.	Å	,	Æ	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	Ø	ð	{	Ð	¯	ö	~	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	[	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	]	®	×	õ	ÿ	Õ	(EO)

Host Code Page 278-1/697-1 Finland, Sweden

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	ä	å	É	0
-1	(RSP)	`	/	\	a	j	ü	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	{	ë	#	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	[	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	}	ï	$	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	é	i	r	z	¾	I	R	Z	9
-A	§	¤	ö	:	«	ª	¡	¬	(SHY)	¹	²	³
-B	.	Å	,	Ä	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	Ö	ð	æ	Ð	¯	¦	~	@	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	]	®	×	õ	ÿ	Õ	(EO)

Host Code Page 280-1/697-1 Italy

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	[	µ	¢	à	è	ç	0
-1	(RSP)	]	/	É	a	j	ì	#	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	{	}	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	@	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	\	~	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	ù	i	r	z	¾	I	R	Z	9
-A	°	é	ò	:	«	ª	¡	¬	¯ (SHY)	¹	²	³
-B	.	$	,	£	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	§	ð	æ	Ð	¯	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	¦	`	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 284-1/697-1 Latin America, Spain

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	{	}	\	0
-1	(RSP)	é	/	É	a	j	¨	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	¦	ß	#	`	i	r	z	¾	I	R	Z	9
-A	[	]	ñ	:	«	ª	¡	^	¯ (SHY)	¹	²	³
-B	.	$	,	Ñ	»	º	¿	!	ô	û	Ô	Û
-C	<	*	%	@	ð	æ	Ð	¯	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	~	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	|	¬	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 285-1/697-1 United Kingdom

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	{	}	\	0
-1	(RSP)	é	/	É	a	j	¯	[	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	`	i	r	z	¾	I	R	Z	9
-A	$	!	¦	:	«	ª	¡	^	¯ (SHY)	1	2	3
-B	.	£	,	#	»	º	¿	]	ô	û	Ô	Û
-C	<	*	%	@	ð	æ	Ð	~	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	|	¬	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 297-1/697-1 France

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	[	`	¢	é	è	ç	0
-1	(RSP)	{	/	É	a	j	¨	#	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	@	}	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	]	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	\	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	µ	i	r	z	¾	I	R	Z	9
-A	°	§	ù	:	«	ª	¡	¬	¯ (SHY)	¹	²	³
-B	.	$	,	£	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	à	ð	æ	Ð	¯	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	~	ò	¦	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 500-1/697-1 International

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	{	}	\	0
-1	(RSP)	é	/	É	a	j	~	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	`	i	r	z	¾	I	R	Z	9
-A	[	]	¦	:	«	ª	¡	¬	¯ (SHY)	1	2	3
-B	.	$	,	#	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	@	ð	æ	Ð	¯	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	þ	Æ	Þ	´	ó	ú	Ó	Ú
-F	!	^	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 870/959 Latin 2 - EBCDIC Multilingual

The column indicates the first digit and the row indicates the second digit.

	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	˅	˘	°	ą	·	{	}	\	0
-1	(RSP)	é	/	É	a	j	~	Ą	A	J	÷	1
-2	â	ę	Â	Ę	b	k	s	ż	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	Ţ	C	L	T	3
-4	ţ	ů	″	Ů	d	m	u	Ż	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ă	î	Ă	Î	f	o	w	ž	F	O	W	6
-7	č	Ĺ	Č	Ľ	g	p	x	ź	G	P	X	7
-8	ç	Í	Ç	Ĺ	h	q	y	Ž	H	Q	Y	8
-9	ć	ß	Ć	`	i	r	z	Ź	I	R	Z	9
-A	[	]	|	:	ś	ł	Ś	Ł	(SHY)	Ě	ď	Ď
-B	.	$	,	#	ň	ń	Ň	Ń	ô	ű	Ô	Ű
-C	<	*	%	@	đ	š	Đ	Š	ö	ü	Ö	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ŕ	ť	Ŕ	Ť
-E	+	;	>	=	ř	˛	Ř	´	ó	ú	Ó	Ú
-F	!	^	?	"	ş	¤	Ş	×	ő	ě	Ő	(EO)

Host Code Page 871-1/697-1 Iceland

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	þ	æ	´	0
-1	(RSP)	é	/	É	a	j	ö	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	ç	ì	Ç	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	ð	i	r	z	¾	I	R	Z	9
-A	Þ	Æ	¦	:	«	ª	¡	¬	¯ (SHY)	¹	²	³
-B	.	$	,	#	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	Ð	`	{	@	¯	~	ü	^	Ü
-D	(	)	_	'	ý	¸	Ý	¨	ò	ù	Ò	Ù
-E	+	;	>	=	{	]	[	\	ó	ú	Ó	Ú
-F	!	Ö	?	"	±	¤	®	×	õ	ÿ	Õ	(EO)

Host Code Page 00875 Greece

The column indicates the first digit and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	¨	΅	°	′	£	{	}	\	0
-1	Α	Κ	/	Ά	a	j	~	ά	A	J		1
-2	Β	Λ	Τ	Έ	b	k	s	έ	B	K	S	2
-3	Γ	Μ	Υ	Ή	c	l	t	ή	C	L	T	3
-4	Δ	Ν	Φ	(RSP)	d	m	u	ϊ	D	M	U	4
-5	Ε	Ξ	Χ	Ί	e	n	v	ί	E	N	V	5
-6	Ζ	Ο	Ψ	Ό	f	o	w	ό	F	O	W	6
-7	Η	Π	Ω	Ύ	g	p	x	ύ	G	P	X	7
-8	Θ	Ρ	Ϊ	Ώ	h	q	y	ϋ	H	Q	Y	8
-9	Ι	Σ	Ϋ	`	i	r	z	ώ	I	R	Z	9
-A	[	]	|	:	α	η	ν	ς	(SHY)	±	²	³
-B	.	$	,	#	β	θ	ξ	τ	ω	½	§	©
-C	<	*	%	@	γ	ι	ο	υ	ΐ			
-D	(	)	_	'	δ	κ	π	φ	ΰ	·		
-E	+	;	>	=	ε	λ	ρ	χ	‘	’	«	»
-F	!	^	?	"	ζ	μ	σ	ψ	—	¦	¬	(EO)

Host Code Page 1025/1150 Cyrillic

The column indicates the first digit, and the row indicates the second digit.

Hex Digits 1st → 2nd ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	Њ	п	й	я	ь	{	}	\	0
-1	(RSP)	љ	/	Ћ	a	j	~	ы	A	J	§	1
-2	ђ	њ	Ѓ	Ќ	b	k	s	з	B	K	S	2
-3	ѓ	ћ	Ё	(SHY)	c	l	t	ш	C	L	T	3
-4	ё	ќ	Є	Ў	d	m	u	э	D	M	U	4
-5	є	ў	S	Џ	e	n	v	щ	E	N	V	5
-6	s	џ	I	ю	f	o	w	ч	F	O	W	6
-7	i	Ъ	Ї	a	g	p	x	ъ	G	P	X	7
-8	ї	№	J	б	h	q	y	Ю	H	Q	Y	8
-9	j	Ђ	Љ	`	i	r	z	А	I	R	Z	9
-A	[	]	|	:	д	к	р	Б	Х	Н	Т	З
-B	.	$	,	#	е	л	с	Ц	И	О	У	Ш
-C	<	*	%	@	ф	м	т	Д	Й	П	Ж	Э
-D	(	)	_	'	г	н	у	Е	К	Я	В	Щ
-E	+	;	>	=	х	о	ж	Ф	Л	Р	Ь	Ч
-F	!	^	?	"	и	п	в	Г	М	С	Ы	(EO)

Host Code Page 1026/1 Latin 5 - Turkey

The column indicates the first digit, and the row indicates the second digit.

	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP)	&	-	ø	Ø	°	µ	¢	ç	ğ	ü	0
-1	(RSP)	é	/	É	a	j	ö	£	A	J	÷	1
-2	â	ê	Â	Ê	b	k	s	¥	B	K	S	2
-3	ä	ë	Ä	Ë	c	l	t	·	C	L	T	3
-4	à	è	À	È	d	m	u	©	D	M	U	4
-5	á	í	Á	Í	e	n	v	§	E	N	V	5
-6	ã	î	Ã	Î	f	o	w	¶	F	O	W	6
-7	å	ï	Å	Ï	g	p	x	¼	G	P	X	7
-8	{	ì	[	Ì	h	q	y	½	H	Q	Y	8
-9	ñ	ß	Ñ	ı	i	r	z	¾	I	R	Z	9
-A	Ç	Ğ	ş	:	«	ª	¡	¬	(SHY)	¹	²	³
-B	.	İ	,	Ö	»	º	¿	|	ô	û	Ô	Û
-C	<	*	%	Ş	}	æ	]	¯	~	\	#	"
-D	(	)	_	'	`	¸	$	¨	ò	ù	Ò	Ù
-E	+	;	>	=	¦	Æ	@	´	ó	ú	Ó	Ú
-F	!	^	?	Ü	±	¤	®	×	õ	ÿ	Õ	(EO)

Latin 5, Turkey

Chapter 8. Keyboard Layouts

This chapter describes keyboards supported by the host system. The keyboards are selected during installation or customization procedures. You can use keyboard layouts to locate character positions on the keyboard.

Different characters can appear in different key positions, depending on the country language selected. The function keys located across the top of the keyboard are not shown. Shaded areas show keys that are not available on some U.S. keyboards. Refer to "Changing the System Configuration" in the *IBM PC DOS User's Guide* and the *Personal System/2 National Language Supplement* for more information about the country and code page options. Ask your system administrator for information about host code pages.

For keys with three or four characters shown, use the key combinations in the following table to produce the desired upper-right and lower-right characters. Lower-left characters require no additional keys. Use the shift key for upper-left characters.

Country	Lower-Right Character Enhanced Template	Upper-Right Character All Templates
Denmark	AltGr	Ctrl
Finland	AltGr	Ctrl
Norway	AltGr	Ctrl
Sweden	AltGr	Ctrl
All others	AltGr	None

Alt and AltGr keys produce the same character on the Enhanced keyboard in DOS mode.

© Copyright IBM Corp. 1989, 1996

Keyboard Layouts for Windows Mode

This section describes keyboards supported by the host system and PC/3270 function for Windows mode. The character positions depending on the country language are the same as those for DOS mode. The function keys are positioned in the following shift status.

-Status-	
BASE	BASE : normal shift by depressing no shift key
SHIFT	SHIFT : Up Shift by depressing Up-Shift key
CTRL	CTRL : Control Shift by depressing Ctrl key
ALT	ALT : Alternate Shift by depressing Alt key
ALTGR	ALTGR : Shift by depressing Ctrl and Alt keys
CTRLSFT	CTRLSFT: Shift by depressing Ctrl and Up-Shift keys

Following are the abbreviation of the keys.

AltCur	Alternate Cursor
BackSp	Back Space
BgnOLn	Begin of Line
BotOPg	Bottom of Page
CarRtn	Carrier Return
ChgScrn	Change Screen
ChrAdv	Character Advance
CurBlink	Cursor Blink
CurSel	Cursor Select
DevCan	Device Cancel
DspTxC	Display TextCode
EndOLn	End of Line
ErEOF	Erase EOF
ErInp	Erase Input
Fld-	Field-
Fld+	Field+
FldColor	Field Color
FldExt	Field Exit
FldHigh	Field Highlight
FldMark	Field Mark
FldPS	PS Field Inherit
FldTrns	Transparency Field Inherit
FastDn	Fast Down
FastUp	Fast Up
HostPr	Host Print
JmpNext	Jump Next
MrkLeft	Mark Left
MrkUp	Mark Up
MrDown	Mark Down
MrRight	Mark Right
MvDown	Move Down
MvLeft	Move Left
MvRight	Move Right
MvUp	Move Up
NewLin	New Line
PSA	Programmed Symbol A
PSB	Programmed Symbol B
PSC	Programmed Symbol C
PSD	Programmed Symbol D
PSE	Programmed Symbol E
PSF	Programmed Symbol F
ReqBSp	Required Backspace
ReqTab	Required Tab
RolDwn	Roll Down
RolUp	Roll Up
Rst/Ctrl	Reset/Ctrl
RPause	Record/Play Pause
SysAttn	System Attention
SysReq	System Request
TabFld	Tab Field
TopOPg	Top of Page
TstReq	Test Request
TransOp	Transparency Opaque
Turq	Turquoise
UndScr	Underscore

PS/2 122-Key Keyboard (3270 Only)



Segment A assignment:

| | | |

Keyboard Layouts

Segment B assignment:



PS/2 Enhanced Keyboard (3270 Only)



Segment A assignment:

11	112	113	114	115	116	117	118	119	12	121	122	123
SysAttn	PF1	PF2	PF3	PF4	PF5	PF6	PF7	PF8	PF9	PF1	PF11	PF12
SysReq	PF13	PF14	PF15	PF16	PF17	PF18	PF19	PF2	PF21	PF22	PF23	PF24
-----	-----	-----	-----	-----	Record	Play	RPause	-----	-----	-----	RTM	-----
-----	Doc	WdWrap	CfgFmt	-----	-----	-----	-----	APL	CurSel	CurBlink	AltCur	+Cr
-----	Doc	WdWrap	CfgFmt	-----	-----	-----	-----	APL	CurSel	CurBlink	AltCur	+Cr
-----	Red	Pink	Green	Yellow	Blue	Turq	White	FldColor	-----	-----	-----	-----

124	125	126
-----	-----	Clear
-----	-----	-----
-----	-----	Break
-----	-----	-----
-----	-----	-----
-----	-----	-----

Segment B assignment:

1	2	3	4	5	6	7	8	9	1	11	12	13	14	15
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	BackSp			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	BackSp			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			

16	17	18	19	2	21	22	23	24	25	26	27	28	29
TabFld	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
BackTab	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			

3	31	32	33	34	35	36	37	38	39	4	41	43
-----	-----	-----	-----	-----	-----	-----	-----	-----	NewLine			
-----	-----	-----	-----	-----	-----	-----	-----	-----	NewLine			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			
-----	-----	-----	-----	-----	-----	-----	-----	-----	-----			

44	46	47	48	49	5	51	52	53	54	55	57
-----	-----	-----	-----	-----	-----	-----	-----		-----		
-----	-----	-----	-----	-----	-----	-----	-----		-----		
-----	-----	-----	-----	-----	-----	-----	-----		-----		
-----	-----	-----	-----	-----	-----	-----	-----		-----		
-----	-----	-----	-----	-----	-----	-----	-----		-----		
-----	-----	-----	-----	-----	-----	-----	-----		-----		

58	6	61	62	64
Reset/Ctrl	-----	-----	-----	Enter/Ctrl
Reset/Ctrl	-----	-----	-----	Enter/Ctrl
-----	-----	-----	-----	-----
Quit	-----	-----	-----	-----
Quit	-----	-----	-----	-----
-----	-----	-----	-----	-----

Keyboard Layouts



PS/2 122-Key Keyboard (5250 Only)



Segment A assignment:

Segment C assignment:

Segment E assignment:



Segment D assignment:



Keyboard Layouts

Segment B assignment:



PS/2 Enhanced Keyboard (5250 Only)



Segment A assignment:



Segment B assignment:



Keyboard Layouts



PS/2 122-Key Keyboard (Combined 3270 and 5250)



Segment A assignment:

7	SysAttn	SysReq
65	Clear	-----
	Clear	-----
71	CurSel	-----
66	RPause	-----
	RPause	-----
72	-----	-----
67	ErEOF	-----
	ErEOF	-----
	-----	-----
	Record	-----
	-----	-----
	-----	-----
73	-----	-----
68	Play	-----
	-----	-----
	-----	-----
	Test	-----
	Test	-----
	-----	-----
74	-----	-----
69	-----	-----
	-----	-----
	-----	-----
	-----	-----
	-----	-----
	-----	-----

Segment C assignment:

75	PA1	Dup	PageUp
8	PA2	FM	PagDwn
85	JmpNxt	JmpNxt	RolDwn
	JmpNxt		RolUp
	-----		ChgScr
76	BackTab	BackTab	-----
81	Insert	Insert	-----
86	Delete	Delete	DelWord
	Delete		DelWord
	-----		-----
82	Up		MkUp
	MvUp		FastUp
	FastUp		-----
78	Left		MkLeft
83	Rule		Rule
88	Right		MkRight
	MvLeft		-----
	MvRight		BtbWord
	BtbWord		Home
	Home		TabWord
	TabWord		-----
84	Down		MkDown
	MvDown		FastDn
	FastDn		-----

Segment E assignment:

9	-----	-----	-----	-----	-----
95	-----	-----	-----	-----	Break
1	-----	-----	-----	-----	TransOp
15	-----	-----	-----	-----	-----
91	-----	-----	-----	-----	-----
96	-----	-----	-----	-----	TabFld
11	-----	-----	-----	-----	-----
16	-----	-----	-----	-----	-----
	-----	-----	-----	-----	FldTrns
92	-----	-----	-----	-----	-----
97	-----	-----	-----	-----	-----
12	-----	-----	-----	-----	-----
17	-----	-----	-----	-----	-----
	PSD	PSE	PSF	-----	
93	-----	-----	ESC J	Enter	
98	-----	-----	-----	Enter	
13	-----	-----	-----	-----	-----
18	-----	-----	-----	-----	-----
	PSA	PSB	PSC	-----	
99	-----	-----	-----		
14	-----	-----	-----		
	-----	-----	-----		
	-----	-----	-----		
	-----	-----	-----		
	-----	-----	-----		
	FldPS	-----	-----		

Segment D assignment:

122	PF13	PF13	HostPr	Red	Red	-----	11	PF1	PF1	Help	Doc	Doc
123	PF14	PF14	-----	Pink	Pink	-----	111	PF2	PF2	-----	WdWrap	WdWrap
124	PF15	PF15	-----	Green	Green	-----	112	PF3	PF3	-----	ChgFmt	ChgFmt
125	PF16	PF16	-----	Yellow	Yellow	-----	113	PF4	PF4	-----	-----	-----
126	PF17	PF17	-----	Blue	Blue	-----	114	PF5	PF5	-----	-----	-----
127	PF18	PF18	RTM	Turq	Turq	-----	115	PF6	PF6	-----	-----	-----
128	PF19	PF19	-----	White	White	-----	116	PF7	PF7	-----	APL	APL
129	PF2	PF2	-----	FldColor	FldColor	-----	117	PF8	PF8	-----	-----	-----
13	PF21	PF21	-----	-----	-----	-----	118	PF9	PF9	-----	Reverse	Reverse
131	PF22	PF22	-----	CurBlink	CurBlink	-----	119	PF1	PF1	-----	-----	-----
132	PF23	PF23	-----	AltCur	AltCur	-----	12	PF11	PF11	-----	UndScr	UndScr
133	PF24	PF24	-----	+Cr	+Cr	-----	121	PF12	PF12	-----	FldHigh	FldHigh

Keyboard Layouts

Segment B assignment:



PS/2 Enhanced Keyboard (Combined 3270 and 5250)



Segment A assignment:

11	112	113	114	115	116	117	118	119	12	121	122	123
SysAttn	PF1	PF2	PF3	PF4	PF5	PF6	PF7	PF8	PF9	PF1	PF11	PF12
SysReq	PF13	PF14	PF15	PF16	PF17	PF18	PF19	PF2	PF21	PF22	PF23	PF24
					Record	Play	RPause				RTM	
	Doc	WdWrap	CfgFmt				APL		CurSel	CurBlink	AltCur	+Cr
	Doc	WdWrap	CfgFmt				APL		CurSel	CurBlink	AltCur	+Cr
	Red	Pink	Green	Yellow	Blue	Turq	White	FldColor				

124	125	126
		Clear
		Break

Segment B assignment:

1	2	3	4	5	6	7	8	9	1	11	12	13	14	15
											BackSp			
											ChrAdv			

16	17	18	19	2	21	22	23	24	25	26	27	28	29
TabFld													
BackTab													

3	31	32	33	34	35	36	37	38	39	4	41	43
									NewLine			
									NewLine			

44	46	47	48	49	5	51	52	53	54	55	57

58	6	61	62	64
Reset/Ctrl				Enter/Ctrl
Reset/Ctrl				Enter/Ctrl
Quit				
Quit				

Keyboard Layouts



APL Keyboard Layouts for Windows Mode (3270 Only)

This section shows the APL keyboard layouts for each country. Only APL characters are shown in each shift position (up/down/ALT). The character position is common to the 122-key keyboard and the IBM Enhanced Keyboard except U.S. English and is categorized into the following types.

Language	Type	Figure on
Austrian/German	1	page 8-16
Belgian	2	page 8-16
Canadian-Bilingual	1	page 8-16
Denmark	1	page 8-16
Finnish/Swedish	1	page 8-16
French AZERTY	2	page 8-16
Italian	1	page 8-16
Japanese	4	page 8-17
Latin American Spanish	1	page 8-16
Norwegian	1	page 8-16
Portuguese	1	page 8-16
Spanish	1	page 8-16
Swiss-French	1	page 8-16
Swiss-German	1	page 8-16
U.K. English	1	page 8-16
U.S. English (for 122-key Keyboard)	1	page 8-16
U.S. English (for IBM Enhanced Keyboard)	3	page 8-17

Keyboard Layouts



Figure 8-1. Type-1 APL Keyboard



Figure 8-2. Type-2 APL Keyboard



Figure 8-3. Type-3 APL Keyboard



Figure 8-4. Type-4 APL Keyboard

Key Map for Home3270

This section shows the position of the following control codes:

NUL (×00)
ESC (×1B)
FS (×1C)
GS (×1D)
RS (×1E)
US (×1F)

The positions of these control codes are fixed and common for all languages (including U.S. English), regardless of the characters assigned to BASE and UP SHIFT positions of the keys. These control codes are positioned to the CONTROL positions of the keys shown in Figure 8-5 through Figure 8-7 on page 8-19.



Figure 8-5. Common Control Code of Keyboard Core Segment for 122-Key Keyboard



Figure 8-6. Common Control Code of Keyboard Core Segment for Enhanced Keyboard



Figure 8-7. Common Control Code of Keyboard Core Segment for Japanese Keyboard

The positions of other control codes vary for each language. These control codes are positioned to the CONTROL position of the associated alphabetic key. Those control codes and the associated alphabetic characters are as follows.

Control Code	Associated Alphabet
SOH (×01)	a
STX (×02)	b
ETX (×03)	c
EOT (×04)	d
ENQ (×05)	e
ACK (×06)	f
BEL (×07)	g
BS (×08)	h
HT (×09)	i
LF (×0A)	j
VT (×0B)	k
FF (×0C)	l
CR (×0D)	m
SO (×0E)	n
SI (×0F)	o
DLE (×10)	p
DC1(XON) (×11)	q
DC2 (×12)	r
DC3(XOF) (×13)	s
DC4 (×14)	t
NAK (×15)	u
SYN (×16)	v
ETB (×17)	w
CAN (×18)	x
EM (×19)	y
SUB (×1A)	z

Figure 8-8. Other Control Code Map of Key Segment B

Following is an example of control code mapping for the U.S. 122-key and the U.S. Enhanced Keyboards.



Figure 8-9. Control Code Map of Keyboard Core Segment for U.S. 122-Key Keyboard



Figure 8-10. Control Code Map of Keyboard Core Segment for U.S. Enhanced Keyboard

Keyboard Layouts

Chapter 9. Messages

PCS52A001 **The system settings will not allow you to use the PC400 API.**

Do you want to change the system settings now?

Explanation: A module required by PC400 API has not been loaded.

User Response: To change your system configuration and load the required module, select **Yes**.

PCSADLC001 **The communication port number in your Workstation profile is invalid.**

Explanation: An incorrect port number was used for SNA-over-Async connection.

User Response: Change the port number to another that is available on your workstation.

PCSADLC002 **The line speed in your Workstation profile is invalid.**

Explanation: The line speed specified in the workstation profile was not valid.

User Response: Make sure the correct line speed is specified in the SNA-over-Async Attachment dialog box.

PCSADLC003 **The Bits and Parity in your Workstation profile is invalid.**

Explanation: The Bits and Parity specified in the workstation profile was not valid.

User Response: Make sure the correct Bits and Parity is specified in the SNA-over-Async Attachment dialog box.

PCSADLC004 **The link station address is invalid. Only values from 01 to FE are allowed.**

Explanation: You selected **OK** in the SNA-over-Async Attachment dialog box, but the value in the **link station address** entry field was not valid. Or, you attempted to start the Personal Communications workstation program with the profile specifying an incorrect link station address.

User Response: Change the link station address to the correct one in the SNA-over-Async Attachment dialog box.

PCSADLC005 **The PU ID in your Workstation profile is invalid.**

Explanation: The PU ID specified in the workstation profile was not valid.

User Response: Make sure the correct PU ID is specified in the SNA-over-Async Attachment dialog box.

PCSADLC006 **The Block ID in your Workstation profile is invalid.**

Explanation: The Block ID specified in the workstation profile was not valid.

User Response: Make sure the correct Block ID is specified in the SNA-over-Async Attachment dialog box.

© Copyright IBM Corp. 1989, 1996

PCSADLC008 **The Bits-per-character and Parity value is invalid. For Basic/Flow transparency, you must use 8-bit mode; for Full transparency, you must use 7-bit mode.**

Explanation: You specified the incorrect **Bits per character and parity**.

User Response: Change the **Bits per character and parity** value to the correct one in the SNA-over-Async Attachment dialog box.

PCSADLC009 **The transparency Level is invalid. In 8-bit mode, you must use Basic/Flow transparency; in 7-bit mode, you must use Full transparency.**

Explanation: You specified the incorrect **Transparency level**.

User Response: Change the **Transparency level** value to the correct one in the SNA-over-Async Attachment dialog box.

PCSADLC011 **The communication port selected is already being used by another application.**

Explanation: The selected port number was being used by another program.

User Response: Change the port number to one that is not currently being used.

PCSADLC012 **No more ports can be opened.**

Explanation: An additional port is not allowed to be opened. The port assignment exceeds the maximum number.

User Response: The maximum port number is 2. Make the number of ports less than or equal to 2.

PCSADLC013 **SNA-over-Async attachment does not support multiple ports.**

Explanation: You attempted to connect multiple SNA-over-Async attachments. Only one SNA-over-Async connection can be used at the same time.

User Response: Reconfigure the SNA-over-Async connection.

PCSADU001 file-name **has been changed. Do you want to save the changes?**

Explanation: The setting in this file has been changed, and you attempted to exit Automatic-Dial Facility.

User Response: Select **Yes** to save new settings and exit Automatic-Dial Facility. Select **No** if you do not want to save the changes.

PCSADU010 **Personal Communications V.25 bis Automatic-Dial Facility only supports the CRN, CRS and CRI commands.** xx **is not supported.**

Explanation: A command that is not supported was specified to the dial facility.

User Response: Use only the valid dial commands: CRN, CRS, or CRI.

PCSADU011 **Modem information was changed. Do you want to save the changes to the PCSMODEM.USR, PCSMSDLC.USR, or PCSHHAM.USR file as the modem's default setting?**

Explanation: The modem setting has been changed. If you want to use this setting later, you can save it as the default setting.

User Response: Select **Yes** if you want to change the default modem setting.

PCSAEA001 **The communication port selected is not available on this PC.**

Explanation: You assigned a communication port that is not available on your workstation.

User Response: Change the communication port to another that is available on your workstation.

PCSAEA002 **The communication port selected is already being used by another application.**

Explanation: The selected port number was already used by another program.

User Response: Change the port number to one that is not currently used.

PCSAEW001 **The DOS-mode API can be used only when Windows is running in 386 Enhanced mode; this is not the case on your PC.**

Explanation: You are running Windows in Standard mode. The DOS-mode API is not supported in Standard mode.

User Response: Re-configure your Windows to 386 Enhanced mode. Additional system memory might be required to run Windows in 386 Enhanced mode on your workstation.

PCSAEW002 **The system settings will not allow you to use the DOS-mode API. Do you want to change the system settings now?**

Explanation: The required module to use the DOS-mode API was not loaded.

User Response: Select **Yes** to change the system settings to load the required module.

PCSAPI001 **The combination of host code-page and PC code-page is invalid. The default PC code-page will be used.**

Explanation: You selected DDE/EHLLAPI to be enabled but the combination of Host code page and PC code page was not valid.

User Response: Reconnect the communication after selecting the proper host code page from the Host Code Page combo box in the Customize Communication - 3270 Host dialog box. (You do not follow this step if you are using Home3270 connection.) Then select the proper PC code page from the PC code page combo box in the API Setting - Session X dialog box.

If the problem persists, ask your system administrator for assistance.

PCSAPI001 **The combination of host code-page and PC code-page is invalid. The default PC code-page will be used.**

Explanation: You selected DDE/EHLLAPI to be enabled, but the combination of host code page and PC code page was not valid.

User Response: Reconnect the communication after selecting the correct host code page from the *Host Code-Page* combo box in the *Customize Communication - 5250 Host* dialog box. Then select the correct PC code page from the *PC Code-Page* combo box in the *API Settings* dialog box of the *Session X* window *File* menu.

If the problem persists, ask your system administrator for assistance.

PCSASYNC001 **Invalid Port-number!**

Explanation: An incorrect port number was used for Advantis (IIN) communication.

User Response: Change the port number to 1, 2, 3, or 4.

PCSASYNC002 **The communication port selected is already being used by another application.**

Explanation: The selected port number was already used by another program.

User Response: Change the port number to one that is not currently used.

PCSASYNC003 **No more ports can be opened!**

Explanation: The port assignment exceeded the maximum number. An additional port is not allowed to be opened.

User Response: The maximum port number is 4. Make the number of ports less than or equal to 4.

PCSASYNC010 **The Link Address specified in your WorkStation profile is invalid.**

Explanation: The link station address specified in the workstation profile was not valid.

User Response: Make sure the correct link station address is specified in the configuration using **Configure** in the Communication menu bar.

PCSASYNC011 **The PU ID specified in your WorkStation profile is invalid.**

Explanation: The Physical Unit ID specified in the workstation profile was not valid.

User Response: Make sure the PU ID specified in the configuration matches the host using **Configure** in the Communication menu bar.

PCSASYNC012 **The Block ID specified in your WorkStation profile is invalid.**

Explanation: The Block ID specified in the workstation profile was not valid.

User Response: Make sure the correct Block ID is specified in the configuration using **Configure** in the Communication menu bar. If 37x5 gateway is used, the same number that is specified by IDBLK in VTAMLIST should be used.

PCSASYNC020 PIU Size: Only values from 265 to 2057 are allowed.

Explanation: An incorrect size was assigned for the PIU size.

User Response: Use valid values from 265 to 2057 for the PIU size.

PCSASYNC021 PAD Buffer Size: Only values from 272 to 2000 are allowed.

Explanation: An incorrect size was assigned for the PAD buffer size.

User Response: Use valid values from 272 to 2000 for the PAD buffer size.

PCSASYNC030 AutoDial file is already being used for the first port.

Explanation: The specified auto dial file was already used by another port that was already opened.

User Response: Specify another auto dial file for this port.

PCSBAT001 Batch file was not specified. PCSBAT.EXE will not execute any application.

Explanation: You attempted to execute **PCSBAT.EXE** with the /R parameter but did not specify the batch file to be executed.

User Response: Specify the batch file in the command line of **PCSBAT.EXE** and try the operation again.

PCSBAT002 Parameter is an invalid parameter.

Explanation: You attempted to execute **PCSBAT.EXE** with an incorrect parameter.

User Response: Remove the incorrect parameter and try the operation again.

PCSBAT003 The file: file-name **is not a Personal Communications batch file.**

Explanation: The file file-name does not have a valid format for a Personal Communications batch file. This message sometimes appears if you have manually modified the batch file.

User Response: Make sure that the correct file name is specified and if it is, re-create the Personal Communications batch file and try the operation again. If the problem persists, install Personal Communications again.

PCSBAT004 Not enough memory to load file-name **because it exceeds** xxxx **bytes.**

Explanation: There was not enough memory to load the program.

User Response: Close other Windows applications to free memory for Personal Communications.

PCSBAT010 file-name **cannot be found.**

Explanation: The file file-name was not found.

User Response: Make sure that the correct path and file name are given.

PCSBAT011 file-name **is not a valid file-name or the file is not in the path you specified. Please check that you entered the correct name or path.**

Explanation: The file file-name does not form a valid DOS file name.

User Response: Make sure that a correct file name is specified.

PCSBAT012 **Error writing the batch file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the Personal Communications batch file: file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSBAT020 file-name **has been changed. Save changes?**

Explanation: You attempted to exit the Personal Communications batch program without saving the changes made since the last time you selected **New** in the File pull-down menu, opened a batch file, or saved the changes into a batch file.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel the changes without exiting. The Personal Communications Batch Window remains opened.

PCSBAT030 **Add this new batch file to the Program Manager?**

Explanation: A new batch file will be added to the Program Manager.

User Response: Select **Yes** to add a new batch file to the Program Manager. Select **No** to not add a new batch file to the Program Manager. If you select No, you need to start the Batch Program manually by the *Run* command of Windows. Run **PCSBAT.EXE** batch-file-name.

PCSBAT040 **The PCSBAT icon cannot be added to the Program Manager. You must start PCSBAT.EXE** file-name **manually.**

Explanation: You selected **No** to add the icon of the batch program to the Program Manager.

User Response: Run **PCSBAT.EXE** batch-file-name from Windows to start the batch program.

PCSBAT041 **The PCSBAT.EXE** file-name **icon has been added to group** group-name**. Double-click the icon to start the program.**

Explanation: The icon of the Batch Program with the specified batch file has been added to the specified program group.

User Response: Double-click the icon of the Batch Program to start it.

PCSBAT050 **Add to Program Manager failed. You must start PCSBAT.EXE** file-name **manually.**

Explanation: The icon of the batch program with the batch file has not been added to the Program Manager.

User Response: Run **PCSBAT.EXE** batch-file-name from Windows to start the batch program.

PCSCC001 **An invalid parameter was specified.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile with an incorrect communication parameter.

User Response: Re-create the Personal Communications workstation profile after setting the communication parameters in the Customize Communication window and its associated dialog boxes, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC002 **The link specified in your workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile, specifying an unrecognized link selection. This message sometimes appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper link connection in the Customize Communication dialog box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC004 **The screen size specified in your Workstation profile is not allowed in the current link connection.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying a screen size that is not supported in the selected link connection. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper screen size from the Screen Size combo box in the Customize Communication - 3270 or 5250 Host dialog box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC005 **The session type specified in your workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile, specifying an unrecognizable session type. This message sometimes appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after choosing either **Display** or **Printer** among the Session Type radio buttons in the Customize Communication - 3270 or 5250 Host dialog box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC006 **The host code-page specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying a nonsupported host code page. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper host code page from the Host Code Page combo box in the Customize Communication - 3270 or 5250 Host dialog

box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC007 **The host code-page specified in your workstation profile is not valid for your Windows installation.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile, specifying the Japanese language as the host code page while your Windows was not the Japanese version.

User Response: Exit from Windows, restart the Japanese version of Windows, and then try the operation again. If the problem persists, ask your system administrator for assistance.

PCSCC008 **The LT number specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect LT number. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper LT number from the LT number combo box in the Customize Communication - 3270 or 5250 Host dialog box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC009 **The LU number specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect LU number. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper LU number from the LU number combo box in the Customize Communication - 3270 or 5250 Host dialog box, then try the operation again. If the problem persists, install Personal Communications again.

PCSCC020 **The** N**th workstation window is not allowed in the** link-name **connection.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the link link-name while other (N-1) Personal Communications workstation windows were already connected to your application through the same link. The following list summarizes the maximum number of workstation windows allowed for each link connection.

5 in the SNA distributed function terminal connection.
5 in the Non-SNA distributed function terminal connection.
1 in the control unit terminal connection.
26 in the 3174 peer communication connection.
26 in the OS/2 client/server connection.
1 in the LAN via IEEE 802.2 connection.
26 in the LAN via 5250 emulation gateway connection.
26 in the asynchronous (IIN) connection.
1 in the Home3270 connection.
26 in the synchronous data link control connection.

User Response: Close one of the other Personal Communications workstation windows connected through the same link before attempting to connect this workstation window.

PCSCC030 **LT number xx has already been assigned to another WorkStation Window.**

Explanation: You attempted to connect the Personal Communications workstation window to your application using the same LT number that was already used by another workstation window. This message does not appear when you select **Smallest Number Available** in the LT Number combo box in the Customize Communication - 3270 or 5250 Host dialog box (default setting) because Personal Communications assigns the LT number automatically to each workstation window. The message appears when the same value other than Smallest Number Available is selected on two different workstation windows.

User Response: Close the other Personal Communications workstation window having the same LT number before attempting to connect this workstation window.

PCSCC031 **LU number xx has already been assigned to another WorkStation Window.**

Explanation: You attempted to connect the Personal Communications workstation window to your application using the same LU number that was in use by another workstation window. This message does not appear when you select **Smallest Number Available** in the LU Number combo box in the Customize Communication - 3270 or 5250 Host dialog box (default setting), because Personal Communications assigns the LU number automatically to each workstation window. This message appears when the same value other than Smallest Number Available is selected on two different workstation windows.

User Response: Close the other Personal Communications workstation window having the same LU number before attempting to connect this workstation window.

PCSCC040 **The Customize Communication dialog box is already open.**

Explanation: You attempted to select **Configure...** in the Communication pull-down menu while the Customize Communication dialog box was already displayed in the other workstation window.

User Response: Close the Customize Communication dialog box in the other workstation window before attempting to select it.

PCSCC041 **Communication will be terminated if you proceed. Are you sure?**

Explanation: You attempted to select **OK** in the Customize Communication dialog box while the communication was connected.

User Response: Select **OK** to continue the operation. The communication will be automatically disconnected when the dialog box is closed and reconnected when **AutoConnect** is selected.

Select **Cancel** to quit the operation. The Customize Communication dialog box remains opened.

PCSCC050 **PC location name is invalid.**

Explanation: The first half field (local network ID) or the last half field (local LU name) of the specified PC location name is blank.

User Response: Enter a PC location name (local network ID and local LU name).

PCSCC051 **System location name is invalid.**

Explanation: The first half field (remote network ID) or the last half field (remote LU name) of the specified system location name is blank.

User Response: Enter a system location name (remote network ID and remote LU name).

PCSCC053 **Only the host code-page Japan is valid for this session.**

Explanation: You selected an incorrect host code page for a printer session.

User Response: Select Japanese alphanumeric katakana or Japanese alphanumeric lowercase as the host code page.

PCSCC056 **Fully qualified local LU name is not valid.**

Explanation: The first half field (local network ID) or the last half field (local LU name) of the specified fully qualified local LU name is blank.

User Response: Enter a fully qualified local LU name (local network ID and local LU name).

PCSCC057 **Fully qualified partner LU name is not valid.**

Explanation: The first half field (local network ID) or the last half field (local LU name) of the specified fully qualified partner LU name is blank.

User Response: Enter a fully qualified partner LU name (local network ID and local LU name).

PCSCDLG001 **Cannot create the program group. Please change the program group.**

Explanation: You selected **OK** in the Add xxxx to Program Group dialog box, but an unrecognizable character by the Windows program manager was included in the specified program group name.

The following restrictions apply to the program group name.

1. You cannot use the character (,), [, or] in the program group name.

   Personal Communications (Version 4.1) is incorrect.

   Personal Communications [Version 4.1] is incorrect.

2. You cannot specify a program group name that does not contain an alphanumeric character in it.

   xxxxxxxx is incorrect.

   xxxxxxx1 is correct.

User Response: Change the program group name to meet the above requirements.

PCSCM001 **Communication Manager is already running.**

Explanation: You attempted to run the Personal Communications Communication Manager program when it was already running.

User Response: Close the Personal Communications Communication Manager program that is running before attempting to restart it.

PCSCOAX001 **The number specified in your WorkStation profile for the 3270 coax adapter is invalid. It can be 0 to 3 only.**

Explanation: You attempted to start the PC/3270 workstation program with the profile, or attempted to open the profile, specifying an unrecognizable 3270 communications adapter number. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the PC/3270 workstation profile after selecting the proper adapter number from the Adapter Number combo box in either the SNA Distributed Function Terminal or the Non-SNA Distributed Function Terminal dialog box, then try the operation again. If the problem persists, install PC/3270 again.

PCSCOAX002 **The memory address specified in your Workstation profile for the 3270 coax adapter is invalid.**

Explanation: You attempted to start the PC/3270 workstation program with the profile, or attempted to open the profile, specifying an unrecognizable 3270 communications adapter buffer address, or the adapter does not exist at the buffer address. This message usually only appears if you have manually modified the workstation profile.

User Response: Re-create the workstation profile and try the operation again, or correct the Buffer Address in your workstation profile and try the operation again.

For example, when the 3270 communication adapter is mapped to CE000 on your workstation, specify CE. If the problem persists, ask your system administrator for assistance.

PCSCOAX003 **Keyboard-type specified in your WorkStation profile is invalid.**

Explanation: The keyboard-type specified in your workstation profile is not supported by PC/3270.

User Response: Specify a valid keyboard-type in your workstation profile. The valid keyboard-type for “KeyboardType” is only “E” for 3278 Emulation.

PCSCOAX004 **Controller-language specified in your Workstation profile is invalid.**

Explanation: The controller-language specified in your workstation profile is not supported by PC/3270.

User Response: Specify a valid language in your workstation profile. The valid language for “CULanguage” is only “US” for U.S. English.

PCSCOAX010 **3270 coax adapter has not been installed.**

Explanation: You attempted to connect the PC/3270 workstation window to your application as SNA Distributed Function Terminal or Non-SNA Distributed Function Terminal, but PC/3270 could not find the 3270 communications adapter card on your workstation.

User Response: Make sure that the 3270 communications adapter is installed on your workstation and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSCOAX011 **Interrupt-level 2 has also been for other hardware such as a Local Area Network adapter. The 3270 coax adapter can not share interrupt-level 2.**

Please change the interrupt level of the other adapter.

Explanation: You attempted to connect the PC/3270 workstation window to your application as SNA Distributed Function Terminal or Non-SNA Distributed Function Terminal, but PC/3270 detected that interrupt level 2 was already used by other hardware such as the Local Area Network adapter.

User Response: Follow the instructions in the message and make sure that interrupt level 2 is assigned to the 3270 communication adapter card only, then try the operation again. If the problem persists, ask your system administrator for assistance.

PCSCOAX012 **The 3270 coax adapter has already been specified for use by another Workstation window.**

Explanation: You attempted to connect the PC/3270 workstation window to your application as SNA Distributed Function Terminal or Non-SNA Distributed Function Terminal, but the 3270 communication adapter was already used by another workstation window configured for another connection.

For example, this message appears when you try to connect the PC/3270 Window as SNA Distributed Function when you have already connected another workstation window as Non-SNA Distributed Function Terminal.

User Response: Close the other workstation window that is using the 3270 communication adapter before attempting to connect the workstation window.

PCSCOAX013 **Coexistence of 3270 Emulator card and PCMCIA, or multiple PCMCIA is not supported. Please change the configuration.**

Explanation: You attempted to connect the PC/3270 workstation window to your application as a DFT or CUT connection with nonsupported configuration.

For example, this message appears when you try to connect the PC/3270 workstation window as SNA Distributed Function with PCMCIA setting when you have already connected another 3270 emulator card setting.

User Response: Reconfigure the DFT or CUT connection.

PCSCOAX014 **To use PCMCIA, you need to run PCSMCIA.BAT before WIN.COM or PCSWIN.BAT runs. PCSMCIA.BAT will be updated with new configuration. Are you sure?**

Explanation: You selected **Yes** for PCMCIA and **OK** in the Configuring Link dialog.

User Response: Select **Yes** to change **PCSMCIA.BAT** with the new configuration and exit Windows. Run **PCSMCIA.BAT** and restart Windows. Select **No** if you don't want to change **PCSMCIA.BAT**.

PCSCOAX020 **Personal Communications might have been disconnected by a timeout. The WorkStation must be re-configured. Please consult your system administrator.**

Explanation: A timeout might have occurred between the workstation and the controller with your configuration. The configuration for your workstation must be changed.

User Response: Ask your system administrator for assistance.

PCSCOAX021 **Your 3270 coax adapter does not support Extended Attribute Buffer. Always 4 color mode is selected.**

Explanation: The COAX adapter card you are using does not support the Extended Attribute Buffer function. The color mode of your workstation is always “4 color mode”.

User Response: Replace the COAX adapter card with a new one, or reconfigure PC/3270 to a different DFT attachment.

PCSCSM001 **The settings for communication to ''host name'' have not been saved. Do you want to save the current definitions?**

Explanation: You configured a new communication link to "host name", but the settings have not been saved yet.

User Response: Select **Yes** if you want to save them. Otherwise, select **No**.

PCSCSM002 **The settings for communication to ''host name'' have not been saved. Do you want to save the current definitions?**

Explanation: You changed the settings for communication to "host name", but they have not saved yet.

User Response: Select **Yes** if you want to save them. Otherwise, select **No**.

PCSCSM003 **The ''program name'' program is still running. You must stop it before you can quit Windows.**

Explanation: You attempted to quit Windows while "program name" was running.

User Response: Close "program name" and then quit Windows again.

PCSCUT52001 **TDLC Attachment (Console) does not allow user to execute another session by the same station address.**

Explanation: You attempted to open another session having the same address as an already open session of a twinaxial connection (Console).

User Response: Change the address, or use more than one session with a twinaxial connection (APPC).

PCSCUT52002 **Since all supported station addresses are already in use by other sessions, this session cannot be opened. Please try again after closing other sessions.**

Explanation: You attempted to open three sessions with different addresses at the same time.

User Response: Close the other sessions and restart the session.

PCSCW001 **You cannot start another session.**

Explanation: You attempted to start the Personal Communications workstation program while 26 other Personal Communications workstation windows have been already opened.

User Response: Close one of the Personal Communications workstation windows that is running before attempting to restart it.

PCSDB001 **This operation will close the current connection. Choose OK to continue.**

Explanation: You selected **Data Source** from the menu when a data source (ODBC driver) was already connected. If you select **OK**, the current data source will be disconnected, then the new data source will be connected.

User Response: Select **OK** to connect a new data source. Select **Cancel** to stay connected to the current data source.

PCSDB002 **An error occurred while connecting with the application.**

Explanation: An error occurred in the DDE connection for the application that you specified in the Run Options window. The application program might not be installed correctly, or the directory in which the application program is installed might not be set in the search path.

User Response: Set the search path for the directory in which the application program is installed using the PATH command.

PCSDB003 **The format of the PC400 access file that you specified is not correct.**

Explanation: The file that you specified in the File combo box is not the current PC400 access file.

User Response: Specify the correct PC400 access file in the combo box.

PCSDB004 **An error occurred in the SQL statement. The first word must be SELECT.**

Explanation: You edited the SQL statement using incorrect syntax in the SQL statement window. You must specify the word SELECT at the beginning of the SQL statement.

User Response: Check and correct the SQL statement in the SQL Statement window.

PCSDB005 **An error occurred in the SQL statement. SQL keyword FROM is not found.**

Explanation: You edited the SQL statement using incorrect syntax in the SQL statement window. You must specify the word FROM in the SQL statement.

User Response: Check and correct the SQL statement in the SQL Statement window.

PCSDB006 **An error occurred while opening the clipboard.**

Explanation: An error occurred while opening the clipboard. The Windows memory might not be enough to open the clipboard.

User Response: Exit any open application programs to free more Windows memory. If the problem persists, exit all application programs and restart Windows.

PCSDIA010 **Host has not responded within the time-out period.**

Explanation: The PC/3270 workstation window canceled the Import/Export because the host did not respond within the timeout period.

User Response: Increase the timeout value in the Miscellaneous Settings dialog box. The default timeout value is 20 seconds. If the problem persists, ask your system administrator for assistance.

PCSDIA011 **Unrecoverable system error.**

Explanation: This message appears with the following messages.

Host connect return code - xxx
Write structured field return code - xxx
Read structured field return code - xxx
Data exception code sent to host - xxx
Data exception code sent from the host - xxx
Host disconnect return code - xxx

User Response: Restart PC/3270 and retry your operation. If the problem persists, ask your system administrator for assistance.

PCSDIA012 **Program error at the host.**

Explanation: The transfer program has detected an error in the data from the host.

User Response: Ask your system administrator for assistance.

PCSDIA013 **Transfer program has stopped.**

Explanation: This message is displayed with message PCSDIA140 or any of several messages.

User Response: None.

PCSDIA014 **Transfer program canceled by the user.**

Explanation: This message appears when you cancel the file transfer.

User Response: None.

PCSDIA015 **Current file transfer canceled by the host program.**

Explanation: This message appears when the host application has signaled to the transfer program that the host does not want to continue with the current file transfer. This could be because of an input/output error at the host.

User Response: Record the messages in the host session and follow the instructions for that host application.

PCSDIA017 **Program error detected by the host program.**

Explanation: This message appears when the host has sensed an error in the data sent to it by the transfer program.

User Response: Ask your system administrator for assistance.

PCSDIA022 **Host rejected your file-transfer attempt.**

Explanation: This message appears when the host rejects a transmission that the transfer program assumed was successful. The transfer program is waiting for a new request from the host. This message will be followed by a message in PCSDIA011.

User Response: Ask your system administrator for assistance.

PCSDIA036 **Current file transfer canceled by the user.**

Explanation: This message appears when you cancel the file transfer. The transfer of the file stops, and the transfer program waits for more requests from the host.

User Response: Begin another file transfer or select exit to quit.

PCSDLC001 **One or more of the Link Parameters conflict with those of another existing Workstation session.**

Explanation: You attempted to connect the Personal Communications workstation window to your application, but the link parameters conflict with the other ones.

For example:

1. Connect a Personal Communications workstation window through the SDLC connection after specifying **C1** in the Station Address entry field of the SDLC Attachment dialog box.
2. Connect another Personal Communications workstation window through the SDLC connection after specifying **01** in the Station Address entry field of the SDLC Attachment dialog box with the same adapter number as that specified in example 1.

User Response: Correct the link parameters and try the operation again.

PCSDLC010 **The system settings will not allow you to make a connection to the host. Do you want to change the system settings now?**

Explanation: The required module for Personal Communications was not loaded. For example, you attempted to run Personal Communications in LAN configuration, but the required module for that configuration was not in the **SYSTEM.INI** file of Windows.

User Response: Select **Yes** to change the system settings. After changing the system settings, you are prompted to restart Windows or to

exit to DOS. Select **No** if you do not change the system settings. The message PCSDLC011 is displayed.

PCSDLC011 **Run the Personal Communications Setup Program and choose the Change System Settings command from the Options menu.**

Explanation: The execution of Setup Program is required to change the system settings correctly to make a connection to the host.

User Response: Run Configuration and Program Options in Administration Tools to change the system settings correctly.

PCSDLC020 **The PIU size is invalid. Only values from 265 to 2042 are allowed.**

Explanation: You selected **OK** in the IEEE 802.2 dialog box, but the value in the **PIU Size** entry field was not valid.

User Response: Correct the value in the **PIU Size** entry field as instructed in the message and try the operation again.

PCSDLC021 **Fully-Qualified CP Name is invalid. Please correct it.**

Explanation: You selected **OK** from the IEEE 802.2, SDLC Attachment, or Twinaxial Attachment (APPC) dialog box, but a fully qualified control point name was not entered.

User Response: Enter a fully qualified control point name in the input field.

PCSDLC022 **The PIU size is invalid. Only values from 265 to 2057 are allowed.**

Explanation: You selected **OK** in the SDLC attachment dialog box, but the value in the **PIU Size** entry field was not valid.

User Response: Correct the value in the **PIU Size** entry field as instructed in the message and try the operation again.

PCSDLC030 **Only hexadecimal numbers (0–9, A–F) are allowed.**

Explanation: You attempted to type a character other than hexadecimal numbers (0–9, A–F) in the entry field of the dialog box.

User Response: Type the hexadecimal number in the entry field.

PCSDLC031 **Only decimal numbers (0–9) are allowed.**

Explanation: You attempted to type a character other than numbers (0–9) in the entry field of the dialog box.

User Response: Type the decimal number in the entry field.

PCSDLC032 **To be valid, a name must start with (A-Z, $, @, #) followed by (0-9, A-Z, $, @, #).**

Explanation: You attempted to enter a character other than the above in the input field.

User Response: Enter a valid character in the input field.

PCSDLC033 **To be valid, a name must start with (A-Z, $, @, #, *) followed by (0-9, A-Z, $, @, #).**

Explanation: You attempted to enter a character other than the above in the input field.

User Response: Enter a valid character in the input field.

PCSDLC041 **There was not enough memory for the trace buffer. Please decrease TraceBufferSize in your workstation profile or free up some the conventional memory.**

Explanation: You attempted to connect the Personal Communications workstation window to your application after specifying a large communication trace buffer size in your workstation profile, but the attempt failed.

User Response: Follow the instructions in the message and decrease the trace buffer size in your workstation profile, or increase the conventional memory as described in message PCSDLC040 for the SDLC or asynchronous connection.

PCSERR001 **Error opening file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to open the file file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSERR002 **Error reading file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to read the file file-name.

User Response: Determine the cause of the error condition and correct it or ask your system administrator for assistance.

PCSERR003 **Error writing file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the file file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSERR004 **Error in the format of Personal Communications file:** file-name**.**

Explanation: The format of the Personal Communications file file-name was incorrect.

User Response: Re-install Personal Communications and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR005 **Error writing file:** file-name **because disk is full.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the file file-name, because the directory was full.

User Response: Make sure that the subdirectory is not full and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR006 **Error closing file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to close the file file-name.

User Response: Determine the cause of the error condition and correct it or ask your system administrator for assistance.

PCSERR007 **Error creating file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to create the file file-name.

User Response: Determine the cause of the error condition and correct it or ask your system administrator for assistance.

PCSERR008 **Error seeking file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to move the file pointer in the file file-name.

User Response: Determine the cause of the error condition and correct it or ask your system administrator for assistance.

PCSERR100 **Error allocating** xxxx **bytes of memory from the Windows global memory heap. Close one or more Windows applications and try again.**

Explanation: Your Windows system does not have enough memory available for Personal Communications to execute the function you selected.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear. If the problem persists, select **Cancel** and ask your system administrator for assistance.

PCSERR101 **Error locking global memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to access the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR102 **Error unlocking global memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to yield the access right of the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR103 **Error page-locking global memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to page-lock the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR104 **Error page-unlocking global memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to page-unlock the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR105 **Error freeing global memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to return the memory to the Windows global memory heap.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR106 **Error reallocating** xxxx **bytes of memory from the Windows global memory heap. Close one or more Windows applications and try again.**

Explanation: Your Windows system does not have enough memory available for Personal Communications to execute the function you selected.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear. If the problem persists, select **Cancel** and ask your system administrator for assistance.

PCSERR110 **Error allocating local memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to allocate the memory from the Windows local memory heap.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR111 **Error locking local memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to access the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR112 **Error unlocking local memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to yield the access right of the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR113 **Error freeing local memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to return the memory to the Windows local memory heap.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR120 **Error allocating xxxx bytes of conventional memory. Close one or more Windows applications and try again.**

Explanation: Windows returned an error condition when Personal Communications attempted to allocate the memory that is accessed by the DOS program.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear.

If the problem persists, select **Cancel** to exit from Windows, unload unnecessary DOS terminate-and-stay-resident (TSR) programs, restart Windows; then try the operation again.

If the problem continues, select **Cancel** to exit from Windows, remove any unnecessary DOS device drivers from your **CONFIG.SYS** file. Turn your workstation off; then turn it on again. Restart Windows and try the operation again.

If the problem still continues, ask your system administrator for assistance.

PCSERR123 **Error freeing conventional memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to return the memory that is accessed by the DOS program.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR130 **Error allocating xxxx bytes of memory for Windows resources. Close one or more Windows applications and try again.**

Explanation: Your Windows system does not have enough memory available for Personal Communications to execute the function you selected.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear. If the problem persists, select **Cancel** and ask your system administrator for assistance.

PCSERR131 **Error locking resource memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to access the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR132 **Error unlocking resource memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to yield the access right for the memory.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR133 **Error freeing resource memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to return the memory to Windows.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR134 **Error loading resource memory.**

Explanation: Windows returned an error condition when Personal Communications attempted to load the data from the Personal Communications file.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR200 function-name **failed :** module-name
Out of memory. Close one or more Windows applications and try again.

Explanation: Windows returned an error condition when Personal Communications executed or loaded the Personal Communications module module-name. The function-name is either WinExec or LoadLibrary.

For each **additional message**:

Out of memory or Out of system resources.
Close one or more Windows applications and try again.

Explanation: Your Windows system does not have enough memory or system resources available to load the module module-name required for Personal Communications to execute the function you selected.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear. If the problem persists, select **Cancel** and ask your system administrator for assistance.

File not found.

Explanation: The module module-name was not found.

User Response: Install Personal Communications again. If the problem persists, ask your system administrator for assistance.

Path not found.

Explanation: A path was not found.

User Response: Install Personal Communications again. If the problem persists, ask your system administrator for assistance.

(all other additional messages)

Explanation: Personal Communications encountered an internal problem.

User Response: Install Personal Communications again. If the problem persists, ask your system administrator for assistance.

PCSERR210 **Error staring Windows timer. Close one or more Windows applications that use the timer such as CLOCK.EXE, then try again.**

Explanation: Enough other Windows applications are using the Windows timer resource so that no timer is available for Personal Communications to execute the function you selected.

User Response: Select **Retry** after closing one or more Windows applications. Repeat the retry operation until this error message does not appear. If the problem persists, select **Cancel** and ask your system administrator for assistance.

PCSERR211 **Error killing Windows timer.**

Explanation: Windows returned an error condition when Personal Communications attempted to free the timer resource for Windows.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSERR900 **Personal Communications cannot run in Windows' Real mode. Exit from Windows and start it in either Standard or Enhanced mode. Then start Personal Communications again.**

Explanation: You attempted to run Personal Communications in Windows real mode. Select **About Program Manager...** in the Help pull-down menu of the Windows Program Manager to check Windows mode.

User Response: Exit from Windows, restart Windows either in standard mode or in enhanced mode; then start Personal Communications again.

PCSERR999 **Personal Communications internal error:** module-name **-** yyyy**.**

Explanation: Personal Communications encountered an internal problem in the module module-name.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance and have the following information available:

Module name and error number shown in the message
Version of DOS, Windows, and Personal Communications
CONFIG.SYS file in root directory
AUTOEXEC.BAT file in root directory
SYSTEM.INI file in the Windows directory
WIN.INI file in the Windows directory
Workstation profile (**.WS**) in the Personal Communications directory.

PCSFLR002 **The Shared Folders program is still running; stop it before you quit Windows.**

Explanation: You attempted to exit Windows during **PCSFLR.EXE** execution.

User Response: Quit **PCSFLR.EXE** first, and then quit Windows.

PCSFLR003 **Vint21hD.386 is not loaded. Please add a statement for it to the [386Enh] section of the SYSTEM.INI file.**

Explanation: **Vint21hD.386** is not loaded.

User Response: Add the following line to the [386Enh] section of the **SYSTEM.INI** file, and then restart Windows.

DEVICE = drive-name:\path-name\VINT21D.386

PCSFLR007 **The Shared Folders program is already running.**

Explanation: You attempted to execute a PCSFLR while a PCSFLR is already being executed.

User Response: None.

PCSFT052 **System name has been defaulted.**

Explanation: No system name was found in the specified transfer request file.

User Response: The default system name has been assumed for the system name in the transfer request. Correct this error, as follows:

Enter, under System Name, an AS/400 name that performs transfer.

Save the transfer request file.

PCSFT101 **The AS/400 system detected a warning situation.**

Explanation: A warning condition was detected on the AS/400 system.

User Response: If you are performing interactive data transfer, the warning type is indicated in the text following the error code.

Do either of the following things:

To continue this transfer, if the continuation option has been specified, select **Continue**. Execution of the transfer request continues, ignoring this warning.

To discontinue this transfer request, select **Cancel**. Correct the error and reissue the transfer request.

If you are performing automatic data transfer, the transfer request is executed immediately after display of this message.

PCSFT201 **File is not a transfer request file.**

Explanation: The specified file is not a transfer request file. Or, this error might have occurred because this transfer request is incomplete or is of an incorrect format.

User Response: If you are performing interactive data transfer, specify another transfer request file name. Transfer request files can be listed by selecting **Open** from the File menu of the menu bar.

If you are performing automatic data transfer, specify a valid transfer request file name, then restart automatic data transfer.

PCSFT204 **PC file description file is required to transfer data.**

Explanation: To transfer data to an AS/400 data file, a file-description file is required. If a file description file has not been specified, the format and properties of the personal computer file are not known, making the transfer of records from the personal computer to an AS/400 data file impossible.

User Response: If you are performing interactive data transfer, do as follows:

Ensure that the AS/400 file name is valid. Then, check whether data is transferred to a data file or to a source file.

If you are transferring data to a data file, ensure that **Use PC file description** has been selected and that a valid file description file name has been specified.

If you are transferring data to a source file, ensure that **Use PC file description** has not been selected and that a valid record length has been specified.

Execute the data transfer request again.

If another message is displayed, indicating that no file-description file can be found, you will have to create a file-description file to enable the transfer of data to a data file. This can be done in one of the following ways.

If data from the AS/400 was first transferred to the personal computer and data is currently being returned from the AS/400, a file-description file should have been created when the data was first transferred to the personal computer.

If a file-description file was not created, it can be created by changing the Create AS/400-PC Transfer Request and selecting **Save Transfer Description**. Then, execute the Create AS/400-PC Transfer Request again. This creates a file-description file that can be used to transfer data to the AS/400.

To prevent overwriting of the data file, specify a temporary PC file name that differs from that of the data file being sent.

After data has been transferred and a file-description file has been created, delete this temporary data file. Change the name of the new file-description file to match the data file name and append extension **.FDF**.

After a file-description file has been created, start the Create PC-AS/400 Transfer Request, ensure that the file that has just been created has been specified, and complete the transfer request.

If the data to be transferred is other than that received from the AS/400, create a file-description file.

After creating a file-description file and prior to executing it again, ensure that the name specified in the Create PC-AS/400 Transfer Request is valid.

If you are performing automatic data transfer, change the transfer request by specifying a file-description file, using the data transfer panel.

For more information, see the recovery action description for interactive data transfer, explained previously.

After making these corrections, retry the transfer request.

PCSFT205 **Numeric data does not fit into range specified by digits.**

Explanation: The data will not fit in the AS/400 field because the value specified in the file-description file is too large. The number of columns for a decimal number (field size) has been specified in the file description for this field on the AS/400 system.

User Response: To avoid this error, match the field definitions in the file-description file and in the AS/400.

PCSFT206 **Total length of record exceeds 4096 bytes.**

Explanation: The length of the record being transferred exceeds 4096 bytes. The record length includes data, 2 bytes for null map offset, 2 bytes for the length portion of each variable-length field, and 1 byte for each field in the record, used to determine whether the field contains a null value.

User Response: Reduce the number of fields such that the length of one record does not exceed 4096 bytes. Then, execute the transfer request again.

PCSFT207 **This system does not support OPTIONS statement.**

Explanation: The transfer facility attempted to send an OPTIONS statement to the requested AS/400, but an error was returned from the AS/400 indicating that the AS/400 did not recognize that statement.

User Response: To continue this transfer request, press **OK**. The resulting data is displayed as if the OPTIONS statement had not been sent.

PCSFT211 **A value must be specified for field reference file name.**

Explanation: Field reference file name has not been specified.

User Response: If you are performing interactive data transfer, specify the name of the AS/400 file containing the field description of the data to be transferred as the field reference file name. Then, execute the transfer request again.

If you are performing automatic data transfer, specify a value for the field reference file name in the transfer request file, using the data transfer panel. Then restart automatic data transfer.

PCSFT212 **A value must be specified for FROM.**

Explanation: The transfer source file has not been specified.

User Response: If you are performing interactive data transfer, enter the name of the AS/400 file whose data is to be transferred. Then, execute the transfer request again.

If you are performing automatic data transfer, specify a value for the **file to be transferred** field in the transfer request file. Then, restart automatic data transfer.

PCSFT213 **A value must be specified for TO.**

Explanation: The transfer destination file has not been specified.

User Response: If you are performing interactive data transfer, enter the name of the AS/400 file to which data is to be transferred. Then, execute the transfer request again.

If you are performing automatic data transfer, specify a value for the transfer destination file in the transfer request file, using the data transfer panel. Then, restart automatic data transfer.

PCSFT215 **A value must be specified for the 'JOIN BY'.**

Explanation: Because two or more AS/400 file names have been specified as files to be transferred, specify the JOIN BY option.

User Response: If you are performing interactive data transfer, specify a condition for joining the files to be transferred, using the JOIN BY option. Then, execute the transfer request again.

If you are performing automatic data transfer, change the transfer request file by specifying a value for the JOIN BY option using the data transfer panel. Then, restart automatic data transfer.

PCSFT216 **Numeric data consists of too many columns for the AS/400 field. The maximum value is used.**

Explanation: Numeric data will not fit in the AS/400 field because it exceeds the specified number of columns. This error might also occur if a number has already reached the maximum value and it has more decimal positions than that defined for the AS/400 system. If this number is to be rounded up, it will become too large to fit in the AS/400 field.

User Response: To execute this transfer request, while ensuring that this error does not occur, ensure that the AS/400 file, PC file, and file-description file have been specified correctly in the transfer request. If they have been specified correctly, check the file-description file and AS/400 file, ensure that the field descriptions are correct and match the actual data for the record. If those descriptions are not correct, correct them to match the actual data. Then, execute the transfer request again.

Change the file-description file by using the PC edit program. Or, if the file-description file was created during data transfer from the AS/400 system to the personal computer, update that file-description file by executing that transfer request again.

When executing a transfer request again, change that AS/400-to-personal computer transfer request, to prevent overwriting of the data file, by specifying a temporary PC file name that differs from that of the data file being sent to the AS/400 system, as the transfer destination file.

After data has been transferred and a file-description file has been created, delete this temporary file. Change the name of the new file-description file to match the data file name and append extension **.FDF**.

If the AS/400, PC, and file-description files all are correct, the amount of file data might be too large to fit in the AS/400 field. In this case, correct the data before transfer. Or, change the transfer facility to enable use of the maximum value.

If you are performing automatic data transfer, the transfer facility continues execution of this transfer request without suspension. In this case, the field value to be transferred to the AS/400 is the maximum value that can fit in the specified AS/400 field (positive or negative, according to the original value).

PCSFT217 **Data types are not compatible.**

Explanation: Unable to convert all or part of the PC data to the data type specified in the AS/400 file description.

User Response: If you are performing interactive data transfer:

Ensure that the specified AS/400, PC data, and file-description file names are valid.

If these file names are valid, the file-description file might not describe the PC file data correctly. In this case, change the file-description file.

To change the file-description file, do either of the following things:

- If a file-description file was not created by the previous transfer request from the AS/400 to the personal computer, change this file-description file, using the PC edit program.
- If a file-description file was created by the previous transfer request from the AS/400 to the personal computer, update that file-description file by executing that transfer request again.

  When creating a file-description file, ensure that the data file being transferred to the AS/400 system is not overwritten. To prevent overwriting of this file, specify a temporary PC file name that differs from that of the data file, as the transfer destination file.

  After data has been transferred and a file-description file has been created, delete the temporary file. Change the name of the new file-description file to match the data file name and append extension **.FDF**.

Ensure that the AS/400 file description is valid. If it is not valid, modify it to match the data type prior to data transfer.

Be particularly careful when correcting this error. Incorrect data might result if an incorrect format is accidentally specified.

If you are performing automatic data transfer, follow the explanation given above for interactive data transfer. If one of the file names specified in the transfer request needs to be corrected, you must also change the transfer request file, using the **Create Data Transfer Request** screen.

PCSFT218 **Data in this field has too many decimal positions. Number will be rounded.**

Explanation: Either of the following things might have occurred.

The number of decimal positions in a PC data field is greater than the number of columns specified for the AS/400, extra bytes being significant digits (other than zero).

A number in a PC data field has too many decimal positions, such that if it is converted, it will be too large for the AS/400 field.

User Response: If you are performing interactive data transfer, do either of the following things:

If you opt to continue this transfer request, data is rounded up if the first digit of the extra data value is equal to or greater than 5, or is truncated if it is equal to or less than 4. If this number is too small to fit in the corresponding AS/400 field, it is truncated to zero. No notification is posted if this field data is rounded.

If you opt to discontinue this transfer, the remaining records in the PC file are not sent to the AS/400. Previously transferred records remain in the AS/400 file, however.

If you are performing automatic data transfer, the program continues execution of this transfer request, without suspension. The value in the PC file is rounded according to the specification made for the AS/400.

PCSFT219 **Data in this field is incorrect or does not match the PC data type.**

Explanation: One of the following things might have occurred.

Data in the PC field is not of the type specified in the file-description file. This condition occurs only if the file type is BASIC serial or BIFF.

Numeric data might contain bytes that cannot be converted.

The position of the decimal point in the numeric data might be incorrect. This file-description file might be incorrect or data might have been shifted.

During data transfer from BIFF, a specific error might have been detected.

User Response: To execute the transfer request, and to prevent the occurrence of this error, ensure that the AS/400, PC, and file-description files have been correctly specified in this transfer request. If they have been specified correctly, check the descriptions in the file-description file and AS/400 file. If either of these descriptions is incorrect, correct it to match the actual data. Then, execute the transfer request again.

PCSFT220 **Data in this field is too short for AS/400 field. Data will be padded.**

Explanation: During the transfer of character data from the personal computer to the AS/400, either of the following things occurred.

The data length of this field, specified in the file description file, is smaller than the specification made for this field for the AS/400.

Data found in the PC file is shorter than the length defined for this fixed-length field for the AS/400.

User Response: If you are performing interactive data transfer, do either of the following things:

If you opt to continue the transfer request, this field is embedded to match the specification made for this field for the AS/400. In the final character field, spaces are embedded to the right. This embedding must not affect the field value. The remaining fields of this record are automatically filled by the transfer program. No notification is posted.

If you opt to discontinue the transfer request, this record and subsequent data are not transferred to the AS/400. Previously transferred data remains in the AS/400 file, however.

If you are performing automatic data transfer, the program continues execution of this transfer request, without suspension. Transfer data is padded with spaces to the right to match the AS/400 specification. This embedding must not affect the field value.

If you do not want this embedding to be performed, ensure that the AS/400, PC, and file-description files have been specified correctly in the transfer request. If they have all been specified correctly, check the file description file and AS/400 file to ensure that the error field descriptions are valid and match actual data for this record.

If either of those descriptions is incorrect, correct it to match the actual data. Then, execute the transfer request again. Change the file-description file using a PC editing program. Or, update it by executing the transfer request again (when the personal computer file-description file

was created during data transfer from the AS/400 system to the personal computer).

To prevent overwriting of the data file being sent to the AS/400 system, specify a temporary PC file name that differs from that of the data file, as the transfer destination file.

After data has been transferred and a file-description file has been created, you can delete this temporary data file. Change the name of the new file-description file to match the data file name and append extension **.FDF**.

To avoid data embedding, the field length described in the file-description file must be equal to that defined for the AS/400.

PCSFT221 **Data in this field is too long for AS/400 field. Data will be truncated.**

Explanation: Character data longer than the specified transfer destination AS/400 field is defined in the file-description file, the extra characters being significant characters (characters other than spaces).

Or data, after conversion, might be longer than the specified AS/400 field due to the presence of shift characters (SO and SI).

User Response: If you are performing interactive data transfer, do either of the following things:

If you opt to continue this transfer request, data in this field is truncated to fit the AS/400 field. This results in loss of the original data. The transfer facility automatically removes all data from this point to the end of this field. No notification is posted.

If you opt to discontinue this transfer request, the current and subsequent records are not transferred to the AS/400. Previously transferred records remain in the AS/400 file, however.

If data is not truncated, ensure that the AS/400, PC, and file-description files have been specified correctly in the transfer request. If they have been specified correctly, check the file-description file and AS/400 file to ensure that the field descriptions are valid and match the actual data for this record. If any description is not valid, correct it to match the actual data. Then, execute this transfer request again.

To change the file-description file, use a PC edit program. If the file-description file was created during data transfer from the AS/400 system to the personal computer, update the description file by executing that request again. To prevent overwriting of the data file being sent to the AS/400, if such updating is performed, specify a temporary PC file name that differs from that of the data file, as the transfer destination file name.

After data has been transferred and a file-description file has been created, delete this temporary data file. Change the name of the new file-description file to match the data file name and append extension **.FDF**.

Execute this personal computer-to-AS/400 transfer request again. Ensure that the file-description file is valid and that the AS/400 file description matches the final AS/400 field. If this description is not correct, it must be changed before you can complete this transfer request.

To avoid data truncation, the field length specified in the file-description file must be equal to that specified in the AS/400 file.

If you are performing automatic data transfer, the transfer facility continues execution of this transfer request, without suspension, and performs data truncation.

If this error is caused by the presence of shift characters, change the descriptions in the file-description file and AS/400 file such that all record data is transferred to the AS/400 fields without data truncation.

PCSFT222 **Numeric data has too many digits for AS/400 field. Maximum value will be used.**

Explanation: Numeric data consists of too many columns to convert to AS/400 data. It will be replaced with the maximum value that is compatible with the AS/400 field.

User Response: Change the columns to match the contents of the file-description file and AS/400 field definition, such that this error does not occur.

PCSFT223 **Data for this field is missing. Default values will be used.**

Explanation: This field is defined in the file-description file and the AS/400 file, but does not exist in the PC data file.

User Response: If you are performing interactive data transfer, do one of the following things:

If you opt to continue the transfer request, this data-missing field is filled with an appropriate default character (spaces in character fields, zeros in numeric fields). If data is missing in this field of a subsequent record, no message will be posted.

If you opt to discontinue the transfer request, the records remaining in the PC file are not sent to the AS/400. Previously transferred records remain in the AS/400 file, however.

If a null value is missing from the field, the AS/400 file description must be corrected to specify that this field can contain a null value.

If you are performing automatic data transfer, the transfer facility continues execution of this transfer request, without suspension. In this case, any data-missing fields are filled with an appropriate character (spaces in numeric fields, zeros in numeric fields).

PCSFT224 **Data in this field exceeds PC filed size. Data will be lost.**

Explanation: A PC field longer than the specification in the file description file exists. This error occurs only during transfer of a BIFF file or a BASIC serial file, because these file types involve an explicit field delimiter.

User Response: To execute the transfer request, without this error occurring, ensure that the AS/400, PC, and file-description files have been specified correctly in the transfer request. If they have been specified correctly, check descriptions in the file-description file and AS/400 file. If either of these descriptions is not valid, correct it to match the actual data. Then, execute the transfer request again.

PCSFT225 **Data size in bytes and decimal positions must be equal for a No conversion file transfer.**

Explanation: During record transfer without conversion to an AS/400 file, the size (in bytes) or the number of decimal positions specified for the field does not match the file data format. When transferring data without conversion, the field descriptions must match exactly.

User Response: Field length definitions are not identical. The file-description file must be changed such that the two definitions match.

The definition in the file-description file must actually match the data format of the PC file without conversion. Correct the definition. Then, execute the transfer request again.

If you are performing automatic data transfer, the transfer program terminates automatically. The field length definitions are not identical. Change the length definition in either the file-description file or the AS/400 file, such that the two match. Ensure that the PC file definition matches the data format of the PC file without conversion. After correcting the field definition, execute the transfer request again.

PCSFT226 **PC data file is incorrect or version of the data format is not supported.**

Explanation: While transferring data from a PC data file to an AS/400 file, the transfer program found the PC data file is incorrect or the data format is not supported.

User Response: Check and correct the format of the PC file, and then try the operation again. Or ask your system administrator what version of the PC data file format is supported.

PCSFT230 **File is not a PC file-description file.**

Explanation: The name of the file-description file is incorrect or its contents are incorrect.

User Response: If you are performing interactive data transfer, correct the **File Description File Name**. Then, execute the transfer request again. (To display a list of existing file-description files when changing this prompt, click **Browse**.)

If you are performing automatic data transfer, change the transfer request by correcting the **File Description File Name** by using the data transfer panel. Then, execute the transfer request again.

If you created this file-description file, use a PC edit program to correct it. If this file-description file was created during data transfer from the AS/400 system to the personal computer and its file name has been specified correctly, it must be re-created.

PCSFT231 **File type is incorrect or missing in PC file-description file.**

Explanation: A record having an incorrect file-type (PCFT) specification was detected. A value other than 1–9 has been specified as the file type, or this PCFT record is not the second record in the file-description file (excluding comments).

User Response: Using a PC edit program, correct the file type specification or add a PCFT specification. Then, execute the transfer request again.

PCSFT232 **Field type is incorrect or missing in PC file-description file.**

Explanation: When retrieving information from the file-description file (PCFL), the transfer facility detected an incorrect field-type specification for a PCFL item.

User Response: Correct the field-type specification, using a PC edit program. Then, execute the transfer request again.

PCSFT233 **Field length is incorrect or missing in PC file-description file.**

Explanation: When retrieving information from the file-description file (PCFL), the transfer facility detected an incorrect field-length specification for a PCFL item.

User Response: Correct the field-length specification, using a PC edit program. Then, execute the transfer request again.

PCSFT234 **Field type not compatible with file type in PC file-description file.**

Explanation: The file-description file (PCFL) contains a field type that cannot be used with the specified file type.

User Response: Correct the field type or file type of the file-description file. Then, execute the transfer request again.

PCSFT235 **Field name is longer than 30 characters in PC file-description file.**

Explanation: The field name of a PCFL item in the file-description file (PCFL) is longer than the maximum number of characters (30 characters).

User Response: Correct the field name in the file-description file, using the PC edit program. This field name must exactly match the corresponding field name for the AS/400 (name of the field to which this data is to be transferred).

PCSFT236 **Incorrect record in PC file-description file.**

Explanation: The file-description file (PCFL) contains an incorrect record. The record type must begin with PCFT, PCFL, PCFO, or * (for a comment).

User Response: Correct or delete the record in the PC file-description file, using a PC edit program. Then, execute this transfer request again.

PCSFT237 **Incorrect decimal positions in PC file-description file.**

Explanation: The file-description file (PCFL) contains a record for which the number of decimal positions is incorrectly specified.

User Response: Correct the decimal position count field in the file-description file, using a PC edit program. Then, execute the transfer request again.

PCSFT238 **More than 256 fields in PC file-description file.**

Explanation: The file-description file (PCFL) contains too many field description records. A maximum of 256 field description records can be specified.

User Response: Using a PC edit program, reduce the number of field description records in the file-description file to reflect the first 256 fields only. This correction is needed only if the data file contains 256 fields. Otherwise, data cannot be transferred correctly.

PCSFT239 **File type specified more than once in PC file-description file.**

Explanation: The file-description file (PCFL) contains more than one PC file type specification.

User Response: Using a PC edit program, correct the file-description file such that the PC file type is specified only once. Then, execute the transfer request again.

PCSFT240 **Extra data was found at the end of record. Extra data will not be transferred.**

Explanation: The PC file contains an extra field that is not specified in the file-description file.

User Response: If you are performing interactive data transfer, do either of the following things:

If you select **OK**, extra data is not transferred to the AS/400. If the transfer program detects a second undefined data item in the file-description file, no message will be posted. All extra data in the PC file is ignored.

If you select **Cancel**, the remaining records in the PC file are not sent to the AS/400. Previously transferred records remain in the AS/400 file, however.

If you are performing automatic data transfer, the transfer facility continues execution of the transfer request, without suspension. Extra data is not transferred to the AS/400 system.

To prevent the occurrence of this error when executing a transfer request, ensure that the AS/400, PC, and file-description files have been specified correctly in the transfer request. If they have been specified correctly, check the descriptions in the file-description file and AS/400 file and ensure that any extra data in the PC data file has been defined.

PCSFT241 **Field name is missing in PC file-description file.**

Explanation: The field name of a PCFL item is missing from the file-description file.

User Response: Correct the PCFL item in the file-description file, using a PC edit program. Then, execute the transfer request again.

PCSFT242 **No PCFL records were found in PC file-description file.**

Explanation: No PCFL record was found in the file-description file. At least one PCFL record must be defined in a file-description file.

User Response: Add a valid PCFL item corresponding to the personal computer data file, using a PC edit program. Then, execute the transfer request again.

PCSFT243 **PC file-description file is empty.**

Explanation: No data was found in the file-description file.

User Response: Transfer data from the AS/400 system to the personal computer. Or, create a file-description file, using a PC edit program. Then, execute the transfer request again.

PCSFT244 **PC file contains no data records to transfer.**

Explanation: No data was found in the specified PC file. A PC data record cannot be transferred to the AS/400. If you are performing automatic data transfer, transfer is terminated.

User Response: The PC file must contain data to be transferred.

PCSFT245 **PC transfer request file is empty.**

Explanation: An attempt was made to open the transfer request file, but the specified file contained no data. If you are performing automatic data transfer, transfer is terminated.

User Response: If you are performing interactive data transfer, specify a valid transfer request file name.

PCSFT246 **No data was matched to the specified options.**

Explanation: Your request has been completed, but there was no data matched to the specified options.

User Response: None.

PCSFT251 **Invalid option in PC file-description file.**

Explanation: In a PCFO item in the file-description file, a number that does not correspond to a valid format or delimiter has been specified.

User Response: Specify a valid format and delimiter corresponding to the PC file. Correct the field description in the PCFO item. Then, execute the request again.

PCSFT252 **Record length is incorrect.**

Explanation: This transfer request is either too short (equal to or shorter than 13 bytes) or too long (equal to or longer than 4097 bytes).

User Response: Specify a valid value. Then, execute the request again.

PCSFT253 **Transfer request character cannot be translated.**

Explanation: The data transfer was terminated because a character could not be translated.

User Response: Check the file to be transferred and the specified translation table, and then execute the translation request again.

PCSFT254 **Untranslatable numeric data was found.**

Explanation: While transferring data, untranslatable numeric data was found.

User Response: Make sure each PC field type matches with the AS/400 field type.

PCSFT255 **Not connected to the host.**

Explanation: Connection to the AS/400 system has not yet been established.

User Response: Establish a connection with the AS/400 system with which you want to perform data transfer, then try the transfer request again.

PCSFT301 **Error detected by AS/400. Statement offset provided.**

Explanation: AS/400 detected an error.

User Response: If you are performing interactive data transfer, the error type will be indicated in the text output after error code 3000.

To correct this error, change the transfer request using the data transfer panel or correct it with the AS/400.

The IWSXXXX message, written during AS/400 job logging, provides detailed information.

PCSFT302 **Error detected by AS/400. No statement offset provided.**

Explanation: AS/400 detected an error.

User Response: The IWSXXXX message, written during AS/400 job logging, provides detailed information.

PCSFT305 **Number of records exceeds limit of the PC data file. The data transfer is terminated.**

Explanation: The number of the received records exceeded the limit of the PC data file. The records under the limit were received normally.

User Response: None.

PCSFT306 **Maximum number of transfer requests active.**

Explanation: The maximum number of transfer requests is currently active. You cannot start another transfer request.

User Response: Close one of the active transfer requests to start another transfer request.

PCSFT316 **The system is not a supported system.**

Explanation: Your specified system is not supported.

User Response: Specify the name of the supported system. Ask your system administrator for the name of the supported system.

PCSFT318 **Contact with the system ended.**

Explanation: The personal computer program is no longer communicating with the system for one of the following reasons:

The connection with the system was stopped.

A permanent error occurred and the program could not recover.

User Response: Correct the problem and establish a connection with the system again, then try your request again.

PCSFT319 **Contact with the system temporarily interrupted.**

Explanation: The personal computer program is no longer communicating with the system for one of the following reasons:

The connection with the system was stopped.

The cable connection to the system is defective or was disconnected.

The QBASE and QCMN subsystems are not started.

User Response: Correct the problem and establish a connection with the system again, then try your request again.

PCSFT320 **Resource failure on the system.**

Explanation: There are not enough resources available on the system to start the requested operation. This message is displayed in the one of the following cases:

The maximum number of sessions are already communicating with the system. No more session conversations are allowed.

There is not enough memory or disk space available on the AS/400 system to start the requested operation.

A system name was not found.

If using PC Support/400 pass-through, a connection to the requested system cannot be established.

The line controller or device is varied off on the AS/400 system.

The subsystem the device is attached to was not started or is ending.

There is a problem accessing objects associated with the user profile for the user ID that was used to sign on to the router.

User Response: Try your request again when the system resources are available. If possible, release one of the active sessions.

If there is a problem with the user profile information, the system operator message queue on the AS/400 system contains CPF1269, which indicates the reason for the failure. You can use this message information to determine the cause of the problem. You might need to start the router again to effect the change of the user profile.

PCSFT321 **Conversation with the system ended unexpectedly.**

Explanation: The previous active conversation with the system was ended unexpectedly. The conversation was ended for one of the following reasons:

The connection with the system was stopped.
A communication failure occurred.

User Response: Correct the problem and establish a connection with the system again, then try your request again.

PCSFT323 **Options not fully supported on this host system.**

Explanation: The OPTIONS statement sent to the AS/400 had keywords that are supported on the personal computer but are not supported on the AS/400 system. An earlier release of PC Support/400 is installed on your AS/400 system.

User Response: Your request is continued, but the keyword not supported on the host system and other keywords following the unsupported one are ignored. To avoid this error, check the release level of your AS/400 system to identify the supported keywords, and change your transfer request using only valid keywords.

PCSFT401 **Transfer request has been changed. Save changes ?**

Explanation: None.

User Response: Selecting **Yes** causes the transfer request save panel to appear.

PCSFT402 **Add this icon to the Program Manager ?**

Explanation: None.

User Response: Selecting **Yes** causes an icon to be registered with the contents of the current transfer request file. You can subsequently execute automatic data transfer simply by clicking this icon.

PCSFT403 **To start this transfer function with the modified definition, enter '**command**' in the command-line field of the 'File - Run' dialog box of the Program Manager.**

Explanation: You saved the transfer request without adding the icon to the Program Manager.

User Response: Select **OK**.

PCSFT404 **To start the transfer function that you have just saved, select the '**icon**' icon in the '**group-name**' program group.**

Explanation: You saved the transfer request and added the icon to the specified program group.

User Response: Select **OK**.

PCSFT405 **An icon was not added to the Program Manager.**

Explanation: You attempted to add a data transfer icon to the Program Manager, but the attempt failed.

User Response: None.

PCSFT406 **Error saving the transfer description :** file-name**.**

Explanation: An attempt was made to save the transfer request file, but it was not successful.

User Response: Ensure that the drive, directory, and file names are correct.

PCSFT410 **System name is incorrect or inactive.**

Explanation: Connection to the specified AS/400 system has not yet been established.

User Response: Establish a connection with the AS/400 system with which you want to perform data transfer, or specify the name of an AS/400 system with which you have already established a connection. Then try the transfer request again.

PCSFT411 **Syntax of system name is invalid.**

Explanation: The syntax of the system name specification is not valid.

User Response: Correct the system name specification. Then, execute the transfer request again. From the data transfer panel, you can view a list of AS/400s with which connection has been established.

PCSFT412 **A value must be specified for system name.**

Explanation: The system name has not been specified.

User Response: If you are performing an interactive data transfer, enter the system name. Then, execute the transfer request again.

If you are performing an automatic data transfer, specify the system name in the transfer request file, using the data transfer panel. Then, restart the automatic data transfer.

PCSFT420 **PC file to receive data records already exists. Do you want to overwrite it ?**

Explanation: The specified file already exists. This message requests confirmation of whether the file can be overwritten.

User Response: Selecting **Yes** causes the file to be overwritten.

PCSFT421 **Specified PC file was not found. Specify the correct PC file name.**

Explanation: The specified file does not exist.

User Response: Specify a valid file. Then, execute the transfer request again.

PCSFT422 **PC file name is incorrect. Specify the correct PC file name.**

Explanation: An incorrect file name has been specified.

User Response: The cursor is positioned on the field for which the incorrect file name was specified. Specify a valid file name. Then, execute the transfer request again.

PCSFT423 **Invalid syntax for the file name.**

Explanation: The syntax of the specified file name is not valid.

User Response: If you are performing an interactive data transfer, enter the correct file name. Then, execute the transfer request again.

If you are performing an automatic data transfer, specify the correct file name in the transfer request file, using the data transfer panel. Then, restart the automatic data transfer.

PCSFT424 **Sort sequence table name cannot be blank. The sort sequence choice has been reset to the AS/400 job default.**

Explanation: The sort sequence table name stored in the transfer request file is blank. When you selected **User specified table** in the Sort sequence list box, you left the **Sort sequence table name** field blank.

User Response: Specify the correct sort sequence table name. After changing the table name, save the transfer request file and try the transfer request again.

PCSFT425 **Language ID cannot be blank. The language choice has been reset to the AS/400 job default.**

Explanation: The language ID stored in the transfer request file is blank. When you selected **User specified language** in the Language list box, you left the **Language ID** field blank.

User Response: Specify the correct language ID. After changing the language ID, save the transfer request file and try the transfer request again.

PCSFT426 **You currently don't have a connection to the host. Before you can proceed you must establish a connection to the host by using the Data Transfer Utility program.**

Explanation: You executed the Data Transfer program, but no connection to the host has been established with it.

User Response: Establish a connection to the host from the **Communication** menu item of the Data Transfer Utility program.

PCSFT427 **Communication settings for ''host name'' have not been defined. Before you can proceed you must configure the communication settings to ''host name'' by using the Data Transfer Utility program.**

Explanation: You attempted to execute the Data Transfer program icon, but the communication settings to the "host name" has not been saved by the Data Transfer Utility program.

User Response: Establish a connection to the "host name" from the **Communication** menu item of the Data Transfer Utility program and save it, then select the icon again.

PCSFT999 **An unexpected error has been detected while processing transfer request.**

Explanation: None.

User Response: Report the problem to your system administrator.

PCSGRP001 **Too little space for the Retain Buffer.**

Explanation: There is not enough space in the Retain Buffer for the Graphic Re-drawing.

User Response: Terminate the application program, and select **Bitmap** in the **Redraw** field.

PCSHAM001 **The communication port number in your workstation profile is invalid.**

Explanation: An incorrect port number was used for the Hayes Autosync connection.

User Response: Change the port number to one that is available on your workstation.

PCSHAM002 **The SDLC station address is invalid. Only values from 01 to FE are allowed.**

Explanation: You selected **OK** in the Hayes Autosync Attachment dialog box, but the value in the **SDLC station address** entry field was not valid. Or, you attempted to start the Personal Communications workstation program with the profile specifying an incorrect SDLC station address.

User Response: Change the SDLC station address to the correct one in the Hayes Autosync Attachment dialog box.

PCSHAM003 **The PU ID in your workstation profile is invalid.**

Explanation: The PU ID specified in the workstation profile was not valid.

User Response: Make sure the correct PU ID is specified in the Hayes Autosync Attachment dialog box.

PCSHAM004 **The block ID in your workstation profile is invalid.**

Explanation: The block ID specified in the workstation profile was not valid.

User Response: Make sure the correct block ID is specified in the Hayes Autosync Attachment dialog box.

PCSHAM011 **The communication port selected is already being used by another application.**

Explanation: The selected port number was already used by another program.

User Response: Change the port number to one that is not currently used.

PCSHAM013 **Hayes Autosync attachment does not support multiple ports.**

Explanation: You attempted to connect multiple Hayes Autosync attachments. Only one Hayes Autosync connection can be used at the same time.

User Response: Reconfigure the Hayes Autosync connection.

PCSHAM051 **PCSHAM.EXE is already installed.**

Explanation: You attempted to execute **PCSHAM.EXE**, but it was already installed.

User Response: None.

PCSHAM052 **Invalid parameter is specified.**

Explanation: You attempted to execute **PCSHAM.EXE** with an incorrect parameter.

User Response: Remove or correct the incorrect parameter and try the operation again.

PCSHAM053 **PCSHAM.EXE cannot remove itself from resident memory.**

Explanation: You attempted to remove **PCSHAM.EXE** from the resident memory, but the attempt failed.

User Response: Reboot your system if you want to remove **PCSHAM.EXE**.

PCSHAM054 **More than 2 communication ports are not allowed.**

Explanation: You configured the Hayes Autosync configuration using more than two communication ports. The maximum number of communication ports is two.

User Response: Reconfigure the Hayes Autosync connection.

PCSHAM055 **Insufficient memory is available.**

Explanation: There was not enough memory to load **PCSHAM.EXE**.

User Response: Unload any unnecessary applications, device drivers, and memory-resident programs, and try the operation again. If the error persists, ask your system administrator for assistance.

PCSHBW001 **The DOS-mode EHLLAPI can be used only when Windows is running in 386 enhanced mode; this is not the case on your PC.**

Explanation: You are running Windows in standard mode. The DOS-mode EHLLAPI is not supported in standard mode.

User Response: Reconfigure your Windows to 386 Enhanced mode. Additional system memory might be required to run Windows in 386 enhanced mode on your workstation.

PCSHBW002 **The system settings will not allow you to use the DOS-mode EHLLAPI. Do you want to change the system settings now?**

Explanation: A required module to use the DOS-mode EHLLAPI was not loaded.

User Response: Select **Yes** to change the system settings to load the required module.

PCSHPO001 **The communication port number in your workstation profile is not valid.**

Explanation: An incorrect port number was used.

User Response: Change the port number to another that is available in your workstation.

PCSHPO002 **The line speed in your workstation profile is not valid.**

Explanation: The line speed specified in your workstation profile was not valid.

User Response: Make sure the correct line speed is specified in the IBM Global Network Connection window.

PCSHPO011 **The communication port selected is already being used by another application.**

Explanation: The selected port number was already used by another program.

User Response: Change the port number to another that is not used.

PCSHPO013 **IBM Global Network Connection does not support multiple ports.**

Explanation: You attempted to connect multiple IBM Global Network Connection attachments. Only one IBM Global Network Connection can be used at the same time.

User Response: Reconfigure the IBM Global Network Connection.

PCSINST001 **The Personal Communications installation program cannot run in Windows' real mode. Exit from Windows and start it in either standard or enhanced mode. Then start the Personal Communications installation program again.**

Explanation: You attempted to run the Personal Communications installation program in Windows real mode.

Select **About Program Manager...** in the Help pull-down menu of the Windows Program Manager to check Windows mode.

User Response: Exit Windows, restart Windows either in standard mode or in enhanced mode; then start the Personal Communications installation program again.

PCSINST002 **The Personal Communications installation program is already running. You can run only one installation program at a time.**

Explanation: You attempted to run the Personal Communications installation program when it was already running.

User Response: Close the Personal Communications installation program that is running before attempting to restart it.

PCSINST003 **Personal Communications installation will be aborted.**

Explanation: You selected **Cancel** during the installation operation. The installation process did not complete.

User Response: Start the installation process from the beginning again, if you are installing Personal Communications.

PCSINST010 **The Personal Communications installation program does not recognize the specified file:** file-name**.**

Explanation: You attempted to start the Personal Communications installation program with the file file-name in the parameter line.

User Response: Remove the incorrect file and try the operation again.

PCSINST011 **The Personal Communications installation program does not allow the parameter:** parameter**.**

Explanation: You attempted to start the Personal Communications installation program with an incorrect parameter.

User Response: Remove the incorrect parameter and try the operation again.

PCSINST018 **Do you want to migrate your 'private' files (macros, poppad, keyboard definitions, configurations, etc.) from the previous version of Personal Communications to the format for Version 4.1?**

Explanation: You are prompted to specify whether the installation program prepares almost the same environment as the previous version.

User Response: Select **Yes** to migrate your Personal Communications to Version 4.1. Select **No** to not migrate your Personal Communications and cancel the installation of Version 4.1.

PCSINST019 **File cannot be backed up to the source subdirectory. Please change the target drive or directory.**

Explanation: You specified the backup directory to the same directory where Personal Communications is being installed. The backup directory cannot be the same directory of Personal Communications.

User Response: Change the drive or directory for backup.

PCSINST020 **Do you want to overwrite the previous version of Personal Communications that is in the specified directory?**

Explanation: You specified the directory where the previous version of Personal Communications was installed as the target directory.

User Response: Select **Yes** if you do not care if the installation program destroys the previous version of Personal Communications. Otherwise, select **No** and specify another drive and directory.

PCSINST021 **File cannot be copied into the source subdirectory. Please change the target drive or directory.**

Explanation: You specified the source directory as the target directory.

User Response: Change the target directory and try the operation again.

PCSINST022 **Error creating the subdirectory. Please change the target drive or directory.**

Explanation: You specified a subdirectory that does not exist, but the Personal Communications installation program failed to create that subdirectory.

User Response: Change the target directory and try the operation again.

PCSINST023 **Personal Communications will be removed from your system.**

Explanation: You attempted to remove Personal Communications already installed in your workstation.

User Response: Select **OK** if you continue the operation. Select **Cancel** if you want to cancel the operation.

PCSINST030 **Personal Communications requires** xxxx **bytes of disk space on drive** disk-drive**: to complete the installation.**

Explanation: Your system does not have enough disk space available to copy the files on the disk disk-drive.

User Response: Delete unnecessary files on the disk disk-drive so that enough free space is available, and try the operation again.

PCSINST030 **Personal Communications requires** xxxx **bytes of disk space on drive DriveName: to complete the installation.**

Explanation: Your system does not have enough disk space available to copy the files on the disk DiskDrive.

User Response: Delete unnecessary files on the disk DiskName so that enough free space is available and try the operation again.

PCSINST031 **The files required to install Personal Communications cannot be found on the source diskette or in the fixed-disk subdirectory.**

Explanation: The files required to install Personal Communications were not found in the source diskette or hard disk subdirectory.

User Response: Try the operation again using the correct Personal Communications installation diskettes.

PCSINST040 **Error opening the Personal Communications file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to open the file file-name in either the installation source diskette/directory or target directory.

User Response: Check the status of the installation target directory, and try the operation again using the correct Personal Communications installation diskettes.

PCSINST041 **Error reading the Personal Communications file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to read the file file-name from the source diskette or disk.

User Response: Try the operation again using the correct Personal Communications installation diskettes.

PCSINST042 **Error writing the Personal Communications file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the file file-name to the installation target directory.

User Response: Check the status of the installation target directory, and try the operation again.

PCSINST045 **Error opening (reading, writing) the SYSTEM.INI file.**

Explanation: Windows returned an error condition when Personal Communications attempted to open, read, or write the **SYSTEM.INI** file.

User Response: Check if the **SYSTEM.INI** file is damaged and correct it. Then install Personal Communications again.

PCSINST050 **You are installing Personal Communications from a server. Will you share the program files with other users and copy only some private files onto your own PC's disk or onto your private drive on the server?**

Explanation: None.

User Response: Select **Yes** to share Personal Communications files, except some private files, with other users on the network. Select **No** to copy all Personal Communications files to your directory.

PCSINST060 **The 'private' files from the previous version will be deleted unless you save them. Do you want to save them?**

Explanation: You selected **Yes** both for PCSINST018 and PCSINST020 messages. The Personal Communications installation program does not destroy the previous version of private files even if you select **Yes** for the PCSINST020 message. (The private files are kept if possible.)

User Response: Select **Yes** if you want to save the previous version of private files. Then the message Please specify the drive and directory where you save the previous version of private files. appears.
Select **No** if you do not care if the installation program destroys the previous version of private files.

PCSINST100 **Icons for Personal Communications have been added to the** 'group-name' **program group. To start the first session, choose the Start/Configure icon.**

Explanation: The icons of workstation and the Batch Program have been added to the program group of Windows you specified.

User Response: Double-click the icon of **Start/Configure Session** or **Multiple Sessions** to start Personal Communications.

PCSINST101 **Icons for Personal Communications have not been added to the Program Manager. You must start the programs manually.**

Explanation: You selected **No** to add the icons of workstation and the batch program to the program group of Windows.

User Response: You have to start Personal Communications manually. At the Windows **Run...**, run **PCSWS.EXE** to start the workstation, and **PCSBAT.EXE** to start the batch program.

PCSINST102 **Icons for sessions that you have migrated from the previous release, together with the standard icons for the new release, have been added to the** 'group-name' **program group.**

Explanation: The icons of workstation and the batch program for the previous release have been automatically added to the program group of Windows you specified.

User Response: Double-click the icon of workstation or the batch program to start Personal Communications.

PCSINST110 **Your system file has been backed up:**

SYSTEM.INI has been copied to SYSTEM.PCS. WIN.INI has been copied to WIN.PCS.

Explanation: The Windows system setting files (**SYSTEM.INI** and **WIN.INI**) have been copied for backup, and they have been changed.

User Response: None.

PCSINST111 **Your system files have been backed up:**

SYSTEM.INI has been copied to SYSTEM.PCS. WIN.INI has been copied to WIN.PCS.

Explanation: Your DOS setting file (**CONFIG.SYS**) has been changed.

User Response: None.

PCSKBD001 file-name **cannot be found.**

Explanation: The file file-name was not found.

User Response: Make sure that the correct path and file name are given.

PCSKBD002 file-name **is not a valid file name.**

Explanation: The file file-name did not form a valid DOS file name.

User Response: Make sure that the correct file name is specified.

PCSKBD100 **The file:** file-name **is not a Personal Communications keyboard file.**

Explanation: The file file-name did not have a valid format for the Personal Communications keyboard file. This message sometimes appears if you have manually modified the keyboard file.

User Response: Make sure that the correct file name is given and if it is, re-create the Personal Communications keyboard file in the Customize Keyboard dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD101 **Unrecognized expression in keyboard file:** file-name**.**

expression: (unrecognized expression)

Explanation: There was an incorrect expression (*keyname=value*) found in the Personal Communications keyboard file file-name. This message sometimes appears if you have manually modified the keyboard file.

User Response: Re-create the Personal Communications keyboard file using the Customize Keyboard dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD110 **KeyboardName is not supported.**

Explanation: The keyboard KeyboardName attached to your workstation is not supported.

User Response: Change the keyboard to one supported by Personal Communications using the Windows Setup program, exit Windows, restart Windows; then try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD150 **Customize Keyboard dialog box is already open.**

Explanation: You selected **Customize** in the Keyboard Setup dialog box while the Customize Keyboard dialog box was already displayed in the other workstation window.

User Response: Close the Customize Keyboard dialog box in the other workstation window before attempting to select it.

PCSKBD151 file-name **has been changed. Save the changes?**

Explanation: You attempted to exit the Customize Keyboard dialog box without saving the changes.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel without exiting. The Customize Keyboard dialog box remains opened.

PCSKBD152 **Error writing keyboard file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the Personal Communications keyboard file file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSKBD160 **Unrecognized key action: KeyAction.**

Explanation: You attempted to select **OK** in the Customize Keyboard dialog box, but an unrecognized key action (KeyAction) was found in the edit field.

User Response: Select a key action from the List Of Key Actions; then select an appropriate arrow button and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD200 **The file:** file-name **is not a Personal Communications popup-keypad file.**

Explanation: The file file-name did not have a valid format as the Personal Communications pop-up keypad file. This message sometimes appears if you have manually modified the pop-up keypad file.

User Response: Make sure that the correct file name is given and if it is, re-create the Personal Communications pop-up keypad file in the Customize Popup Keypad dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD201 **Error in the dimensions of the popup keypad defined in popup-keypad file:** file-name**.**

dimension: Pad=xx**, Column=**yy**, Row=**zz**.**

Explanation: The dimensions (Pad=xx, column=yy, Row=zz) defined in the Personal Communications pop-up keypad file file-name were not in the supported range. This message sometimes appears if you have manually modified the pop-up keypad file.

User Response: Re-create the Personal Communications pop-up keypad file using the Customize Popup Keypad dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD202 **No key in the popup-keypad file:** file-name**.**

key: key-name**.**

Explanation: The key name (key-name) was not found in the Personal Communications pop-up keypad file file-name. This message sometimes appears if you have manually modified the pop-up keypad file.

User Response: Re-create the Personal Communications pop-up keypad file using the Customize Popup Keypad dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD203 **Unrecognized expression in popup-keypad file:** file-name**.**

expression: key-name**=**value**.**

Explanation: An incorrect expression (key-name=value) was found in the Personal Communications pop-up keypad file file-name. This message sometimes appears if you have manually modified the pop-up keypad file.

User Response: Re-create the Personal Communications pop-up keypad file using the Customize Popup Keypad dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD210 **Error in the dimension of the popup keypad.**

dimension: Pad=xx**,Column=**yy**,Row=**zz**.**

Explanation: A Personal Communications internal error was detected in the pop-up keypad operation.

User Response: Ask your system administrator for assistance.

PCSKBD250 **Customize Popup Keypad dialog box is already open.**

Explanation: You attempted to select **Customize** in the Popup Keypad Setup dialog box while the Customize Popup Keypad dialog box was already displayed in the other workstation window.

User Response: Close the Customize Popup Keypad dialog box in the other workstation window before attempting to select it.

PCSKBD251 file-name **has been changed. Save the changes?**

Explanation: You attempted to exit the Customize Popup Keypad dialog box without saving the changes.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel without exiting. The Customize Popup Keypad dialog box remains opened.

PCSKBD252 **Error writing popup-keypad file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the Personal Communications pop-up keypad file file-name.

User Response: Determine the cause of the error condition and correct it or, ask your system administrator for assistance.

PCSKBD300 **The file:** file-name **is not a Personal Communications mouse file.**

Explanation: The file file-name did not have a valid format for a Personal Communications mouse file. This message sometimes appears if you have manually modified the mouse file.

User Response: Make sure that the correct file name is given and if it is, re-create the Personal Communications mouse file using the Customize Mouse dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD301 **Unrecognized key expression in mouse file:** file-name**.**

key expression: key-name**.**

Explanation: The key name (key-name) was not found in the Personal Communications mouse file file-name. This message sometimes appears if you have manually modified the mouse file.

User Response: Re-create the Personal Communications pop-up keypad file using the Customize Mouse dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD302 **Unrecognized expression in mouse file:** file-name**.**

expression: key-name**=**value**.**

Explanation: An incorrect expression (key-name=value) was found in the Personal Communications mouse file file-name. This message sometimes appears if you have manually modified the mouse file.

User Response: Re-create the Personal Communications mouse file using the Customize Mouse dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD350 **Customize Mouse dialog box is already open.**

Explanation: You attempted to select **Customize** in the Mouse Setup dialog box while the Customize Mouse dialog box was already displayed in the other workstation window.

User Response: Close the Customize Mouse dialog box in the other workstation window before attempting to select it.

PCSKBD351 file-name **has been changed. Save the changes?**

Explanation: You attempted to exit the Customize Mouse dialog box without saving the changes.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel without exiting. The Customize Mouse dialog box remains opened.

PCSKBD352 **Error writing mouse file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the Personal Communications mouse file file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSKBD400 **The file:** file-name **is not a Personal Communications macro file.**

Explanation: The file file-name did not have a valid format for a Personal Communications macro file. This message sometimes appears if you have manually modified the macro file.

User Response: Make sure that the correct file name is given and if it is, re-create the Personal Communications macro file in the Customize Macro dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD401 **No macro file can be found in the directory:** directory-name**.**

Explanation: No Personal Communications macro file was found in the directory directory-name.

User Response: Make sure that the Personal Communications macro file exists in the directory and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD402 **Unrecognized expression in macro file:** file-name**.**

expression: value**.**

Explanation: An incorrect expression (value) was found in the Personal Communications macro file file-name. This message sometimes appears if you have manually modified the macro file.

User Response: Re-create the Personal Communications macro file using the Customize Macro dialog box and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD410 **Macro:** macro-name **cannot be found.**

Explanation: The macro macro-name was not found in the macro table currently loaded.

User Response: Close the Personal Communications workstation program, restart it and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD450 **Customize Macro dialog box is already open.**

Explanation: You attempted to select **Customize** in the Macro Setup dialog box while the Customize Macro dialog box was already displayed in the other workstation window.

User Response: Close the Customize Macro dialog box in the other workstation window before attempting to select it.

PCSKBD451 file-name **has been changed. Save the changes?**

Explanation: You attempted to exit the Customize Macro dialog box without saving the changes.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel without exiting. The Customize Macro dialog box remains opened.

PCSKBD452 **The file:** file-name **is not a Personal Communications macro file. The file extension must be "MAC".**

Explanation: The file file-name is not a Personal Communications macro file.

User Response: Make sure that the correct file name and file extension are given, and then try the operation again. If the problem persists, install Personal Communications again.

PCSKBD453 **Macro file:** file-name **is too large.**

Explanation: You attempted to open the file file-name in the Customize Macro dialog box, but it was too large.

User Response: Make sure that the given file is the Personal Communications macro file and try the operation again. If the problem persists, install Personal Communications again.

PCSKBD460 **Unrecognized key action in the highlighted line.**

Explanation: You attempted to save the macro into the macro file in the Customize Macro dialog box, but an unrecognized key action was found in the macro statements.

User Response: Select a key action from the List of Key Actions or type any interspersed text strings necessary to complete the macro; then try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD461 **Macro:** macro-name **cannot be found. Please create it, otherwise this macro will not work correctly.**

Explanation: You attempted to save the macro into the macro file in the Customize Macro dialog box, but the macro used in the current macro does not exist.

User Response: Follow the instruction in the message and create the macro referred to by the current macro. Otherwise, when you invoke the current macro, you will get an error message.

PCSKBD462 **String in the highlighted line is too long.**

Explanation: You attempted to save the macro into the macro file in the Customize Macro dialog box, but the macro in the highlighted line was too long.

User Response: Change the macro expression so that it does not exceed 253 characters and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSKBD500 **The label name '**label-name**' was not found in '**macro-name**'.**

Explanation: You specified the target label label-name followed by the GOTO statement, but it was not found in the macro.

User Response: Check if the label name exists in the macro, and then add or correct the required label in the macro.

PCSKBD501 **Invalid label name was found in '**macro-name**'.**

Explanation: An incorrect expression of label name was found in the macro. The possible reasons that cause the error are as follows:

A character other than alphabetic characters (A–Z) and numeric characters (0–9) is used.

The length of the label name exceeds 32 characters.

The label name is defined as the case-sensitive character string.

User Response: Identify the cause of the error, and then remove or correct the label name in the macro.

PCSKBD502 **The label name '**label-name**' already exists in '**macro-name**'.**

Explanation: A duplicate label name was found in the macro.

User Response: Change one of the label names to an appropriate one.

PCSMGRT5001 **PC Support migration will be terminated.**

Explanation: The conversion of a PC Support configuration file was not completed because you selected **Cancel**, or an error occurred during the operation.

User Response: Execute the conversion again from the beginning.

PCSMGRT5002 **The file:** file-name **is not a configuration file for PC Support.**

Explanation: The **CONFIG.PCS** file in the specified directory is not a valid format for a PC Support configuration file.

User Response: Specify a directory to which a valid PC Support configuration file has been saved.

PCSMGRT5003 Only the twinaxial router type (5250) can be migrated.

Explanation: The routing facility program of the **CONFIG.PCS** file in the specified directory is not the twinaxial type.

User Response: Specify a directory in which a configuration file containing a twinaxial routing facility program (RTYP is 5250) has been saved.

PCSMGRT5004 Only standard DOS version can be migrated.

Explanation: The **CONFIG.PCS** file-specified directory is for extended DOS.

User Response: Specify a directory to which a PC Support program for other than the extended version of DOS (excluding the PCSXI description in the **STARTPCS.BAT** file) has been saved.

PCSMGRT5007 To start this session with the modified definitions, enter 'PCSWS.EXE file-name**' in the command-line field of the 'File - Run' dialog box of the Program Manager.**

Explanation: A workstation program icon for the created profile has not been added to the specified program group.

User Response: When you next start a Personal Communications workstation program, follow the directions given in this message.

PCSMGRT5008 To start the workstation (session) that you have just saved, select the 'workstation**' icon in the '**group-name**' program group.**

Explanation: A workstation program icon for the created profile has been added to the specified program group.

Explanation: When you next start a Personal Communications workstation program, follow the directions given in this message.

PCSMGRT5009 An icon was not added to the Program Manager.

Explanation: When Personal Communications attempted to add a workstation program icon to the Windows program manager, Windows returned an error.

User Response: Retry the operation. If this error persists, contact the system administrator.

PCSMP001 The Gateway name is not specified or is not valid.

Explanation: The fully qualified OS/2 gateway name is not specified correctly.

User Response: Enter the correct OS/2 gateway name to which this workstation should be connected.

PCSMP002 AnyNet for Windows is not loaded successfully.

Explanation: An attempt to load AnyNet for Windows has failed.

User Response: Check whether AnyNet for Windows is installed correctly. If it's installed successfully, check the path is set to the directory where MPTNCMM.DLL resides.

PCSMP003 **AnyNet for Windows is not available for use.**

Explanation: An attempt to load AnyNet for Windows has failed.

User Response: Close the other applications or other sessions that have been using AnyNet.

PCSMT001 **The file : INSTCSD.EXE or PTF.TXT cannot be found in the source drive and directory. Please insert another diskette or name a different drive and directory.**

Explanation: You attempted to install a CSD or apply a PTF, but there is no required component. This operation has been canceled.

User Response: Insert a correct CSD diskette (diskette-1) or specify the correct drive and directory for the CSD diskette, and try the operation again.

PCSMT002 **The file : PCSPROD.INF or PCSMAINT.TXT cannot be found in the target drive and directory. This fix has not been applied.**

Explanation: You attempted to apply a PTF, but there is no required component. This operation has been canceled.

User Response: Specify the correct target drive and directory to install the CSD diskette or apply your APAR fix diskette.

PCSMT003 **The file :** file-name **cannot be found in the source drive and directory. Please check your APAR Fix diskette.**

Explanation: You attempted to apply a PTF, but there are no fixed modules, which are listed in **PTF.TXT**, in your APAR fix diskette.

User Response: Check if there are necessary files to apply a PTF in your APAR fix diskette. If you cannot find them, contact an IBM representative to get a correct APAR fix diskette.

PCSMT004 **This APAR fix is not applicable to this Personal Communications.** version-name **is required to apply this APAR fix.**

Explanation: You attempted to apply a PTF, but the base level of the Personal Communications did not match your APAR fix diskette.

User Response: Contact an IBM representative to get a correct APAR fix diskette.

PCSMT005 **File :** file-name **cannot be found.**

Explanation: You attempted to view the CSD information, but there was no **APAR327 .LST** or **APAR525 .LST** found in your CSD diskette. The Display CSD Information operation has been canceled.

User Response: Contact an IBM representative to get the correct Personal Communications CSD diskettes.

PCSMT006 **PCSMAINT.EXE failed: PCSPROD.INF or PCSMAINT.TXT not found.**

Explanation: You attempted to apply a PTF by executing **PCSMAINT.EXE**, but there was no **PCSPROD.INF** or **PCSMAINT.TXT** in the current drive and directory, which is required to apply a PTF.

User Response: Check if there is **PCSPROD.INF** or **PCSMAINT.TXT** in the current drive and directory. If it is not found, install Personal Communications, a CSD, or APAR fix again.

PCSMT007 **Personal Communications is active. You must terminate it before you apply a fix.**

Explanation: You attempted to apply a PTF, but Personal Communications was running.

User Response: Terminate Personal Communications before applying a PTF.

PCSMT011 **Error happened while Opening the Personal Communications file :** file-name**. Please retry the operation.**

Explanation: You attempted to apply a PTF, but a critical error occurred in opening a file.

User Response: Check that your APAR fix diskette is not damaged, and retry the operation.

PCSMT012 **Error happened while reading the Personal Communications file :** file-name**. Please retry the operation.**

Explanation: You attempted to apply a PTF, but a critical error occurred in reading a file.

User Response: Check that your APAR fix diskette is not damaged, and retry the operation.

PCSMT013 **Error happened while writing the Personal Communications file :** file-name**. Please retry the operation.**

Explanation: You attempted to apply a PTF, but a critical error occurred in writing a file.

User Response: Check that the target disk is not damaged, and retry the operation.

PCSMT015 **Error happened while writing the Personal Communications file:** file-name **because the disk is full. Please clear some disk space and retry the operation.**

Explanation: You attempted to apply a PTF, but there was no space to save the fix modules on the disk.

User Response: Erase unnecessary files to make free space on the disk, and then try the operation again.

PCSMT016 **A file could not be copied. Perhaps the disk is full or you are not authorized to write.**

Explanation: You attempted to apply a PTF, but the target drive has a problem as follows:

There is no space to save the fix modules on the disk.
When the target drive is a network drive, it is a read-only drive.

User Response: If the target disk is full, erase unnecessary files to make free space on the disk. When the target drive is a network drive and you do not have authorization to write, contact your system administrator.

PCSNTC001 **FMI initialization failed.**

Explanation: An attempt to initialize FMI failed. The server might be down or might not be connected to your workstation.

User Response: Check the connection and the condition of the server.

PCSNWCS001 **The server Name specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect Server Name for the LAN via NetWare for SAA attachment. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct Server Name in the **Server Name** entry field in the LAN via NetWare for SAA dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSNWCS002 **The User Name specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect User Name for the LAN via NetWare for SAA attachment. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct User Name in the **User Name** entry field in the LAN via NetWare for SAA dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSNWCS003 **The Service Name specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect Service Name for the LAN via NetWare for SAA attachment. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct Service Name in the **Service Name** entry field in the LAN via NetWare for SAA dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSNWCS004 **The LU Category specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect LU category for the LAN via NetWare for SAA attachment. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct LU Category in the **LU Category** entry field in the LAN via NetWare for SAA dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSNWCS005 **The LU Name (or LU Pool Name) specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect LU Name (or LU Pool Name) for the LAN via NetWare for SAA attachment. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct LU Name (or LU Pool Name) in the **LU Name** (or **LU Pool Name**) entry field in the LAN via NetWare for SAA dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSNWCS006 **The trace buffer size specified in your Workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect trace buffer size for the LAN via NetWare for SAA attachment. Only values from 1 to 63 are allowed.

User Response: Modify the trace buffer size entry of your workstation profile; then try the operation again.

PCSNWCS007 **The trace entry size specified in your Workstation profile is invalid. Default value (576 bytes) will be used instead.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect trace entry size for the LAN via NetWare for SAA attachment. Only values from 576 to 16384 are allowed.

User Response: You can continue your operation, but you should modify the trace entry of your workstation profile.

PCSNWCS101 **Invalid character is specified.**

Explanation: You selected **OK** in the LAN via NetWare for SAA dialog box, but specified an incorrect character in the entry field.

User Response: Type an correct character in the entry field.

PCSNWCS102 **Required parameter is not specified.**

Explanation: You selected **OK** in the LAN via NetWare for SAA dialog box, but specified nothing in the entry field.

User Response: Fill in the entry field, and try again.

PCSNWCS103 **Invalid character specified for your password.**

Explanation: Your selected **OK** in the LAN via NetWare for SAA Password dialog box, but specified an incorrect character in the entry field.

User Response: Type a correct character in the entry field.

PCSNWCS201 **NWIPXSPX.DLL initialization error.**

Explanation: Attempt to load **NWIPXSPX.DLL** failed. **NWIPXSPX.DLL** does not exist on the Windows subdirectory.

User Response: Install **NWIPXSPX.DLL** to your Windows subdirectory. For more information, refer to online help *Set up Windows for LAN via NetWare for SAA attachment*.

PCSNWCS301 **The connection request is canceled.**

Explanation: The connection request was canceled. You might have selected **Cancel** in the LAN via NetWare for SAA Password dialog box, or some network error occurred when the dialog box was displayed.

User Response: Disconnect and reconnect to establish the communication.

PCSNWCS401 **IPX/SPX protocol driver is not installed.**

Explanation: IPX/SPX protocol was not available in your workstation.

User Response: Make sure the correct version of DOS IPX/SPX driver is installed before starting Windows, and your Windows is set up correctly for LAN via NetWare for SAA attachment. For more information, refer to online help.

PCSNWCS402 **SPX Initialization Failure: return code -** xx**.**

Explanation: NetWare IPX/SPX driver failed its initialization.

User Response: Ask your system administrator for assistance.

PCSNWCS403 **Socket Open Failure: return code -** xx**.**

Explanation: NetWare IPX/SPX driver failed to open a socket.

User Response: Ask your system administrator for assistance.

PCSNWCS501 **This attachment is available only when Windows is running on 386 Enhanced mode.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the LAN via NetWare for SAA attachment although your Windows is running in Standard Mode.

User Response: Start up your Windows in 386 Enhanced Mode.

PCSPCO001 **DisplayWrite is not supported.**

Explanation: You cannot use the DisplayWrite program in PC400.

User Response: Change the editing program to Office Vision/400.

PCSPCO002 **PCO command processor (PCSPCOC.EXE) failed: WinExec return code -** xx**.**

Explanation: When PC400 attempted to execute the PCO command processing program, Windows returned an error status.

User Response: Install PC400 again, and then retry the operation. If this error persists, contact your system administrator.

PCSPCO003 **Application** program-name **is already running.**

Explanation: The program program-name specified is already running in Windows.

User Response: Stop the active application program; then run the program again.

PCSPD010 **Printer has not been selected. The Windows default printer will be used instead.**

To select a printer, select Printer Setup in the File pull-down menu.

Explanation: The printer was not selected for this workstation.

User Response: Select the printer using **Printer Setup...** in the File menu bar command. The Windows default printer is selected if the printer is not selected.

PCSPD020 printer-name **cannot be found. The Windows default printer will be used instead.**

Explanation: The specified printer was not found.

User Response: Install the specified printer using **Printers** in the Control Panel of the Program Manager, or select another printer using **Printer Setup...** in the File menu bar command.

PCSPD050 **The Windows default printer has been not selected. Print canceled.**

Explanation: The print function was canceled because the Windows default printer was not selected.

User Response: Select the printer using **Printer Setup...** in the File menu bar command, or select a default printer using **Printers** in the Control Panel of the Program Manager.

PCSPD060 printer-name **is not active. Print canceled.**

Explanation: The specified printer was not active.

User Response: Activate the printer using **Printers** in the Control Panel of the Program Manager.

PCSPD070 **The Windows default printer has been not selected. Font list is empty.**

Explanation: The font list for the printer was empty because the printer was not selected.

User Response: Select the printer for the font using **Printer Setup...** in the File menu bar command.

PCSPD080 printer-name **is not assigned to Printer. Print canceled.**

Explanation: The specified Printer Name has not been assigned to the printer.

User Response: Select the printer by using **Printer Setup...** in the File menu bar, or by using **Printer** in the Control Panel of the Program Manager.

PCSPD090 **Not enough disk space for spooling.**

Explanation: There was not enough disk space in your workstation for printing.

User Response: Delete unnecessary files from your disk, and try the print operation again.

PCSPD091 **Not enough memory space for spooling.**

Explanation: There was not enough memory space in your workstation for printing.

User Response: Close one or more Windows applications and try the print operation again.

PCSPD092 **General print error. Command:** xxxx**.**

Explanation: A printer error was reported from the printer driver.

User Response: If this error message is displayed before the previous print job is finished, try the operation again after it is finished. Ask your system administrator for assistance if you continue to get this message.

PCSPD093 **File operation error. Please refer to Personal Communications Help.**

Explanation: During the print-to-disk operation, one of the following file I/O errors occurred.

Access denied	You attempted to write in a read-only file.
Write protected	The specified disk is write-protected.
Drive not ready	The specified disk drive is not ready to read.
Disk full	The free disk space is not large enough.

User Response: Remove the cause of the file I/O error, and then select the **Retry** button.

PCSPD120 **The Host Print Transform function is provided by OS/400 V2R3 or later.**

Explanation: The Host Print Transform function is provided by OS/400 V2R3 or later.

User Response: Check off the Host Print Transform function in the advanced session configuration.

PCSPFC000 **Converting** file-name1 **to** file-name2**.**

Explanation: PFT migration utility (**PCSPFC.EXE**) is converting the printer function table (PFT) file to the printer definition file (PDF) file.

User Response: None.

PCSPFC001 **PFT conversion completed successfully.**

Explanation: The conversion from PFT to PDF was completed successfully.

User Response: None.

PCSPFC002 **PFT conversion completed with** xx **errors.**

Explanation: The conversion from PFT to PDF was completed, but errors occurred.

User Response: Correct the errors, and execute the conversion again if necessary.

PCSPFC003 **PFT conversion failed with** xx **errors.**

Explanation: The conversion from PFT to PDF failed because errors occurred.

User Response: Correct the errors and execute the conversion again.

PCSPFC004 **Fatal error: Cannot open file:** file-name**.**

Explanation: The conversion from PFT to PDF failed because the PFT migration utility could not open the file.

User Response: Check the file and try the operation again.

PCSPFC005 **Cannot close file:** file-name**.**

Explanation: The conversion from PFT to PDF failed because the PFT migration utility could not close the file.

User Response: Check the file and try the operation again.

PCSPFC006 **Cannot delete file:** file-name**.**

Explanation: The conversion from PFT to PDF failed because the PFT migration utility could not delete the file.

User Response: Check the file and try the operation again.

PCSPFC007 **Cannot read file:** file-name**.**

Explanation: The conversion from PFT to PDF failed because the PFT migration utility could not read the file.

User Response: Check the file and try the operation again.

PCSPFC008 **Cannot write file:** file-name**.**

Explanation: The conversion from PFT to PDF failed because the PFT migration utility could not write the file.

User Response: Check the file and try the operation again.

PCSPFC009 **File** file-name **is not a PFT file.**

Explanation: The conversion from PFT to PDF failed because the specified file was not a PFT file.

User Response: Check the file and try the operation again.

PCSPFC010 **Cannot migrate** PDF-field-name**.**

Explanation: No data was converted into the PDF-field-name.

User Response: Check the file and try the operation again, or specify the data at the field in the PDF file.

PCSPOLL051 **PCSPOLL.EXE is already installed.**

Explanation: You attempted to load **PCSPOLL.EXE**, but it was already installed.

User Response: None.

PCSPOLL052 **Invalid parameter is specified.**

Explanation: You attempted to execute **PCSPOLL.EXE** with an incorrect parameter.

User Response: Remove or correct the incorrect parameter and try the operation again.

PCSPOLL053 **PCSPOLL.EXE cannot remove itself from the resident memory.**

Explanation: You attempted to remove **PCSPOLL.EXE** from the resident memory, but the attempt failed.

User Response: Re-boot your system if you want to remove **PCSPOLL.EXE**.

PCSPOLL054 **Memory allocation error. The buffer size specified with the /B option is too large.**

Explanation: There was not enough memory to execute **PCSPOLL.EXE**.

User Response: Decrease the buffer size specified with */B* option, or unload any unneeded applications, device drivers, and memory-resident programs. If the error persists, ask your system administrator for assistance.

PCSRBW001 **The system settings will not allow you to use the PC Support/400 functions.**

Do you want to change the system settings now?

Explanation: A module required to use PC Support/400 has not yet been loaded.

User Response: To change the system settings and load the required module, select **Yes**.

PCSRTR001 **The PC Support/400 router has not been started.**

Explanation: The PC Support/400 router has not been started or it has terminated abnormally.

User Response: Exit Windows, and then start the router program.

PCSRTR002 **The PC Support/400 Windows compatibility module has not been installed.**

Explanation: The PC Support/400 Windows compatibility module (**PCSWIN.EXE**) has not been installed.

User Response: Exit Windows, and then install the PC Support/400 Windows compatibility module. Ensure that the Microsoft Windows option is specified in the PC Support/400 configuration.

PCSRTR003 **The communication buffer for the PC Support/400 Windows compatibility module is too small.**

Explanation: The communication buffer for the PC Support/400 Windows compatibility module (**PCSWIN.EXE**) is too small.

User Response: Specify a larger value for the /B= parameter for the PC Support/400 Windows compatibility module in the PC Support/400 startup program **STARTPCS.BAT** file. With PC400, each session requires 6 KB.

PCSRTR004 **The AS/400 system is not active.**

Explanation: Communication has not been established with the specified host.

User Response: Ensure that a valid host system is specified in the PC Support/400 configuration.

PCSRTR010 **The PC Support/400 router cannot allocate the memory. Please terminate application programs that you are not using.**

Explanation: The PC Support/400 router cannot allocate the conventional memory that is required to perform the request.

User Response: Terminate the application programs that are not used or remove the unnecessary TSR program and start Windows again.

PCSRTR021 **The Network Services program has not been started.**

Explanation: The Network Services program has not been started or it has terminated abnormally.

User Response: Start the Network Services program.

PCSSDLC001 **The SDLC station address is invalid. Only values from 01 to FE are allowed.**

Explanation: You selected **OK** in the SDLC Attachment dialog box, but the value in the **SDLC station address** entry field was not valid. Or, you attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an unrecognized SDLC station address. This message sometimes appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct Link Address in the **SDLC Station Address** entry field in the SDLC Attachment dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSSDLC002 **The PU ID in your workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile, specifying an unrecognized PU ID for the synchronous data link connection. This message sometimes appears if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct PU ID in the **Physical Unit ID** entry field in the SDLC Attachment dialog box; then try the operation again. If the problem persists, install Personal Communications again.

PCSSDLC003 **The block ID in your workstation profile is invalid.**

Explanation: You attempted to start the Personal Communications workstation program with a profile, or attempted to open a profile, specifying an unrecognized block ID for the synchronous data link connection. This message might appear if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct block ID in the **Block ID** entry field in the SDLC Attachment dialog box; then try the operation again. If the problem persists, install Personal Communications again.

PCSSDLC010 **An SDLC adapter has not been installed.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through synchronous data link connection, but the adapter was not found.

User Response: Make sure that the adapter for the synchronous data link connection is installed on your workstation and the adapter number specified in your profile matches the installed adapter number, and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSSDLC011 **PCSSDLC.EXE has not been installed correctly. Add /N=2 to the PCSSDLC.EXE command.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the synchronous data link connection, but **PCSSDLC.EXE** (DOS TSR program) was not installed correctly before Windows was started. This message appears, for example, when you attempt to use multiple SDLC cards, but installed **PCSSDLC.EXE** for only one adapter card.

User Response: Exit Windows and run **PCSEND.EXE** from the DOS prompt to remove **PCSSDLC.EXE**. (If you have started Windows by invoking **PCSWIN.BAT** instead of **WIN.COM**, you might not need to run **PCSEND.EXE** because **PCSSDLC.EXE** is removed automatically when you exit Windows.) Run **PCSSDLC.EXE** with the /N=2 parameter, restart Windows, and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSSDLC051 **PCSSDLC.EXE is already installed.**

Explanation: You attempted to load **PCSSDLC.EXE**, but it was already installed.

User Response: None.

PCSSDLC052 **Invalid parameter is specified.**

Explanation: You attempted to execute **PCSSDLC.EXE** with an incorrect parameter.

User Response: Remove or correct the incorrect parameter and try the operation again.

PCSSDLC053 **PCSSDLC.EXE cannot remove itself from the resident memory.**

Explanation: You attempted to remove **PCSSDLC.EXE** from the resident memory, but the attempt failed.

User Response: Re-boot your system if you want to remove **PCSSDLC.EXE**.

PCSSDLC054 **More than 2 SDLC Adapters are not allowed.**

Explanation: You configured the SDLC configuration using more than two SDLC adapter cards. The maximum number of SDLC adapter cards is two.

User Response: Reconfigure the SDLC connection.

PCSSDLC055 **Insufficient memory is available.**

Explanation: There was not enough memory to load **PCSSDLC.EXE**.

User Response: Unload any unneeded applications, device drivers, and memory-resident programs, and retry the operation. If the error persists, ask your system administrator for assistance.

PCSSETUP001 **The Personal Communications files that are needed to perform the function you selected have not been installed. Do you want to install the files now?**

Explanation: You attempted to perform some functions of Personal Communications, but the required modules or files did not exist in the directory where Personal Communications is installed.

User Response: Select **Yes** to install the required modules or files to perform that function. You are prompted to insert the *Personal Communications Windows Mode* diskette to the drive A. The error message is displayed if you select No.

PCSSLAN010 **IBM Local Area Network Support Program has not been loaded.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through either LAN via IEEE 802.2 connection or 3174 peer communication connection, but the IBM Local Area Network Support Program was not installed.

User Response: Exit Windows and make sure that the IBM Local Area Network Support Program is specified in your **CONFIG.SYS** file. Turn your workstation off, and then turn it on again. Restart Windows and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSSLAN011 **Network adapter has not been installed.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through either LAN via IEEE 802.2 connection or 3174 peer communication connection, but the Network adapter was not installed on your PC.

User Response: Exit Windows and make sure that the proper Network adapter is installed on your workstation. Restart Windows and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSSLAN012 Number of link stations on this local SAP is insufficient.

Explanation: You attempted to connect the Personal Communications workstation window to your application through either LAN via IEEE 802.2 connection or 3174 peer communication connection, but enough link stations were not available on the local SAP. This message appears, for example, when you specify different destination addresses on the same local SAP.

The number of link stations on the SAP is determined by the application or device driver that opens the SAP. It could be the Personal Communications workstation program, another Windows application, or DOS application, or DOS device driver.

User Response: Disconnect all workstation windows currently connected to your application through either LAN via IEEE 802.2 connection or 3174 peer communication from your application, increase the number of link stations in the **Link Station Count** entry field in the IEEE 802.2 advanced options dialog box, and then try the operation again. If the problem persists, it could be another application or the device driver that opens the SAP. Ask your system administrator for assistance.

PCSSLAN020 Destination address is invalid. Only values from 000000000000 to 7FFFFFFFFFFF are allowed.

Explanation: You selected **OK** in the IEEE 802.2 dialog box, but the value in the **Destination Address** entry field was not valid.

User Response: Correct the value in the **Destination Address** entry field as instructed in the message, and try the operation again.

PCSSLAN051 PCSSLAN.EXE is already installed.

Explanation: You attempted to load **PCSSLAN.EXE**, but it was already installed.

User Response: None.

PCSSLAN052 Invalid parameter is specified.

Explanation: You attempted to execute **PCSSLAN.EXE** with an incorrect parameter.

User Response: Remove or correct the incorrect parameter and try the operation again.

PCSSLAN053 PCSSLAN.EXE cannot remove itself from the resident memory.

Explanation: You attempted to remove **PCSSLAN.EXE** from the resident memory, but the attempt failed.

User Response: Re-boot your system if you want to remove **PCSSLAN.EXE**.

PCSSLAN054 IBM Local Area Network Support Program is not installed.

Explanation: The IBM Local Area Network Support Program is required for this connection, but it is not installed.

User Response: Install the IBM Local Area Network Support Program.

PCSTDLC001 **TDLC configuration data is saved. You must restart Windows so that the changes you made can take effect.**

Explanation: The configuration information for the adapter is saved.

User Response: Restart Windows.

PCSTDLC002 **IBM Twinax adapter cannot be found or OEM Twinax Virtual Device Driver is not loaded.**

Explanation: An IBM Twinax adapter has not been installed or is not ready. If you are using an OEM Twinax adapter card, OEM Twinax Virtual Device Driver is not successfully loaded.

User Response: Make sure that an IBM Twinax adapter has been installed in the workstation. If you are using a 5250 PCMCIA adapter, make sure that the 5250 PCMCIA device drivers have been successfully loaded. If you are using an OEM Twinax adapter, make sure that the adapter is correctly installed and set up.

PCSTDLC003 **Twinax adapter cannot be found.**

Explanation: Explanation: No adapter error was reported from the OEM Twinax Virtual Device Driver.

User Response: Make sure that an OEM Twinax adapter has been correctly set up.

PCSTDLC004 **Twinax adapter RAM error occurred during start-up. Check adapter memory address.**

Explanation: An adapter RAM error was reported from the OEM Twinax Virtual Device Driver.

User Response: Make sure that you do not specify the same address for the driver such as EMM386.EXE and for 5250 adapter memory address.

PCSTDLC005 **A hardware error is detected during start-up.**

Explanation: An adapter RAM error was reported from the OEM Twinax Virtual Device Driver.

User Response: Make sure that an OEM Twinax adapter has been correctly set up.

PCSTDLC006 **Files needed by Twinax Virtual Device Driver are missing. Re-install Personal Communications or OEM Twinax Virtual Device Driver.**

Explanation: The files needed cannot be found.

User Response: Re-install Personal Communications or OEM Twinax Virtual Device Driver.

PCSTDLC007 **Another Twinax device driver is loaded. Remove it and try again.**

Explanation: The Twinax Virtual Device Driver for Personal Communications cannot be loaded with another Twinax Device driver.

User Response: Remove the device drivers from memory and try again.

PCSTDLC008 **This connection is not supported by OEM Twinax Virtual Device Driver.**

Explanation: OEM Twinax Virtual Device Driver does not support this connection type.

User Response: Use another connection.

PCSTLNET001 **WINSOCK.DLL could not be loaded.**

Explanation: An attempt to load **WINSOCK.DLL** failed. **WINSOCK.DLL** does not exist on the current path.

User Response: Install the **WINSOCK.DLL** for the TCP/IP protocol stack used. The **WINSOCK.DLL** must support the Windows Sockets Version 1.1 interface.

PCSTLNET002 **The WINSOCK.DLL in the path does not work with this version of Windows.**

Explanation: **WINSOCK.DLL** found on the path indicates that it does not work on the Windows version used.

User Response: Install the correct **WINSOCK.DLL** that supports the Windows version used.

PCSTLNET003 **The specified host was not found.**

Explanation: The host name specified in the **Host Name or IP Address** field was not found on the connected network.

User Response: Enter the correct name or IP address of the host on the network.

PCSTLNET004 **A connection to the host was not established.**

Explanation: The specified host does not exist on the network, so the attempt to establish a connection to the host failed. The network or the host system itself might be inoperative.

User Response: Wait until the network or the host becomes available.

PCSTLNET005 **The Windows Sockets implementation detected that the network subsystem failed.**

Explanation: The network subsystem to which the machine is connected, might be down or having problems.

User Response: Check the network subsystem.

PCSTLNET006 **No more file descriptors are available. The socket cannot be created.**

Explanation: An attempt to create a socket for the session has failed because of a shortage of file descriptors.

User Response: Increase the FILES= definition in the **CONFIG.SYS** file.

PCSTLNET007 **No buffer space is available. The socket cannot be created.**

Explanation: An attempt to create a socket for the session has failed because of a shortage of conventional memory.

User Response: Increase the unused area in the conventional memory by removing unnecessary TSR programs.

PCSTLNET008 **The requested LU name is already associated with another Telnet session.**

Explanation: The requested LU name is already associated with another Telnet session.

User Response: Wait until the LU is freed, or specify another LU name in the Telnet3270 Customization window.

PCSTLNET009 **The specified LU name is not known to the server.**

Explanation: The specified LU name is not known to the server.

User Response: Specify the correct LU name in the Telnet3270 Customization window.

PCSTLNET010 **The server does not support the requested LU type.**

Explanation: The server does not support the requested LU type.

User Response: If *TerminalType* or *TerminalTypeString* is specified in your workstation profile, make sure the value is correct.

PCSTLNET011 **The requested LU name is not compatible with the requested LU type.**

Explanation: The requested LU name is not compatible with the requested LU type, such as terminal/printer mismatch.

User Response: Specify the correct LU name in the Telnet3270 Customization window.

PCSTLNET012 **The server is unable to process this type of request.**

Explanation: None.

User Response: Specify the LU type or LU name correctly.

PCSTLNET013 **An unknown error occurred during DEVICE-TYPE negotiation.**

Explanation: None.

User Response: Specify the correct LU type.

PCSUPM001 **The user ID is not specified.**

Explanation: A user ID must be specified as part of a user profile at automatic logon.

User Response: Specify a user ID.

PCSUPM002 **The password is not specified.**

Explanation: A password must be specified as part of a user profile at automatic logon.

User Response: Specify a password.

PCSUPM003 **Type twice for the confirmation of the password.**

Explanation: To confirm that the password has been entered as desired, the system requests that it be entered a second time.

User Response: Enter the desired password again.

PCSUPM004 **The new and confirmation passwords are not the same.**

Explanation: The first and second password entries are different.

User Response: Reenter the password, taking care to specify it exactly as desired.

PCSUPM005 **No user profile is selected.**

Explanation: A user profile name must be specified.

User Response: Specify a user profile name, or select a user profile name by using the Windows *Browse* function.

PCSUPM006 **The selected file does not contain the user profile information.**

Explanation: The specified user profile does not contain the required user ID or password information.

User Response: Specify a user ID and password.

PCSVLAN001 **The network-adapter number specified in your Workstation profile is invalid. It must be 0 or 1.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an unrecognized Network adapter number for the LAN via 3270 Emulation Program Gateway connection. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after selecting the proper adapter number from the Adapter Number combo box in the LAN via 3270 Emulation Program Gateway dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSVLAN002 **A space has been used in the Network-Station Name specified in your Workstation profile.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect Network Station Name for the LAN via 3270 Emulation Program Gateway connection. A space character was included in the Network Station Name. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct Network Station Name in the **Network Station Name** entry field in the LAN via 3270 Emulation Program Gateway. dialog box; then try the operation again. If the problem persists, install PC/3270 again.

PCSVLAN003 **Network-Station Name specified in your Workstation profile exceeds 15 characters.**

Explanation: You attempted to start the Personal Communications workstation program with the profile, or attempted to open the profile, specifying an incorrect Network Station Name for the LAN via 3270 Emulation Program Gateway connection. The Network Station Name exceeded 15 characters in length. This message might appear only if you have manually modified the workstation profile.

User Response: Re-create the Personal Communications workstation profile after specifying the correct Network Station Name in the **Network Station Name** entry field in the LAN via 3270 Emulation Program Gateway

dialog box, then try the operation again. If the problem persists, install PC/3270 again.

PCSVLAN004 **'*' has been used as the first character of the Network-Station Name specified in your WorkStation profile.**

Explanation: The incorrect character '*' has been used as the first character of the Network-Station Name.

User Response: Use a character other than '*'.

PCSVLAN010 **IBM Local Area Network Support Program has been not loaded.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through LAN via 3270 Emulation Program Gateway connection, but the IBM Local Area Network Support Program was not installed.

User Response: Exit Windows and make sure that the IBM Local Area Network Support Program is specified in your **CONFIG.SYS** file. Turn your workstation off; then on again. Restart Windows and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSVLAN011 **NetBIOS has been not installed.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the LAN via 3270 Emulation Program Gateway connection, but the Network Basic Input/Output System (NetBIOS) was not installed.

User Response: Exit Windows and make sure that the NetBIOS is specified in your **CONFIG.SYS** file. Turn your workstation off; then turn it on again. Restart Windows and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSVLAN012 **This Network-Station Name is already used by another Workstation session or by another application.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the LAN via 3270 Emulation Program Gateway connection, but the Network Station Name specified in your workstation profile was used by another workstation window or an application on your workstation.

User Response: Close the application using the Network Station Name and try the operation again. The application to be closed might be either DOS or Windows application and you might need to ask your system administrator for assistance.

PCSVLAN013 **This Network-Station Name is already being used by an application on another PC in the network.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the LAN via 3270 Emulation Program Gateway connection, but the Network Station Name specified in your workstation profile was used by an application on the other workstation in the network.

User Response: Ask your system administrator for the unique Network Station Name.

PCSVLAN014 **NetBIOS command NCB.ADD.NAME failed: return code -** xx**.**

Explanation: You attempted to connect the Personal Communications workstation window to your application through the LAN via 3270 Emulation Program Gateway connection, but your Network Station Name could not be added to the network.

User Response: When the return code is *0xfc*, refer to online help (*LAN error* in *When you encounter a problem*) of PC/3270. For other return codes, ask your system administrator for assistance.

PCSVLAN020 **Network-Station Name was not specified.**

Explanation: You selected **OK** in the LAN via 3270 Emulation Program Gateway dialog box, but nothing was specified in the **Network Station Name** entry field.

User Response: Fill in the **Network Station Name** entry field and try the operation again.

PCSVLAN021 **Spaces are not allowed in the Network-Station Name.**

Explanation: You selected **OK** in the LAN via 3270 Emulation Program Gateway dialog box, but a space character was included in the **Network Station Name** entry field.

User Response: Remove the space from the **Network Station Name** entry field and try the operation again.

PCSVLAN022 **'*' is not allowed to be the first character of the Network-Station Name.**

Explanation: '*' was used for the first character of the Network-Station Name, but it is not allowed.

User Response: Used a character other than '*'.

PCSVLAN023 **Before you can use a LAN via 3270 Emulation Program v3 Gateway connection in Windows' Standard mode, the gateway's CONFIG.SYS file must be modified. If the gateway's CONFIG.SYS file is not modified, you will lose your connection to the host.**

Please refer to the Personal Communications online Help for more information.

Explanation: You selected **OK** in the LAN via 3270 Emulation Program Gateway dialog box while operating in Windows standard mode. You are requested to install the **PCSGW.SYS** module in the gateway machine to avoid timeout errors.

User Response: Modify the **CONFIG.SYS** file on the gateway machine as follows:

1. Insert the 3.5 inch *Personal Communications/3270 Windows Mode Diskette 1 (Installation)* or 5.25 inch *Personal Communications/3270 Windows Mode Diskette 2* into the diskette drive of the workstation that is running the gateway.
2. Copy **PCSGW.SYS** from the diskette to the gateway workstation.
3. Edit the **CONFIG.SYS** file of the gateway workstation as follows.

```
                :
device=C:\LSP\DXMT MOD.SYS O=N ES=1 EST=2
device=(d:)\(path)\PCSGW.SYS
                :
```

Put the device=PCSGW.SYS statement immediately after the device=DXMT MOD.SYS statement. The actual drive, path name, and parameters for DXMT0MOD will depend on your installation.

4. Restart the gateway workstation.

PCSVLAN051 **PCSVLAN.EXE is already installed.**

Explanation: You attempted to load **PCSVLAN.EXE**, but it was already installed.

User Response: None.

PCSVLAN052 **Invalid parameter is specified.**

Explanation: You attempted to execute **PCSVLAN.EXE** with an incorrect parameter.

User Response: Remove or correct the incorrect parameter and try the operation again.

PCSVLAN053 **PCSVLAN.EXE cannot remove itself from the resident memory.**

Explanation: You attempted to remove **PCSVLAN.EXE** from the resident memory, but the attempt failed.

User Response: Re-boot your system if you want to remove **PCSVLAN.EXE**.

PCSVLAN054 **IBM Local Area Network Support Program is not installed.**

Explanation: The IBM Local Area Network Support Program is required for this connection, but it is not installed.

User Response: Install the IBM Local Area Network Support Program.

PCSVLAN055 **NetBIOS is not installed.**

Explanation: The NetBIOS program is required for this connection, but it is not installed.

User Response: Install the NetBIOS program.

PCSVP001 **VvprtD.386, the virtual printer driver is not loaded. Please add a statement for it to the [386Enh] section of the SYSTEM.INI file.**

Explanation: VvprtD.386 is not loaded.

User Response: Add the following line to the [386Enh] section of the SYSTEM.INI file, and then restart Windows.

```
DEVICE = drive-name:\path-name\VVPRTD.386
```

PCSVP002 **The Virtual Printer program is already running.**

Explanation: You attempted to execute a PCSVPRT while a PCSVPRT is already being executed.

User Response: None.

PCSVP003 **The Virtual Printer program is still running. You must stop it before you can quit Windows.**

Explanation: You attempted to exit Windows during PCSVPRT.EXE execution.

User Response: Quit PCSVPRT.EXE first, and then quit Windows.

PCSVP011 **Only decimal numbers (0–9) are allowed.**

Explanation: You attempted to type a character other than numbers (0–9) in the entry field of the dialog box.

User Response: Type a decimal number in the entry field.

PCSVP012 **Only hexadecimal numbers (0–9, A–F) are allowed.**

Explanation: You attempted to type a character other than hexadecimal numbers (0–9, A–F) in the entry field of the dialog box.

User Response: Type a hexadecimal number in the entry field.

PCSVP013 *file-name* **cannot be found.**

Explanation: The file: *file-name* cannot be found.

User Response: Select **OK** and specify the correct file name.

PCSVP014 **The specified Page Length in Lines is not valid. A valid range is from 1 through 255.**

Explanation: You specified a value that is not within the valid range, from 1 through 255 for the Page Length in Lines.

User Response: Select **OK** and specify the correct value of the Page Length in Lines.

PCSVP015 **You did not specify the value of the Characters Per Line.**

Explanation: You must specify the value of the Characters Per Line, but you left the input field blank.

User Response: Select **OK** and specify the value of the Characters Per Line.

PCSVP016 **The specified Lines Per Page is not valid. A valid range is from 1 through a value of Page Length in Lines.**

Explanation: You specified the value that is not within the valid range, from 1 through the value of Page Length in Lines for the Lines Per Page.

User Response: Select **OK** and specify the correct value of the Lines Per Page.

PCSVP017 **The specified Number of Copies is not valid. A valid range is from 1 through 255.**

Explanation: You specified a value that is not within the valid range, from 1 through 255 for the Number of Copies.

User Response: Select **OK** and specify the correct value for the Number of Copies.

PCSVP018 **The specified Timeout value is not valid. A valid range is from 0 through 255.**

Explanation: You specified a Timeout value that is not within the valid range, from 0 through 255.

User Response: Select **OK** and specify the correct Timeout value.

PCSVP019 **The specified Hex code for an untranslatable character is not valid. The valid range is from 40 through FF.**

Explanation: You specified the hexadecimal code for an untranslatable character that is not within the valid range from 40 through FF.

User Response: Select **OK** and specify the correct hexadecimal code.

PCSVP020 **You must specify either a printer device name or printer file name.**

Explanation: You must specify at least either a printer device name or a printer file name when you assign an LPT by the Virtual Printer transaction program of an AS/400, but you specified neither of them.

User Response: Select **OK** and specify either or both of them.

PCSVP021 *LPT-name*: **This assignment will be released.**

Explanation: This message is displayed to confirm if you want to release the LPT: *LPT-name*

User Response: Select **OK** if you want to release the LPT. Otherwise, select **Cancel**.

PCSVP022 *LPT-name*: **All settings will be changed to default values.**

Explanation: This message is displayed to confirm if you want to change all settings to default values for the LPT: *LPT-name*.

User Response: Select **OK** if you want to change all settings to default values for the LPT. Otherwise, select **Cancel**.

PCSVP023 *LPT-name*: **The Virtual Printer program cannot assign the specified LPT. Assign the LPT again.**

Explanation: PCSVPRT.EXE cannot connect the LPT: *LPT-name* with the AS/400.

User Response: Select **OK** and assign the LPT again. If necessary, disconnect the session connected to the AS/400 and open it again on the Select Communication window. Then, assign the the LPT again.

PCSVP024 *LPT-name*: **The spooled file was closed successfully.**

Explanation: You attempted to close the spooled file in the output queue that the LPT *LPT-name* is assigned to. It was closed successfully.

User Response: None.

PCSVP025 *LPT-name*: **The spooled file is already closed.**

Explanation: You attempted to close the spooled file in the output queue that the LPT *LPT-name* is assigned to. But it is already closed.

User Response: None.

PCSVP026 **You must specify a printer device name.**

Explanation: You must specify a printer device name when you assign an LPT by the Network Print Server transaction program of an AS/400, but you left the input field blank.

User Response: Select **OK** and specify a printer device name.

PCSVP041 *host-name***- You have either defined a new session for this host or changed one or more of its settings. Do you want to save the current settings?**

Explanation: You have either defined a new session for the AS/400: *host-name* or changed one or more of its settings, but they have not been saved yet.

User Response: Select **OK** if you want to save them. Otherwise, select **No**.

PCSVP042 **At least one LPT is using this session. You must release this LPT before you can disconnect it.**

Explanation: You can disconnect only a session no LPT is using, but you attempted to disconnect a session that at least one LPT is using.

User Response: Select **OK** and release the LPT before you disconnect the session.

PCSVP043 *host-name***: The Virtual Printer program cannot connect with this host.**

Explanation: PCSVPRT.EXE cannot make a connection with the AS/400 *host-name*.

User Response: Select **OK** and open the workstation profile again.

PCSVP044 *host-name***: This session will be disconnected.**

Explanation: This message is displayed to confirm if you want to disconnect the session with the AS/400 *host-name*.

User Response: Select **OK** if you want to disconnect the session. Otherwise, select **Cancel**.

PCSVP045 **At least one LPT is using this session. You must release this LPT before you can change it.**

Explanation: You can change only a session no LPT is using, but you attempted to change a session that at least one LPT is using.

User Response: Select **OK** and release the LPT before you change the session.

PCSVP061 **The selected spooled file will be deleted.**

Explanation: This message is displayed to confirm if you want to delete the spooled file you selected.

User Response: Select **OK** if you want to delete the spooled file. Otherwise, select **Cancel**.

PCSVP062 *LPT-name*(*parameter-name*)**: The host system did not accept the specified value for the parameter.**

Explanation: You attempted to assign the LPT: *LPT-name*, but the AS/400 did not accept the specified value for the parameter: *parameter-name*. The possible *parameter-name* is one of the following items:

Printer device name
Characters per inch
Lines per inch
Page length in lines
Characters per line
Lines per page
Number of copies
Hexadecimal value for an untranslatable character

This message is displayed only when you attempt to assign the LPT by the Network Print Server transaction program.

User Response: Select **OK** and correct the specified value for the parameter. Then, assign the LPT again.

PCSVP063 **You do not have authority at the host for the selected operation.**

Explanation: The host did not accept the selected operation because you do not have enough authority at the host for the operation.

User Response: Obtain the required authority from the system administrator. Then, request the operation again.

PCSVP064 **The spooled file you selected has no message waiting with the host.**

Explanation: You attempted to display a message for the spooled file you selected, but it has no message waiting with the AS/400 system.

User Response: None.

PCSVP065 **Requested list is empty; no objects matched the selection criteria.**

Explanation: You attempted to list one of the following objects:

Printer device
Spooled file

but there are no items. This message is displayed only when you attempt to list objects by the Network Print Server transaction program.

User Response: None.

PCSVP066 **Your request to start the printer has been processed successfully.**

Explanation: Your request to start the printer has been processed successfully. Note that the printer itself may not be started when this message is displayed.

User Response: None.

PCSVP067 **Your request to end the printer has been processed successfully.**

Explanation: Your request to end printing has been processed successfully. Note that the printer itself may not be ended when this message is displayed.

User Response: None.

PCSVP068 **You must specify one of the answers between the parentheses of the message text.**

Explanation: You must specify your answer when you select **OK** on the Answer Messages window, but you left the input field for the answer blank.

User Response: Select **OK** and specify one of the answers between the parentheses of the message text.

PCSVPD001 **Invalid character in Device Type field. Valid input characters are: A–Z a–z 0–9 space**

Explanation: You attempted to select **OK** in the Vital Product Data dialog box while incorrect characters were in the **Device Type** entry field. Characters A–Z, 0–9 and space are valid characters in this field.

User Response: Remove the incorrect characters from the **Device Type** entry field and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSVPD002 **Invalid character in Model field. Valid input characters are: A–Z a–z 0–9 space**

Explanation: You attempted to select **OK** in the Vital Product Data dialog box while incorrect characters were in the **Model** entry field. Characters A–Z, 0–9 and space are valid characters in this field.

User Response: Remove the incorrect characters from the **Model** entry field and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSVPD003 **Invalid character in Machine Serial field. Valid input characters are: A–Z a–z 0–9 space**

Explanation: You attempted to select **OK** in the Vital Product Data dialog box while incorrect characters were in the **Machine Serial** entry field. Characters A–Z, 0–9, and space are valid characters in this field.

User Response: Remove the incorrect characters from the **Machine Serial** entry field and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSVPD010 **Invalid character is in No.**xx **Data field. Valid input characters are: A-Z a-z 0-9 Space + < = > % & * '' ' ( ) . , _ - / : ; ?**

Explanation: You attempted to select **OK** in the Extended Vital Product Data dialog box while incorrect characters were in the **Data** entry field. Characters A–Z, 0–9, space, + < = > % & * " ' ( ) . , _ – : ; ? are valid characters in these field.

User Response: Remove the incorrect characters from the **Data** entry field and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSWKBD001 file-name **cannot be found.**

Explanation: The file file-name was not found.

User Response: Make sure that the correct path and file name are given.

PCSWKBD002 file-name **is not a valid file name. Please make sure that you specified the correct file name.**

Explanation: The file file-name did not form a valid DOS file name.

User Response: Make sure that the correct file name is given.

PCSWKBD003 file-name **is not a valid file name. Wildcard characters are not supported.**

Explanation: A wildcard character was found in the file name.

User Response: Remove the wildcard character from the file name.

PCSWKBD004 **Path:** path **does not exist. Please verify that you specified the correct path.**

Explanation: The path path did not exist.

User Response: Make sure that the correct path name is given.

PCSWKBD100 **Macro does not exist. Please select a function.**

Explanation: You attempted to select **OK** in the Keyboard/Macro dialog box after selecting no macro in the Macro combo box. (You did not create the macro, so nothing was in the Macro combo box.)

User Response: Select a function from the Function combo box and try the operation again.

PCSWKBD200 **Please specify a keyboard-file name.**

Explanation: You attempted to select **OK** in the Keyboard Setup dialog box after selecting **User defined** keyboard, but not specifying the **Keyboard File Name**.

User Response: Type a file name of the keyboard file in the **Keyboard File Name** entry field and try the operation again.

PCSWKBD201 **Please select a keyboard layout.**

Explanation: You attempted to select **OK** in the Keyboard Setup dialog box without selecting a keyboard language from the Keyboard Layout combo box.

User Response: Select a keyboard language from the Keyboard Layout combo box and try the operation again.

PCSWKBD300 **Please specify a popup-keypad-file name.**

Explanation: You attempted to select **OK** in the Popup Keypad Setup dialog box after selecting **User defined** pop-up keypad, but the **Popup Keypad File Name** was not specified.

User Response: Type the file name of the pop-up keypad file in the **Popup Keypad File Name** entry field and try the operation again.

PCSWKBD400 **Please specify a mouse-file name.**

Explanation: You attempted to select **OK** in the Mouse Setup dialog box after selecting **User defined** mouse, but the **Mouse File Name** was not specified.

User Response: Type a mouse file name in the **Mouse File Name** entry field and try the operation again.

PCSWKBD500 **Macro does not exist.**

Explanation: You attempted to select **OK** in the Play Macro dialog, but there was no macro file to play.

User Response: Select **Cancel** to close the Play Macro dialog.

PCSWS001 **Extremely low on memory. Close one or more Windows applications and start again.**

Explanation: Your Windows system does not have enough available memory to start the Personal Communications workstation program.

User Response: Close one or more Windows application and start the Personal Communications workstation program again.

PCSWS010 **Workstation profile:** file-name **cannot be found. Do you want to select another?**

Explanation: The profile file-name defining the characteristics of the Personal Communications workstation window was not found. A possible reason is that the path does not exist, that path is not correct, or that file name is not correct.

User Response: Select **Yes** to select another profile and continue the operation. The Open Workstation Profile dialog box will appear and allow you to select another profile. Select **No** to quit the operation.

PCSWS011 **The file:** file-name **is not a Personal Communications workstation profile.**

Explanation: The file file-name does not have a valid format as a profile for the Personal Communications workstation window. This message might appear if you have manually modified the workstation profile.

User Response: Make sure that the correct file name is given and if it is, re-create the Personal Communications workstation profile and try the operation again. If the problem persists, install Personal Communications again.

PCSWS020 **You have asked to close this session. It might be a new session or you might have changed one or more of its settings; do you want to save the current definitions?**

Explanation: You attempted to exit the Personal Communications workstation window without saving the settings changed since the last time you selected **New** in the File pull-down menu, opened the profile, or saved the settings into the profile.

User Response: Select **Yes** to exit after saving the changes. Select **No** to exit without saving the changes.

Select **Cancel** to cancel without exiting. The Personal Communications workstation window remains open.

PCSWS021 **Because you have changed the profile for this session, communication will be terminated if you proceed. Are you sure?**

Explanation: You attempted to change the profile of the Personal Communications workstation window without disconnecting the communication.

User Response: Select **OK** to continue the operation. The communication is automatically disconnected before loading of the settings from the new profile and reconnected if **AutoConnect** is selected in the new profile.

Select **Cancel** to quit the operation. The settings of the Personal Communications workstation window remains unchanged.

PCSWS022 **Do you want to add an icon for this session to the Program Manager?**

Explanation: You created a new profile for the Personal Communications workstation window.

User Response: Select **Yes** to add the icon of the Personal Communications workstation program with the current settings. The Add Workstation Program-to-Program Group dialog box is displayed to prompt you to specify the group name to which the icon is added.

Select **No** to not add the icon of the Personal Communications workstation program with the current settings.

PCSWS023 **Enter '(d:\path)PCSWS.EXE (d:\path)**file-name**' in the command-line entry-field of the Run dialog box of Program manager, then press ENTER to start the Workstation with the modified definitions.**

Explanation: You did not add the icon of the Personal Communications workstation program when you created the new profile.

User Response: Follow the instruction in the message the next time you start the Communications workstation program.

PCSWS024 **To start the workstation (session) that you have just saved, select the '**workstation**' icon in the '**group-name**' program group.**

Explanation: You added the icon of the Personal Communications workstation program when you created the new profile.

User Response: Follow the instruction in the message the next time you start the Personal Communications workstation program.

PCSWS025 **An icon was not added to the Program Manager.**

Explanation: Windows returned an error condition when PC400 attempted to add the icon of the Personal Communications workstation program to the Windows Program Manager.

User Response: Try the operation again. If the problem persists, ask your system administrator for assistance.

PCSWS026 **Error saving the workstation profile:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to write the Personal Communications workstation profile file-name.

User Response: Determine the cause of the error condition and correct it or ask your system administrator for assistance.

PCSXFER001 **Insufficient Windows system memory available. Close one or more unnecessary Windows application program, and try again.**

Explanation: Your Windows system does not have enough available memory to transfer the files you selected.

User Response: If you were sending or receiving more than one file, try sending or receiving one file at a time. If the problem persists, close one or more Windows applications and try again. If the problem still persists, ask your system administrator for assistance.

PCSXFER010 **PC file:** file-name **cannot be found in the path specified.**

Explanation: The file file-name was not found.

User Response: Make sure that the correct path and file name are given.

PCSXFER011 **Error reading file:** file-name **from the PC disk.**

Explanation: The file might have write-only access, or the disk or the diskette might be damaged. Or you might have specified an incorrect subdirectory or file name.

User Response: Make sure that the correct path name and file name are given. If they are correct, make sure that the file can be read by checking that the file is not a write-only file. If the problem persists, ask your system administrator for assistance.

PCSXFER012 **Error creating file:** file-name **on the PC disk.**

Explanation: The disk or diskette was either damaged, full, or unformatted. Or you might have specified an incorrect subdirectory or file name.

User Response: Make sure that the correct path name and file name are given. If they are correct, make sure that the file can be written by checking that the diskette is not write-protected, and ensure that there is adequate space available. If the problem persists, ask your system administrator for assistance.

PCSXFER013 **Error writing file:** file-name **to the PC disk.**

Explanation: The disk or diskette was either damaged, full, or unformatted. Or you might have specified an incorrect subdirectory or file name.

User Response: Make sure that the correct path name and file name are given. If they are correct, make sure that the file can be written by checking that the diskette is not write-protected or the file is not a read-only file, and ensure that there is adequate space available. If the problem persists, ask your system administrator for assistance.

PCSXFER014 **Error writing file:** file-name **to the PC disk because the disk is full.**

Explanation: The disk or diskette is full.

User Response: Erase unnecessary files from the target disk and try the operation again. If the problem persists, ask your system administrator for assistance.

PCSXFER015 **PC file:** file-name **which is to be appended to cannot be found in the path specified. The file is created as a new file.**

Explanation: There was no file-name file to append.

User Response: Make sure the correct path and file name are given.

PCSXFER020 **Error opening send/receive-list file:** file-name**.**

Explanation: Windows returned an error condition when Personal Communications attempted to open the send/receive file file-name.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSXFER030 **Cannot send zero-length file:** file-name**.**

Explanation: You attempted to send an empty file file-name to the host.

User Response: Erase the file.

PCSXFER040 **Lost contact with the host.**

Explanation: The host was inactive, or the communications link with the host was lost.

User Response: If you have received an error code in the operator information area, copy it down and refer to the online helps.

PCSXFER041 **Host has not responded within time-out period. You may have to disconnect from IND$FILE by pressing the PF2 key once or twice.**

Explanation: IND$FILE is the host application program that manages file transfers.

The Personal Communications workstation window canceled the file transfer because IND$FILE did not respond within the timeout period, and the workstation window screen might look incorrect because of the IND$FILE process.

User Response: Exit IND$FILE by pressing F2 once or twice and restart the file transfer. Make sure that the ready prompt appears on the screen before transferring the files.
If the problem persists, you might need to increase the timeout value in the Miscellaneous Settings - Session X dialog box. The default timeout value is 20 seconds.

PCSXFER042 **Transfer has been canceled. You may have to disconnect from IND$FILE by pressing the PF2 key once or twice.**

Explanation: IND$FILE is the host application program that manages file transfers.

You canceled the file transfer, and the workstation window screen might look incorrect because of the IND$FILE process.

User Response: Exit IND$FILE by pressing F2 once or twice to terminate IND$FILE completely and restore the screen.

PCSXFER050 **The combination of host code-page and PC code-page is invalid.**

Explanation: You attempted to start file transfer, but the combination of the host code page and PC code page was not valid.

User Response: Reconnect the communication after selecting the proper host code page from the Host Code Page combo box in the Customize Communication - 3270 Host dialog box. (Ignore this step if you are using the Home3270 connection.) Then select the proper PC code page from the PC Code Page combo box in the Miscellaneous Settings - Session X dialog box and try the operation again.

If the problem persists, ask your system administrator for assistance.

PCSXFER060 **Transfer had finished successfully before your pause request was accepted.**

Explanation: You selected **Pause** in the Send Files Status or the Receive Files Status dialog box while transferring multiple files. But the file transfer completed successfully before your request was accepted.

User Response: None.

PCSXFER070 file-name **is not a valid file-name. Please make sure that you specified the correct file-name.**

Explanation: The file file-name does not have a valid DOS file name.

User Response: Make sure you have specified the correct file name.

PCSXFER071 file-name **cannot be found.**

Explanation: The file file-name could not be found.

User Response: Make sure you have specified the correct path and file name.

PCSXFER072 **Path:** path **does not exist. Please make sure that you specified the correct path.**

Explanation: The path path does not exist.

User Response: Make sure that correct path name is given.

PCSXFER073 **Please specify a translation-file name.**

Explanation: A translation-table name has not been specified in the **File Name** field of Translation-Table Setup dialog box.

User Response: Select **OK** and specify a translation-file name.

PCSXLT001 **The file:** file-name **is not a Personal Communications code-page-translation file.**

Explanation: The file file-name was not a Personal Communications code-page translation file.

User Response: Make sure that the correct file name is given, and then try the operation again. If the problem persists, install Personal Communications again.

PCSXLT002 **A character outside the revisable range was found and ignored.**

Explanation: A character outside the revisable range was found and ignored.

User Response: Re-create the Personal Communications code-page translation file and try the operation again. If the problem persists, install Personal Communications again.

PCSXLT350 **Customize Translation Table dialog box is already open.**

Explanation: You attempted to open the Translation Table dialog box while it was already opened in another workstation window.

User Response: Close the Translation Table dialog box in the other workstation window.

PCSXLT351 file-name **has been changed. Save the changes?**

Explanation: You attempted to exit the Translation Table dialog box, but the translation table has been changed.

User Response: Select **OK** to save changes, or select **No** to cancel the changes.

PCSXLT352 **Error writing translation file:** file-name

Explanation: Windows returned an error condition when Personal Communications attempted to save the translation table.

User Response: Determine the cause of the error condition and correct it, or ask your system administrator for assistance.

PCSXLT353 hex-code1 **has been translated from** hex-code2**. Replace** hex-code2 **by undefined code?**

Explanation: You attempted to specify the code hex-code1, which has been already translated from hex-code2. Therefore, you should change hex-code2 to the undefined code.

User Response: Select **OK** to replace hex-code2 with the undefined code. Select **No** to cancel the change.

PCSXLT354 file-name **is not a valid file-name. Please make sure that you specified the correct file-name.**

Explanation: The extension of the file file-name is not .XLT.

User Response: Select **OK** and specify the correct file name.

PCSXLT355 file-name **cannot be found.**

Explanation: The file file-name cannot be found.

User Response: Select **OK** and specify the correct file name.

PCSXLT356 **Path:** path-name **does not exist. Please make sure that you specified the correct path.**

Explanation: The path path-name does not exist.

User Response: Select **OK** and specify the correct path.

PCSXLT357 **Please specify a translation-file name.**

Explanation: A translation-file name has not been specified in the **File Name** field of the Translation-Table Setup dialog box.

User Response: Select **OK** and specify a translation-file name.

VPOLLD010 **VpollD.386 was unable to allocate the conventional memory buffer. Increase the conventional memory before starting Windows, or adjust the value of 'VpollHeapSize=' in the [386Enh] section of SYSTEM.INI file, then exit and restart Windows.**

Explanation: There was not enough memory for **VPOLLD.386**.

User Response: Unload any unneeded applications, device drivers, and memory-resident programs, or adjust VpollHeapSize as described in the message.

VPOLLD011 **Now PCSPOLL.EXE is not required for your current configuration. Run the Personal Communications Setup Program to configure the Windows environment. Press any key to continue.**

Explanation: You changed your configuration, and **PCSPOLL.EXE** is no longer required.

User Response: Execute the Configuration and Program Options in Administration Tools after exiting Windows.

VSLAND010 **VSLAND.386 cannot be loaded since IBM Local Area Network Support Program is not installed. Press any key to continue.**

Explanation: IBM Local Area Network Support Program is required to load **VSLAND.386**, but it was not installed.

User Response: Install the IBM Local Area Network Support Program.

VSLAND011 **Now PCSSLAN.EXE is not required for your current configuration. Run the Personal Communications Setup Program to configure the Windows environment. Press any key to continue.**

Explanation: You changed your configuration, and **PCSSLAN.EXE** is no longer required.

User Response: Execute the Configuration and Program Options in Administration Tools after exiting Windows.

VTDLCD012 **System environment is not correct. Please check your environment. Press any key to continue . . .**

Explanation: The BIOS returned an error during 5250 adapter card initialization.

User Response: Make sure that the workstation on which this error occurred is supported by PC400. If this error occurs on the workstation supported by PC400, make sure that you do not specify the same address for the driver such as **EMM386.EXE** and for 5250 adapter card memory address.

VTDLCD014 **Twinaxial adapter card RAM Error. Please check Twinaxial card. Press any key to continue . . .**

Explanation: The 5250 adapter card has a problem.

User Response: Install the 5250 adapter card again, and test it as specified in the 5250 adapter installation procedures.

VTDLCD015 **PCSTDBOT.LEX is not found. Press any key to continue . . .**

Explanation: **PCSTDBOT.LEX** could not be found in the directory where PC400 is installed.

User Response: Make sure that **PCSDBOT.LEX** is in the directory where PC400 is installed. If you have accidentally erased it, install PC400 again.

VTDLCD016 **PCSTDOCM.LEX is not found. Press any key to continue . . .**

Explanation: **PCSTDOCM.LEX** could not be found in the directory where PC400 is installed.

User Response: Make sure that **PCSDOCM.LEX** is in the directory where PC400 is installed. If you have accidentally erased it, install PC400 again.

VTDLCD017 **Error occurs while loading 5250 adapter microcode. Press any key to continue . . .**

Explanation: An error occurred while loading the adapter microcode for the 5250 adapter card. This error can occur if the adapter card is defective or an address used by a device driver such as **EMM386.EXE** duplicates that used by the 5250 adapter card.

User Response: Set a memory address for the 5250 adapter card that does not duplicate that of another card or device driver.

VTDLCD018 **Since twinaxial adapter handler for PC Support is already loaded, twinaxial virtual device driver for Personal Communications is not loaded. Press any key to continue . . .**

Explanation: The twinaxial adapter handler for PC Support/400 and the twinaxial virtual device driver for PC400 cannot be loaded together.

User Response: If this error has occurred for a connection to the host via the PC Support/400 router, deselect the **TWINAX** check box in the Change System Settings dialog box of System Setup, or delete the twinaxial virtual device driver (**VTDLCD.386**) from SYSTEM.INI file.

VVLAND010 **VVLAND.386 can not be loaded since IBM Local Area Network Support Program is not installed. Press any key to continue.**

Explanation: IBM Local Area Network Support Program is required to load **VVLAND.386**, but it was not installed.

User Response: Install the IBM Local Area Network Support Program.

VVLAND011 **VVLAND.386 can not be loaded since NetBIOS is not installed. Press any key to continue.**

Explanation: NetBIOS program is required to load **VVLAND.386**, but it was not installed.

User Response: Install the NetBIOS program.

VVLAND012 **Now PCSVLAN.EXE is not required for your current configuration. Run the Personal Communications Setup Program to configure the Windows environment. Press any key to continue.**

Explanation: You changed your configuration, and **PCSVLAN.EXE** is no longer required.

User Response: Execute the Configuration and Program Options in Administration Tools after exiting Windows.

File Transfer Messages

TRANS03 and TRANS04 are not error messages, and are usually not displayed. When file transfer terminates with no messages having been displayed, it means that file transfer was successful. More than one file can be transferred by a single file transfer request. To avoid interrupting the transfer operation, the system is designed not to display messages during transfer, provided the operation is normal.

TRANS03 **File Transfer Complete.**

Explanation: File transfer has been completed normally. The file having the name or properties specified by the send or receive command has been stored at the host or workstation. (This message is not usually displayed.)

User Response: None.

TRANS04 **File transfer complete with records segmented.**

Explanation: The file transfer operation has been completed normally. Some of the transferred files contained records that are longer than the host's file record length. Such records are divided into two or more records. (This message is not usually displayed.)

User Response: The record length of a file containing 2-byte characters might be longer than that of a corresponding file on a workstation because SO/SI is inserted in the file on the host. Specify a larger LRECL, counting these SO/SI characters, or create a file with a larger record length beforehand. AS/400 determines the record length for each file. It is possible for one file to contain two or more members, but those members must all have the same record length. When a file already exists on the host, however, the record length cannot be changed when LRECL is specified. In this case, transfer another file, or delete the file and create a new one.

Messages TRANS12 through TRANS99 are error messages. File transfer is abended. Error information might also be output from AS/400. This information can be viewed by using the DSPJOBLOGT command.

TRANS12 **Write error, insufficient PC disk space, or defective disk File transfer aborted.**

Explanation: None.

User Response: Ensure that there is sufficient free space available on the workstation. Then, request the transfer again. If the same message is displayed again, check whether the workstation disk is defective, as described in the workstation *System Operation Guide*.

TRANS13 **Error writing file to host. File transfer canceled.**

Explanation: A program error might have been detected, or the connection to the host might be defective.

User Response: Contact your system administrator.

TRANS14 **Error reading file from host. File transfer canceled.**

Explanation: A program error might have been detected, or the connection to the host might be defective.

User Response: Contact your system administrator.

TRANS16 **Incorrect request code File transfer canceled.**

Explanation: The SEND/RECEIVE command has been specified with an incorrect parameter.

User Response: Request the transfer again. If the same message is displayed again, contact your system administrator.

TRANS17 **Missing or incorrect library/file/member name File transfer canceled.**

Explanation: To execute a RECEIVE command, the specified library/file/member must exist. When a SEND command is executed, a file/member is automatically created if it does not already exist. The library, however, must already exist.

User Response: Specify a valid library/file/member. Then, request file transfer again.

TRANS18 **Incorrect option specified. File transfer canceled.**

Explanation: An incorrect option was specified.

User Response: Specify a valid option. Then, execute it again.

TRANS28 **Invalid option File transfer canceled.**

Explanation: The specified option does not exist, or an incorrect combination of options might have been specified.

User Response: Specify a valid option. Then, execute it again.

TRANS29 **Invalid option with RECEIVE File transfer canceled.**

Explanation: An option specified with the file transfer command is not valid. The APPEND or LRECL option cannot be specified with the RECEIVE command.

User Response: Specify a valid option. Then, execute it again.

TRANS30 **Invalid option with APPEND File transfer canceled.**

Explanation: An option that cannot be specified with APPEND has been specified.

User Response: Specify a valid option. Then, execute it again.

TRANS34 **File not found. File transfer canceled.**

Explanation: The file specified with the RECEIVE command could not be found.

User Response: Specify a valid library/file/member. Then, request transfer again.

TRANS35 **File authorization invalid. File transfer canceled.**

Explanation: You must have the *READ authority to issue a RECEIVE command for the specified file. To issue a SEND command, you must have the *ADD authority for the specified library and must also have the *ADD/*UPDATE/*DELETE authority for the file. For more information about AS/400 security, refer to the AS/400 manual.

User Response: Execute this operation for a file for which you have authorization. Or, obtain the required authority from the system administrator or file owner. Then, request transfer again.

TRANS51 **File type option is not proper. File transfer canceled.**

Explanation: Only physical files and source physical files can be sent to or received from the workstation by using the PCT/400 file transfer facility. The issued command is identified as a source physical file if specified with the SCR option, or as a physical file if specified without the SCR option. An option specified in the command, however, is not compatible with the type of the existing file.

User Response: Check the type of the file. Then, request transfer again.

TRANS53 **Library not found. File transfer canceled.**

Explanation: None.

User Response: Check the library name. Then, request file transfer again.

TRANS54 **Member not found. File transfer canceled.**

Explanation: None.

User Response: Check the member name. Then, request file transfer again.

TRANS55 **Cannot access the file. File transfer canceled.**

Explanation: The target file cannot be opened due to a problem with AS/400.

User Response: Execute the AS/400 command DSPJOBLOG to view detailed error information. Remove the cause of the error. Then, request file transfer again.

TRANS56 **No authorization to library. File transfer canceled.**

Explanation: None.

User Response: Obtain the required authority from the system administrator or the library owner. Then, request file transfer again.

TRANS57 **No authorization to file. File transfer canceled.**

Explanation: None.

User Response: Obtain the required authority from the system administrator or the file owner. Then, request file transfer again.

TRANS58 **Cannot create file/member. File transfer canceled.**

Explanation: A file or member cannot be created when using the SEND command. The reasons might be: (1 and 2, below, can be viewed by executing the DSPJOBLOG command.)

1. Maximum Member Count is included as an AS/400 file attribute. The member count has already reached the maximum, thus a new member cannot be created.
2. An incorrect AS/400 file or member name has been specified. For example, a name beginning with a number cannot be specified as an AS/400 file name.
3. Two requests were simultaneously issued for a single file or member.

You can determine the cause by viewing the AS/400 job log. To view the detailed error information, execute the DSPJOBLOG command.

User Response:

1. To include two or more members in one file, you must create a file for which MAXMBRS(NOMAX) is specified.
2. Check the file name or member name. Then, request file transfer again.
3. Wait a short while. Then, request file transfer again.

TRANS60 **Error on AS/400 program - APVAFILE File transfer canceled.**

Explanation: None.

User Response: Contact your system administrator.

Other error messages can also be displayed on the AS/400 screen. Determine and remove the cause of these errors by checking the job logging. Typical error messages are listed below.

Command APVAFILE not found in Library *LIBL.

Explanation: To use the file transfer facility, PCT/400 must have been installed and set up on the destination AS/400.

User Response: Contact your system administrator and confirm that Personal Communications Tool/400 has been installed and set up.

Cursor is positioned to a protected area of the screen. Only a number from 0 to 9 can be specified. Unable to use the specified option number and others.

Explanation: When executing the file transfer facility, the cursor must be on the command line (a field available for input and execution of a command) of the AS/400 screen.

User Response: Ensure that the cursor is on the command line. Then, request file transfer again.

PCSXFERxx error messages can also be displayed during file transfer. These messages are explained in this chapter.

Personal Communications/3270

© Copyright IBM Corp. 1989, 1996

Chapter 10. Building a Printer Definition Table (PDT) for PC/3270

If you are using a printer that is not directly supported by PC/3270, you can use the printer table compiler to build a printer definition table for use by PC/3270. The input to the printer table compiler is a text file that defines how characters and control codes are sent to the printer and how printer output is formatted. You can create this file by using a text editor that produces an ASCII file or by modifying one of the printer definition tables supplied with PC/3270. The printer definition files are files that have an extension of **.PDF**.

Customizing the Printer Definition Table

To use the PDT file:

1. Select **File** from the menu bar of the workstation window.
2. Select **Printer Setup** from the File menu.

   The Printer Setup window appears.
3. Select the **Use PDT file** check box and then **Select PDT**.

   The Select PDT File window appears.



4. Select **Convert PDF**. Select the PDF file to be converted from the list in the Convert PDF to PDT window; then select **Convert**. After the file has been converted, control is returned to the Select PDT File window, and the converted PDT file is listed. Select the PDT file; then select **OK**.
5. Select **OK** on the Printer Setup window.

   After printer setup is complete, the Printer Setup window is closed.

Printer Definition File Format

The printer definition file consists of a macro definitions section and a definitions section. In the *macro definitions section*, you can equate a sequence of hexadecimal numbers, decimal numbers, and ASCII characters with a name that is used in place of that sequence in the definitions section. In the *definitions section*, the left side of each statement contains the name of a character or control command.

© Copyright IBM Corp. 1989, 1996

You enter a string of hexadecimal numbers, decimal numbers, ASCII characters, or previously defined macro names on the right side of each statement that defines the character or the command that is sent to the printer.

Different printer manuals define printer control strings in different ways. Some printer manuals describe control sequences as a string of hexadecimal numbers, while others use symbols such as esc J 1 K. The printer table compiler accepts either format and allows you to define macros for more readable files. The right side of each statement in the definitions section of the printer definition file can be any of these:

Single characters that are interpreted as their ASCII value
Two-digit numbers that are interpreted as hexadecimal values
Three-digit numbers that are interpreted as decimal values
Previously defined macros that are expanded by the printer table compiler.

If you leave the right side of a statement blank or if you delete it, the character or control code is interpreted as a null string. If a character or control code is defined more than once in the file, the last definition is used. If an error is detected in a statement, the printer table compiler ignores the statement and goes to the next statement.

After you have created your printer definition file, use the printer table compiler to compile it. The resulting file has the extension **.PDT**.

The symbols / indicate the beginning of a comment and the symbols / indicate the end of a comment. Comments can be entered anywhere in your printer definition table and are ignored by the printer table compiler.

A macro definition cannot contain another macro definition.

You can find a sample file, **IBM42 2.PDF**, on your PC/3270 diskettes. You can copy this file and modify the copy to create your custom printer definition table.

Printer Definition Tables

Standard printer definition table file names are of the form **IBM**nnnnn**.PDT**, and tables containing code page fonts are of the form **PRN**nnnnn**.PDT**, where nnnnn is a machine type.

Example Printer Definition File

The following example is an annotated version of a printer definition file for the IBM 4202 Proprinter. (This is an example only. The actual file might differ.)

Example 4202 Proprinter Definition

```
/                                   /
/                                                   /
/     PRINTER SESSION DEFINITION FILE FOR: Proprinter XL 42 2-1      /
/                                                   /
/                                   /
/                                   /
/                  Macro  Definitions                 /
/ Define values here that will be used commonly throughout your     /
/ definitions.   Then use the left hand side of the equate as you   /
/ define your characters and control strings.   The printer compiler  /
/ will substitute the right hand side of the equate for each      /
/ occurrence of the left hand side throughout the file.        /
/                                                   /
```

```
/ Macro names must be at least three characters long and may not        /
/ begin with a number.                                                  /
/                                                                       /
/ Format                                                                /
/ A Macro Name is associated with a value or string of values by the  /
/ EQU statement.  The right hand side of an EQU statement must be a   /
/ string of zero or more two digit hexadecimal numbers.  If a macro   /
/ definition is more than one line long, you may extend it to the     /
/ next line by ending the first line with a comma.  In this manner    /
/ you may define a macro which is many lines long by terminating each /
/ line except the last with a comma.  No macro names are allowed on   /
/ right hand side.                                                    /
/                                   /
BEGIN_MACROS
/ The following values are standard for most printers.  Check your    /
/ printer manual to verify that these are correct for your printer    /
NUL EQU                  / Nul character                 /
BEL EQU  7               / Beeper                        /
BAK EQU  8               / Back Space                    /
TAB EQU  9               / Tab                           /
LFF EQU  A               / Line Feed                     /
VTB EQU  B               / Vertical Tab                  /
FFF EQU  C               / Form Feed                     /
CRR EQU  D               / Carriage Return               /
P 5 EQU 1B 57  1         / 5 Pitch-Characters/inch       /
                         / Same as Double Wide           /
SEL EQU 11               / Select Printer                /
P1  EQU 12               / 1  Pitch-Characters/inch      /
CDW EQU 1B 57            / Cancel Double Wide contin.    /
CDL EQU 14               / Cancel Double Wide line       /
ESC EQU 1B               / Escape                        /
CAN EQU 18               / Cancel Data                   /
SPA EQU 2                / Space                         /
P17 EQU 12  F            / 17.1 Pitch-Characters/inch    /
CS2 EQU 1B 36            / Select Character Set 2        /
CS1 EQU 1B 37            / Select Character Set 1        /
P12 EQU 1B 3A            / 12 Pitch-characters/inch      /
SVT EQU 1B 42            / Set Vertical Tabs             /
SFL EQU 1B 43            / Set Form Length               /
SHT EQU 1B 44            / Set Horizontal Tabs           /
SDS EQU 1B 47            / Start Double Strike           /
CDS EQU 1B 48            / Cancel Double Strike          /
SSP EQU 1B 4E            / Set skip perforation          /
CSP EQU 1B 4F            / Cancel skip perforation       /
CAT EQU 1B 52            / Cancel all tabs Clears VT     /
                         / and sets HT every 8 position /
CSS EQU 1B 54            / Cancel Subscript or Superscr /
SSO EQU 1B 53            / Set Superscript over          /
SSU EQU 1B 53  1         / Set Subscript under           /
SUL EQU 1B 2D  1         / Start Underline               /
CUL EQU 1B 2D            / Cancel Underline              /
LL6 EQU 1B 41  C 1B 32 / Set line length 6 lines/inch /
LL8 EQU 1B 41  9 1B 32 / Set line length 8 lines/inch /
LL  EQU 1B 41  7 1B 32 / Set line length 1  lines/inc /
                         / actually 7/72 inch            /
SDQ EQU 1B 49            / Select Draft Printing Quality /
SLQ EQU 1B 49  2         / Select Letter Printing Quality /
END_MACROS
/                        Session  Parameters                          /
/ These parameters determine the way in which output will be          /
/ formatted for your printer.                                         /
/ Numeric Parameters                                                  /
/ These parameters should be defined with a two digit hex number      /
/ or a three digit decimal number.  The range of the number is zero   /
/ to 255 (decimal).                                                   /
MAXIMUM_PAGE_LENGTH= 66          / Printed lines per page          /
MAXIMUM_PRINT_POSITION=132       / Printed characters per line  /
INTERV_REQ_TIMER=  1
RESELECT_TIME_EXCPT_52 4=  1
INTERV_TIMER_ON_PE_ONLY?=NO
/ YES/NO Parameters                                                   /
/ These parameters should be defined with either "YES" or "NO" on the /
```

```
/ right hand side of the '='                                                    /
COMPRESS_LINE_SPACING?=NO          / Should blank or null lines    /
                                   / be printed?                   /
FORM_FEED_ANY_POSITION?=YES        / Should the form feed be       /
                                   / valid in any position?        /
OVERRIDE_FORMATTED_PRINT?=YES      / Should nulls be printed as    /
                                   / blanks?                       /
AUTO_NEWLINE_AT_MAX_POS?=NO
/                          Control  Codes                                       /
/ These definitions tell the emulator what control strings to send to /
/ your printer to issue control commands.                                       /
/                                                                               /
/ Format                                                                        /
/ The name of the control command should always be at the beginning    /
/ of a line followed by a '=' and then a definition string.           /
/ A Definition String is any combination of macro names, hexadecimal  /
/ numbers, and characters separated by blanks.    A macro must have   /
/ previously defined in the macro definitions section above. A        /
/ hexadecimal number must be two digits ( ,..,F) long. and a          /
/ character must be preceded and followed by a blank.    If a         /
/ definition string will not fit on a line, it may be continued      /
/ as many lines as you wish by ending each line except the last with  /
/ a comma;    ','.      You made add any comments you wish to by including /
/ them between a slash     and a  slash where slash is the symbol /.      /

/ START_JOB is the control string which will be sent to your printer  /
/ at the beginning of each print job.                                 /
START_JOB=SEL CDW CDL CUL CDS CS2
/ END_JOB is the string which will be sent to your printer at the end /
/ of each print job.                                                  /
END_JOB=CAT CDW CDL CUL CDS FFF
BACKSPACE=BAK
BEL=BEL
CARRIAGE_RETURN=CRR
NEW_LINE=CRR LFF
LINE_FEED=LFF
FORM_FEED=FFF
HORIZONTAL_TAB=TAB
VERTICAL_TAB=VTB
START_SUBSCRIPT=SSU
END_SUBSCRIPT=CSS
START_SUPERSCRIPT=SSO
END_SUPERSCRIPT=CSS
DUP=
FIELD_MARK=;
/ The following commands specify control codes for which most PC      /
/ printers require command strings which contain a variable value     /
/ or values somewhere in the middle of the string.                    /
/ Place the word "value(s)" in the position of your definition        /
/ string where the Personal Communications 327  should fill in        /
/ the hexadecimal value(s) indicated.                                 /
/ For example, on the IBM Proprinter, the SET_HORIZONTAL_TABS         /
/ definition is:                                                      /
/ SET_HORIZONTAL_TABS=ESC D values NUL                                          /
SET_HORIZONTAL_TABS=SHT values NUL    / "values" are the tab stops    /
                                      / in column numbers             /
SET_VERTICAL_TABS=SVT values NUL      / "values" are the tab stops    /
                                      / in line numbers               /
SET_HORIZONTAL_MARGINS=
SET_PAGE_LENGTH=SFL value             / "value"=number of lines       /
SET_AUTO_PERFORATION_SKIP=SSP value
                                      / "value"=number of lines to /
                                      / skip over the perforation     /
                                      / between pages.    Used to set /
                                      / top and bottom margins.       /
SET_VARIABLE_LINE_DENSITY=ESC A value ESC 2
                                      / "value"=number of points.  /
                                      / A point is 1/72 of an inch.  /
SET_CHARACTER_SET=
/ SET_CHARACTER_SET=ESC I NULL    selects the normal font             /
/ SET_CHARACTER_SET=ESC I  2    selects the NLQ (near letter quality)  /
/ SET_CHARACTER_SET=ESC I  4    selects the normal downloaded font     /
```

```
/ SET_CHARACTER_SET=ESC I 6   selects the NLQ downloaded font          /
/ SET_CHARACTER_SET=CS1           selects the Character set 1          /
/ SET_CHARACTER_SET=CS2           selects the Character set 2          /

/ These control codes set the printer lines per inch and characters    /
/ per inch to fixed amounts.                                           /
/ If your printer does not support setting the line density in points /
/ then you can enter control strings for the following commands.       /
/ When Personal Communications 327 gets a command from the host to     /
/ set the lines per inch, it will round it to the closest line per     /
/ inch setting that you provide.  Note that if you provide a command  /
/ for the SET_VARIABLE_LINE_DENSITY command above that it will be      /
/ used and any control strings you provide for the set lines per inch /
/ commands below will not be used.                                     /

SET_6_LINES_PER_INCH=LL6
SET_8_LINES_PER_INCH=LL8
SET_1 _LINES_PER_INCH=LL              / 7/72 inch or 9/96 inch         /
SET_1 _CHARACTERS_PER_INCH=P1
SET_12_CHARACTERS_PER_INCH=P12
SET_15_CHARACTERS_PER_INCH=           / The proprinter does not        /
                                      / support 15 pitch except in     /
                                      / graphs mode                    /
SET_17_CHARACTERS_PER_INCH=P17        / Condensed mode                 /
START_DOUBLE_WIDTH_CHARACTERS=P 5
END_DOUBLE_WIDTH_CHARACTERS=CDW

/ These control codes are used to select the source drawer number      /
/ when your printer has the dual drawer sheetfeed option.              /
SELECT_DRAWER1=
SELECT_DRAWER2=
SELECT_DRAWER3=
/ These control codes select the print mode (quality of print).        /
SELECT_DRAFT_QUALITY=SDQ
SELECT_LETTER_QUALITY=SLQ
SELECT_ENHANCED_QUALITY=
SELECT_SETUP_QUALITY=
/                          Color Specifications                        /
START_COLOR_BLUE=
END_COLOR_BLUE=
START_COLOR_GREEN=
END_COLOR_GREEN=
START_COLOR_CYAN=
END_COLOR_CYAN=
START_COLOR_RED=
END_COLOR_RED=
START_COLOR_MAGENTA=
END_COLOR_MAGENTA=
START_COLOR_YELLOW=
END_COLOR_YELLOW=
START_COLOR_BLACK=
END_COLOR_BLACK=
START_COLOR_WHITE=
END_COLOR_WHITE=

/                        Highlight Specifications                      /
/ These definitions will determine how things which are sent by the    /
/ host to be displayed or printed as underlined, reverse video, or     /
/ blinking will be highlighted on your printer.                        /

START_HIGHLIGHT_INTENSE=SDS           / This is double strike          /
END_HIGHLIGHT_INTENSE=CDS
START_HIGHLIGHT_UNDERLINE=SUL
END_HIGHLIGHT_UNDERLINE=CUL
START_HIGHLIGHT_REVERSE_VIDEO=
END_HIGHLIGHT_REVERSE_VIDEO=
START_HIGHLIGHT_BLINK=
END_HIGHLIGHT_BLINK=

/                        Character Definitions                         /
/ The remainder of the definitions are for printable characters.       /
/ See your users guide for the actual character referred to by each    /
```

```
/ character name.                                                    /
/ Format                                                             /
/ The format of a character definition is the same as for a control  /
/ code.                                                              /

SPACE=SPA
EXCLAMATION_POINT=21
QUOTATION_MARKS=22
NUMBER_SIGN=23
DOLLAR_SIGN=24
PERCENT_SIGN=25
AMPERSAND=26
APOSTROPHE=27
LEFT_PARENTHESIS=28
RIGHT_PARENTHESIS=29
ASTERISK=2A
PLUS_SIGN=2B
COMMA=2C
HYPHEN=2D
PERIOD=2E
SLASH=2F
ZERO=
ONE=1
TWO=2
THREE=3
FOUR=4
FIVE=5
SIX=6
SEVEN=7
EIGHT=8
NINE=9
COLON=3A
SEMICOLON=3B
LESS_THAN_SIGN=3C
EQUAL_SIGN=3D
GREATER_THAN_SIGN=3E
QUESTION_MARK=3F
AT_SIGN=4
A_CAPITAL=A
B_CAPITAL=B
C_CAPITAL=C
D_CAPITAL=D
E_CAPITAL=E
F_CAPITAL=F
G_CAPITAL=G
H_CAPITAL=H
I_CAPITAL=I
J_CAPITAL=J
K_CAPITAL=K
L_CAPITAL=L
M_CAPITAL=M
N_CAPITAL=N
O_CAPITAL=O
P_CAPITAL=P
Q_CAPITAL=Q
R_CAPITAL=R
S_CAPITAL=S
T_CAPITAL=T
U_CAPITAL=U
V_CAPITAL=V
W_CAPITAL=W
X_CAPITAL=X
Y_CAPITAL=Y
Z_CAPITAL=Z
LEFT_BRACKET=5B
BACKSLASH=5C
RIGHT_BRACKET=5D
CIRCUMFLEX_ACCENT=5E
UNDERLINE=5F
GRAVE_ACCENT=6
A_SMALL=a
B_SMALL=b
```

```
C_SMALL=c
D_SMALL=d
E_SMALL=e
F_SMALL=f
G_SMALL=g
H_SMALL=h
I_SMALL=i
J_SMALL=j
K_SMALL=k
L_SMALL=l
M_SMALL=m
N_SMALL=n
O_SMALL=o
P_SMALL=p
Q_SMALL=q
R_SMALL=r
S_SMALL=s
T_SMALL=t
U_SMALL=u
V_SMALL=v
W_SMALL=w
X_SMALL=x
Y_SMALL=y
Z_SMALL=z
LEFT_BRACE=7B
VERTICAL_BAR=B3
RIGHT_BRACE=7D
TILDE_ACCENT=7E
C_CEDILLA_CAPITAL=8
U_DIAERESIS_SMALL=81
E_ACUTE_SMALL=82
A_CIRCUMFLEX_SMALL=83
A_DIAERESIS_SMALL=84
A_GRAVE_SMALL=85
A_OVERCIRCLE_SMALL=ESC 4C  8     6 6A AA AA 6A 1E  2
C_CEDILLA_SMALL=87
E_CIRCUMFLEX_SMALL=88
E_DIAERESIS_SMALL=89
E_GRAVE_SMALL=8A
I_DIAERESIS_SMALL=8B
I_CIRCUMFLEX_SMALL=8C
I_GRAVE_SMALL=8D
A_DIAERESIS_CAPITAL=8E
A_OVERCIRCLE_CAPITAL=8F
E_ACUTE_CAPITAL=9
AE_DIPTHONG_SMALL=91
AE_DIPTHONG_CAPITAL=92
O_CIRCUMFLEX_SMALL=93
O_DIAERESIS_SMALL=94
O_GRAVE_SMALL=95
U_CIRCUMFLEX_SMALL=96
U_GRAVE_SMALL=97
Y_DIAERESIS_SMALL=98
O_DIAERESIS_CAPITAL=99
U_DIAERESIS_CAPITAL=9A
/                                                  /
/ The following character is printed by printing an o    (6F) then       /
/ backspacing(BAK) and over printing with a slash(2F).                     /
/                                                  /
O_SLASH_SMALL=6F BAK 2F
POUND_SIGN=9C
O_SLASH_CAPITAL=4F BAK 2F
/                                                  /
/ The following escape sequence defines the character in all points  /
/ addressable mode (APA).    The ESC 4C starts the APA mode.    The          /
/  8    is the count low and count high and defines eight bytes of     /
/ APA data. The    44 28 1  28 44       are the eight bytes of data. /
/ A bit set to 1 prints the dot and a bit set to   does not print.     /
/ The most significant bit prints as the top dot.    The least               /
/ significant bit prints as the bottom dot.    The first byte is            /
/ printed on the left following the last character.    The next byte     /
/ is printed to the right one dot column to the right of the last       /
```

```
/ byte etc..  Refer to the Proprinter Guide to Operations for          /
/ more information.                                                    /
/                                                                      /
MULTIPLY_SIGN=ESC 4C  8      44 28 1  28 44
A_ACUTE_SMALL=A
I_ACUTE_SMALL=A1
O_ACUTE_SMALL=ESC 4C  8    C 12 12 52 92 12  C
U_ACUTE_SMALL=A3
N_TILDE_SMALL=A4
N_TILDE_CAPITAL=A5
ORDINAL_INDICATOR_FEMININE=A6
ORDINAL_INDICATOR_MASCULINE=A7
QUESTION_MARK_INVERTED=A8
REGISTERED_TRADEMARK_SYMBOL=ESC 4C  9   7E 81 BD A9 B9 A5 81 7E
LOGICAL_NOT=AA
ONE_HALF=AB
ONE_QUARTER=AC
EXCLAMATION_POINT_INVERTED=AD
LEFT_ANGLE_QUOTES=AE
RIGHT_ANGLE_QUOTES=AF
A_ACUTE_CAPITAL=ESC 4C  8    6  C 54 A4 14  C  6
A_CIRCUMFLEX_CAPITAL=ESC 4C  8    6 4C 94 A4 94 4C  6
A_GRAVE_CAPITAL=ESC 4C  8    6  C 14 A4 54 4C  6
COPYRIGHT_SYMBOL=ESC 4C  9   7E 81 99 A5 A5 A5 81 7E
CENT_SIGN=9B
YEN_SIGN= 9D
A_TILDE_SMALL=ESC 4C  9    6 2A 2A CA AA 5E 42 8
A_TILDE_CAPITAL=ESC 4C  8    6 4C 94 A4 54 4C 86
INTERNATIONAL_CURRENCY_SYMBOL=ESC 4C  9   82 54 28 44 44 28 54 82
ETH_ICELANDIC_SMALL=EB
ETH_ICELANDIC_CAPITAL=ESC 4C  8   92 FE 92 92 44 7C 38
E_CIRCUMFLEX_CAPITAL=ESC 4C  8   3E 6A AA AA AA 62 22
E_DIAERESIS_CAPITAL=ESC 4C  8   3E AA AA 2A 2A A2 A2
E_GRAVE_CAPITAL=ESC 4C  8   3E 2A 2A AA 6A 22 22
I_DOTLESS_SMALL=ESC 4C  8        12 1E  2
I_ACUTE_CAPITAL=ESC 4C  8        52 9E 12
I_CIRCUMFLEX_CAPITAL=ESC 4C  8      4  92 9E 92 4
I_DIAERESIS_CAPITAL=ESC 4C  8      4  52 1E 52 4
VERTICAL_LINE_BROKEN=ESC 4C  8           77
I_GRAVE_CAPITAL=ESC 4C  8        12 9E 52
O_ACUTE_CAPITAL=ESC 4C  8    E 11 11 51 81 11  E
SHARP_S_SMALL=ESC 4C  8    2 3E 4  52 52 2A  4
O_CIRCUMFLEX_CAPITAL=ESC 4C  8   1C 22 62 A2 A2 62 1C
O_GRAVE_CAPITAL=ESC 4C  8   1C 22 22 A2 62 22 1C
O_TILDE_SMALL=ESC 4C  8    C 12 52 92 52 92 8C
O_TILDE_CAPITAL=ESC 4C  8   1C 22 62 A2 62 A2 9C
MICRO_SYMBOL=E6
THORN_ICELANDIC_SMALL=ESC 4C  8    2 FC   48 3  3
THORN_ICELANDIC_CAPITAL=ESC 4C  8   81 FF FF 42 24 3C 18
U_ACUTE_CAPITAL=ESC 4C  8   3C  2 42 82  2  2 3C
U_CIRCUMFLEX_CAPITAL=ESC 4C  8   3C  2 42 82 82 42 3C
U_GRAVE_CAPITAL=ESC 4C  8   3C  2  2 82 42  2 3C
Y_ACUTE_SMALL=ESC 4C  8   2  1  4A 84  8 1  2
Y_ACUTE_CAPITAL=ESC 4C  8   2  1  48 86  8 1  2
OVERLINE=ESC 4C  8   8  8  8  8  8  8  8
ACUTE_ACCENT=ESC 4C  8        4  8
SYLLABLE_HYPHEN=ESC 4C  8   1  1  1
PLUS_OR_MINUS_SIGN=F1
THREE_QUARTERS=ESC 4C  9   89 AA 74  8 16 2A 47 82
PARAGRAPH_SYMBOL=ESC 4C  8   6  F  FE      FE
SECTION_SYMBOL=ESC 4C  8   3  4B A9 A5 95 D2  C
DIVIDE_SIGN=F6
CEDILLA=ESC 4C  8           3  C  C
DEGREE_SYMBOL=F8
DIAERESIS=ESC 4C  8      8  8       8  8
MIDDLE_DOT_ACCENT=F9
ONE_SUPERSCRIPT=ESC 4C  8        48 F8  8
THREE_SUPERSCRIPT=ESC 4C  8        88 A8 A8 D8
TWO_SUPERSCRIPT=ESC 4C  8      48 98 A8 A8 48
REQUIRED_SPACE=FF
/                                                                      /
/                        PC/327  Internal Data Area.                   /
```

```
/ Do not change these statement.                                    /
/                                        /
TOP_MARGIN=
LEFT_MARGIN=
DYNAMIC_START_JOB=
DYNAMIC_END_JOB=
DYNAMIC_SET_PAGE_LENGTH=
PRINTER_ID=42  2
/                          End of Definition File                   /
```

Supplemental Explanation of PDF Statements

The PDF statements listed below have the following functions.

MAXIMUM_PAGE_LENGTH
Printed lines per page. If you change this value, you must change the value in the "SET_PAGE_LENGTH=SFL value" statement to be the same.

MAXIMUM_PRINT_POSITION
Printed characters per line.

COMPRESS_LINE_SPACING?
(For LU 3 only) Whether blank or null lines are to be printed if all characters on that line are nulls.

FORM_FEED_ANY_POSITION?
Whether a form feed is to be valid in any position. If NO, a form feed will be valid only in the following positions:

First print-position of the buffer
After a valid new line operation
First print-position of a line

OVERRIDE_FORMATTED_PRINT?
Whether nulls are to be printed as blanks.

INTERV_REQ_TIMER
This statement is ignored.

INTERV_TIMER_ON_PE_ONLY?
This statement is ignored.

RESELECT_TIME_EXCPT_5204
This statement is ignored.

ESC/P_LINE_FEED?
If YES, the line feed (LF) function is emulated when the line feed command is received. This is useful when you do not want a line feed accompanied by a carriage return (CR) on a printer using the ESC/P printer language. If NO, the value defined in the LINE_FEED statement is sent to the printer.

FFAnyPos? If YES, the form feed (FF) function is effective in any position (for LU 2, LU 3, and non-SNA sessions only).

IGNORE_FORM_FEED_AT_FIRST_POS?
If YES, the form feed (FF) function is ignored at the first position (for LU 2, LU 3, and non-SNA sessions) or at the beginning of the print job (for LU 1 sessions). Using this option eliminates extra blank pages at the beginning of each print job.

FORM_FEED_TAKES_POSITION?
If YES, the form feed (FF) function is effective if followed by data (LU 2, LU 3, and non-SNA sessions only).

SCS TAB Setting

A PC/3270 printer session LU type 1 can accept any number of tab positions, and the host printer session can send any number of tabs to the printer session. However, the workstation printer you are using might support fewer tab positions than the host application sets; for example, the IBM Proprinter supports 27 tab positions.

If the number of tab positions that the host application sets exceeds the maximum number of positions that the printer supports, your printed output will not look as you expect it to. You can avoid this situation by modifying the PDF file and reconfiguring PC/3270 as follows:

Modify the SET_HORIZONTAL_TABS statement as follows:

SET_HORIZONTAL_TABS=*number*

Save the file under a new name.

Convert the PDF file (with the procedure described on "Customizing the Printer Definition Table" on page 10-1).

Select a new PDT file created by the above step.

Printer Definition File Field Names and Symbols

The following table lists the symbols that are defined for printer definition files.

Table 10-1 (Page 1 of 3). Printer Symbol Definitions

Field Name	Symbol
SPACE	
EXCLAMATION_POINT	!
QUOTATION_MARKS	"
NUMBER_SIGN	#
DOLLAR_SIGN	$
PERCENT_SIGN	%
AMPERSAND	&
APOSTROPHE	'
LEFT_PARENTHESIS	(
RIGHT_PARENTHESIS	)
ASTERISK	*
PLUS_SIGN	+
COMMA	,
HYPHEN	-
PERIOD	.
SLASH	/
ZERO	0
ONE	1
TWO	2
THREE	3

Table 10-1 (Page 1 of 3). Printer Symbol Definitions

Field Name	Symbol
FOUR	4
FIVE	5
SIX	6
SEVEN	7
EIGHT	8
NINE	9
COLON	:
SEMICOLON	;
LESS_THAN_SIGN	<
EQUAL_SIGN	=
GREATER_THAN_SIGN	>
QUESTION_MARK	?
AT_SIGN	@
A_CAPITAL	A
B_CAPITAL	B
C_CAPITAL	C
D_CAPITAL	D
E_CAPITAL	E
F_CAPITAL	F
G_CAPITAL	G

Table 10-1 (Page 2 of 3). Printer Symbol Definitions

Field Name	Symbol
H_CAPITAL	H
I_CAPITAL	I
J_CAPITAL	J
K_CAPITAL	K
L_CAPITAL	L
M_CAPITAL	M
N_CAPITAL	N
O_CAPITAL	O
P_CAPITAL	P
Q_CAPITAL	Q
R_CAPITAL	R
S_CAPITAL	S
T_CAPITAL	T
U_CAPITAL	U
V_CAPITAL	V
W_CAPITAL	W
X_CAPITAL	X
Y_CAPITAL	Y
Z_CAPITAL	Z
LEFT_BRACKET	[
BACKSLASH	\
RIGHT_BRACKET	]
CIRCUMFLEX_ACCENT	^
UNDERLINE	_
GRAVE_ACCENT	`
A_SMALL	a
B_SMALL	b
C_SMALL	c
D_SMALL	d
E_SMALL	e
F_SMALL	f
G_SMALL	g
H_SMALL	h
I_SMALL	i
J_SMALL	j
K_SMALL	k
L_SMALL	l
M_SMALL	m
N_SMALL	n
O_SMALL	o
P_SMALL	p
Q_SMALL	q
R_SMALL	r

Table 10-1 (Page 2 of 3). Printer Symbol Definitions

Field Name	Symbol
S_SMALL	s
T_SMALL	t
U_SMALL	u
V_SMALL	v
W_SMALL	w
X_SMALL	x
Y_SMALL	y
Z_SMALL	z
LEFT_BRACE	{
VERTICAL_BAR	|
RIGHT_BRACE	}
TILDE_ACCENT	~
C_CEDILLA_CAPITAL	Ç
U_DIAERESIS_SMALL	ü
E_ACUTE_SMALL	é
A_CIRCUMFLEX_SMALL	â
A_DIAERESIS_SMALL	ä
A_GRAVE_SMALL	à
A_OVERCIRCLE_SMALL	å
C_CEDILLA_SMALL	ç
E_CIRCUMFLEX_SMALL	ê
E_DIAERESIS_SMALL	ë
E_GRAVE_SMALL	è
I_DIAERESIS_SMALL	ï
I_CIRCUMFLEX_SMALL	î
I_GRAVE_SMALL	ì
A_DIAERESIS_CAPITAL	Ä
A_OVERCIRCLE_CAPITAL	Å
E_ACUTE_CAPITAL	É
AE_DIPTHONG_SMALL	æ
AE_DIPTHONG_CAPITAL	Æ
O_CIRCUMFLEX_SMALL	ô
O_DIAERESIS_SMALL	ö
O_GRAVE_SMALL	ò
U_CIRCUMFLEX_SMALL	û
U_GRAVE_SMALL	ù
Y_DIAERESIS_SMALL	ÿ
O_DIAERESIS_CAPITAL	Ö
U_DIAERESIS_CAPITAL	Ü
O_SLASH_SMALL	ø
POUND_SIGN	£
O_SLASH_CAPITAL	Ø
MULTIPLY_SIGN	×

Table 10-1 (Page 3 of 3). Printer Symbol Definitions

Field Name	Symbol
A_ACUTE_SMALL	á
I_ACUTE_SMALL	í
O_ACUTE_SMALL	ó
U_ACUTE_SMALL	ú
N_TILDE_SMALL	ñ
N_TILDE_CAPITAL	Ñ
ORDINAL_INDICATOR_FEMININE	a
ORDINAL_INDICATOR_MASCULINE	o
QUESTION_MARK_INVERTED	¿
REGISTERED_TRADEMARK_SYMBOL	®
LOGICAL_NOT	¬
ONE_HALF	½
ONE_QUARTER	¼
EXCLAMATION_POINT_INVERTED	¡
LEFT_ANGLE_QUOTES	«
RIGHT_ANGLE_QUOTES	»
A_ACUTE_CAPITAL	Á
A_CIRCUMFLEX_CAPITAL	Â
A_GRAVE_CAPITAL	À
COPYRIGHT_SYMBOL	©
CENT_SIGN	¢
YEN_SIGN	¥
A_TILDE_SMALL	ã
A_TILDE_CAPITAL	Ã
E_CIRCUMFLEX_CAPITAL	Ê
E_DIAERESIS_CAPITAL	Ë
I_ACUTE_CAPITAL	Í
I_CIRCUMFLEX_CAPITAL	Î
I_DIAERESIS_CAPITAL	Ï
VERTICAL_LINE_BROKEN	¦
I_GRAVE_CAPITAL	Ì
O_ACUTE_CAPITAL	Ó
O_CIRCUMFLEX_CAPITAL	Ô
O_GRAVE_CAPITAL	Ò
O_TILDE_SMALL	õ
O_TILDE_CAPITAL	Õ
MICRO_SYMBOL	µ
U_ACUTE_CAPITAL	Ú
U_CIRCUMFLEX_CAPITAL	Û
U_GRAVE_CAPITAL	Ù
ACUTE_ACCENT	´
SYLLABLE_HYPHEN	-
PLUS_OR_MINUS_SIGN	±

Table 10-1 (Page 3 of 3). Printer Symbol Definitions

Field Name	Symbol
THREE_QUARTERS	¾
PARAGRAPH_SYMBOL	¶
SECTION_SYMBOL	§
DIVIDE_SIGN	÷
DEGREE_SYMBOL	°
ONE_SUPERSCRIPT	
THREE_SUPERSCRIPT	
TWO_SUPERSCRIPT	
REQUIRED_SPACE	
INTERNATIONAL_CURRENCY_SYMBOL	¤
ETH_ICELANDIC_SMALL	ð
ETH_ICELANDIC_CAPITAL	Ð
SHARP_S_SMALL	ß
THORN_ICELANDIC_SMALL	þ
THORN_ICELANDIC_CAPITAL	Þ
Y_ACUTE_SMALL	ý
Y_ACUTE_CAPITAL	Ý
OVERLINE	¯
CEDILLA	¸
DIAERESIS	..
MIDDLE_DOT_ACCENT	.

Printer Color Mixing

Some printers, such as the IBM 5182, compose certain colors by mixing colors. Colors are mixed by printing the text in one color and then printing over the same text in another color on a second pass.

PC/3270 will compose a color if the color is not defined in the printer definition table of a color printer that is capable of mixing colors. Therefore, if you are using a printer that composes some colors by mixing two colors, leave the definition of the composed colors blank in the printer definition file. Only the composite colors defined in Table 10-2 are created by double-printing the primary colors.

Table 10-2. Color Mixes

Composite Color	Primary Colors
Red	yellow, magenta
Green	yellow, cyan
Blue	magenta, cyan

For example, to create red, you must define yellow and magenta. The primary colors must be defined in the printer definition table.

Printer Session Data Stream Support

There are two types of host-directed print data streams supported by PC/3270: the 3270 data stream and the SNA character string (SCS) data stream.

3270 Data Stream

The 3270 data stream is a buffer-oriented data stream. The print data is formatted as if it were going to be displayed on a screen. The host system sends commands to format the presentation space. These commands can change the presentation space in any location at any time. Once the host system completes formatting the presentation space, it issues a START PRINT command and the presentation space is printed as accurately as the printer hardware allows. The 3270 data stream can be sent to PC/3270 workstations over an SNA LU 3 session or a non-SNA DFT printer session.

Table 10-3 lists the commands that can be sent in the 3270 data stream.

Table 10-3. 3270 Data Stream Commands

Command	Meaning
W	Write
EW	Erase/Write
EWA	Erase/Write Alternate
RB	Read Buffer
RM	Read Modified
RMA	Read Modified All
EAU	Erase All Unprotected
WSF	Write Structured Field

The RB, RM, and RMA commands cannot be used with an SNA attachment.

Table 10-4 lists the orders that can be sent in the 3270 data stream.

Table 10-4. 3270 Data Stream Orders

Order	Meaning
SBA	Start Buffer Address
SSF	Start Field
IC	Insert Cursor
PT	Program Tab
RA	Repeat to Address
EUA	Erase Unprotected to Address
SFE	Start Field Extended
SA	Set Attribute
MF	Modify Field

The last three orders in this list manage the color, extended highlighting, and programmed symbols attributes for fields and individual characters. The programmed symbols attribute is not supported by PC/3270.

In addition to the commands and orders in the preceding list, there are special printer formatting control codes that can be included in the 3270 data stream.

Table 10-5 lists the control codes that can be sent in the 3270 data stream.

Table 10-5. 3270 Data Stream Control Codes

Code	Description
NL	New Line control code moves the print position to the left margin and down one line.
CR	Carriage Return control code moves the print position to the left margin.
EM	End of Message control code ends the print operation.
FF	Form Feed control code moves the print position to the left margin at the top of the next page.

Note: NL, CR, and EM are valid only if a line-length format specified by the WCC is not used. The FF code is valid in any buffer position.

PC/3270 printer support interprets each 3270 attribute and printer control code and translates them into a sequence of one or more workstation printer control codes. For more information about the 3270 data stream, refer to *IBM 3270 Information Display Data Stream Programmer's Reference*.

SCS Data Stream

The SCS data stream is a sequential data stream that is oriented toward line printers. The characters are translated according to the host system code page and printed according to the attributes and formatting specified by the control commands. The way in which SCS characters are printed depends only on the control codes that precede them. Therefore, it is not necessary to buffer the characters before they are printed. The SCS data stream flows across the SNA LU 1 session only.

The valid SCS control codes supported by PC/3270 are listed in Table 10-6.

Table 10-6 (Page 1 of 2). Supported SCS Control Codes

Code	Value	Command
NL	X'15'	New Line
LF	X'25'	Linefeed (Index)
CR	X'0D'	Carriage Return
FF	X'0C'	Form Feed
BS	X'16'	Backspace
BEL	X'2F'	Bell Function
IRS	X'1E'	Interchange-Record Separator
SA	X'28'	Set Attribute

Table 10-6 (Page 2 of 2). Supported SCS Control Codes

Code	Value	Command
TRN	X'35'	Transparent
NUL	X'00'	Null
HT	X'05'	Horizontal Tab
VT	X'0B'	Vertical Tab
SHF	X'2B C1'	Set Horizontal Format
SVF	X'2B C2'	Set Vertical Format
SLD	X'2BC 6'	Set Line Density
SPD	X'2BD2 xx29'	Set Print Density
VCS	X'04 xx'	Vertical Channel Select
ENP	X'14'	Enable Presentation
INP	X'24'	Inhibit Presentation
GE	X'08'	Graphic Escape
PPM	X'2BD2 xx48'	Page Presentation Media

Note: The ENP and INP commands are accepted, but are ignored, in an LU 1 session.

For more information about the SCS printer data stream, refer to *IBM Systems Network Architecture - Sessions Between Logical Units*.

Delimiting Print Jobs

Many print jobs can be sent over a single PC/3270 printer session. PC/3270 allows multiple sessions and applications to share a single workstation printer on a between-jobs basis. PC/3270 needs to know when each print job starts and ends so that printers can be shared properly and begin and end job strings can be sent at the appropriate times. The emulator recognizes a number of different methods of delimiting print jobs:

By Session PC/3270 printer support assumes, by default, that all print jobs are delimited by sessions. That is, in the absence of all other indicators, PC/3270 assumes that a print job begins when a printer session is started and ends when it is reset.

Time-Out Interval On non-SNA DFT sessions, print jobs can be delimited by a user-specified timeout interval. A print job on a non-SNA DFT printer session begins when the first host-outbound data for that job is received, and ends when no host-outbound data is received for a period of time exceeding the user-specified non-SNA DFT timeout interval. For PC/3270, this interval is specified during configuration.

By Brackets On an SNA session with an LU 1 or LU 3 host application, PC/3270 can use bracket indicators to delimit print jobs. The emulator opens the printer when it receives the begin bracket, then it processes and prints data. The emulator closes the printer after it receives an end bracket.

When the emulator receives another begin bracket, it again opens a printer and begins processing a print job.

Structured Fields The host can use structured fields to indicate to the device that a new file is beginning or that the current file is completed. PC/3270 delimits print jobs with Begin of File and End of File structured fields (SF) to perform host-directed printing. Structured fields are described in the next section.

Structured Fields

The host uses Begin of File and End of File structured fields to indicate to a device that a file is beginning or ending.

Begin/End of File Query Reply

The Begin/End of File query reply indicates that a device supports Begin of File and End of File to delineate print jobs. The PC/3270 sends a query reply, as shown in Table 10-7, to the host in response to a Read Partition General query.

Table 10-7. Begin/End of File Query Reply Format

Byte	Contents	Description
0–1	X'0005'	The length of this structure
2	X'81'	Query reply
3	QCODE X'9F'	Begin/End of File
4	FLAGS	Reserved; must be set to 0's

Begin/End of File Structured Fields

Begin/End of File structured fields are accepted on either LU 1 or LU 3 sessions. Table 10-8 shows the format of the Begin/End of File structured fields.

Table 10-8. Begin/End of File Structured Field Format

Byte	Bit	Contents	Description
0–1		X'0007'	The length of this structure
2–3		X'0F85'	Begin/End of File
4		PID	Partition ID
5		FLAG1	
	0–1	B'00'	Reserved
		B'01'	End of File is being sent
		B'10'	Begin of File is being sent
		B'11'	Reserved
	2–7		Reserved
6		FLAG2	Reserved; must be set to 0's.

This byte indicates whether Begin of File or End of File is being sent.

Processing Begin/End of File Structured Fields: When the Begin/End of File structured fields are used with brackets or non-SNA timeout intervals, the Begin/End of File SFs take precedence over the brackets or timeout intervals in determining when a print job begins or ends. Refer to the following examples:

Begin/End of File structured fields overriding brackets:

Begin Bracket, Begin of File Structured Field, ...Data...,
End Bracket

The device will wait indefinitely until the End of File structured fields is received before ending the print job.

Begin/End of File structured fields overriding non-SNA timeout intervals:

Begin of File structured fields, ...Data..., pause > timeout value

The device will wait indefinitely until the End of File structured fields is received before ending the print job.

Inconsistent use of Begin/End of File structured fields and brackets:

Begin Bracket, ...Data1...,
Begin of File Structured Fields,...Data2..,
End of File Structured Fields, ...Data3...,
End Bracket

When you use the Begin of File and End of File structured fields inconsistently with brackets, the results are unpredictable. In the preceding example, the device might process Data1, Data2, and Data3 as separate jobs or combine two or more of them into one file.

For predictable results, each data block must be enclosed by a Begin of File structured field and an End of File structured field. The following example shows three print jobs all delimited by Begin/End of File structured fields:

Begin Bracket, Begin of File Structured Field, ...Data1...,
End of File Structured Field,(job1)
Begin of File Structured Field, ...Data2..., End of File Structured Field, (job2)
Begin of File Structured Field, ...Data3..., End of File Structured Field,
End Bracket(job3)

PC/3270 always keeps track of brackets and timeout intervals. After the emulator receives a Begin of File structured field, it takes no action on Begin Brackets, End Brackets, or timeout until it receives an End of File structured field. Once a valid End of File SF is processed, the emulator defaults to delimiting jobs by brackets or timeout intervals until it receives the next Begin of File structured field.

Begin/End of File Structured Field Error Conditions: PC/3270 does not accept transmission of data belonging to two separate print jobs in the same chain. To be accepted by the emulator, Begin of File structured fields must be the first structured field of a chain and End of File structured fields must be the last structured field of a chain.

PC/3270 rejects transmission in the following instances:

The emulator receives an End of File structured field without first receiving a Begin of File structured field.

The emulator receives a second Begin of File structured field without receiving an intervening End of File structured field.

The emulator receives a Begin of File structured field that is not the first structured field following a **write structured field** command (LU 2, LU 3, and non-SNA sessions) or a Function Management Header 1 (LU 1 sessions).

The emulator receives an End of File structured field that is not the last structured field following a **write structured field** command (LU 2, LU 3, and non-SNA sessions) or a Function Management Header 1 (LU 1 sessions).

Processing SCS Data Streams: When processing an SCS data stream, PC/3270 treats Begin/End of File structured fields as follows:

A Begin of File structured field indicates that all SCS data in the same transmission until an End of File structured field is received is part of a new print job.

An End of File structured field indicates that any SCS data received in the same chain as the End of File structured field is the last data of the current print job.

Processing 3270 Data Streams: When processing a 3270 data stream, PC/3270 treats Begin/End of File structured fields as follows:

A Begin of File structured field indicates that the next presentation space print (initiated by a **write type** command with the start print bit turned on in the write control character) is the first in a print job.

An End of File structured field indicates that the last presentation space print was the last of the current print job. The emulator immediately sends a terminate string to the printer to close the printer session.

If PC/3270 receives a Begin of File structured field and an End of File structured field without at least one presentation space separating them, it ignores the structured fields.

Building PC/3270 PDTs

Chapter 11. File Transfer Commands for PC/3270

You can send data files to and receive them from IBM host systems that are running:

CICS/MVS	Customer Information Control System running under MVS
CICS/VSE	CICS running under Virtual Storage Extended
MVS/TSO	Multiple Virtual Storage/Time Sharing Option
OV/MVS	OfficeVision/MVS
VM/CMS	Virtual Machine/Conversational Monitor System

For more information on using these commands, select **Help** from the Personal Communications menu bar, then select **Commands** and **Transfer** in the pop-ups that follow.

File Transfer Methods

You can transfer files in the following ways with PC/3270:

By using the *Transfer* menu of the workstation window
By using the **SEND** and **RECEIVE** commands at the DOS command prompt

Requirements and Restrictions

Install the file transfer program, IND$FILE, at your host system. Ask your system administrator for additional file transfer procedures and precautions.

An alternate host command name can be used by defining a DOS environment variable IND$FILE before starting Windows. For example:

```
SET IND$FILE = MYXFER
```

You should not use the following words as a VM file name or file type, as an MVS data set name, or as a CICS file name, because they are reserved for use as option commands. However, if you must use them for files, add a '\' (backslash), with a space before and after, immediately after the file name and so on, even if you do not specify any options.

ASCII, APPEND, TIME, CLEAR, NOCLEAR, SILENT, QUIET, PROGRESS, JISCII, SO, NOSO, BLANK, USER, CRLF, BINARY, NOCRLF

For example:

```
SEND c:\MYFILE a:APPEND \ QUIET \ H
```

© Copyright IBM Corp. 1989, 1996

Sending and Receiving Files from the DOS Command Prompt

The PC is the point of reference for the SEND and RECEIVE commands: You send from the PC to the host and receive from the host to the PC.

To send or receive a file:

1. Make sure you are logged on to your host.
2. Make sure the **Ready** message of the host system is displayed, except if you are transferring files through the command option of the ISPF application.

   Note: In the latter case, you must specify the NOCLEAR option for the file transfer command.

   If your screen is blank, make sure that no applications are running and that your host session is not in a *holding* state.

   Note: If you receive any messages from host application programs while you are transferring files, the transfer might not succeed. To prevent messages from interfering, enter the appropriate host command to set messages off temporarily. When file transfer is finished, set messages on again.
3. Switch to your DOS window session or DOS full-screen session.
4. If you use a hard disk, make sure the **SEND.EXE** and **RECEIVE.EXE** files are in your current directory or in your path.
5. Type the appropriate SEND or RECEIVE command at the DOS command prompt.

   Details on the SEND and RECEIVE commands and their options are explained in the following sections.

Using the VM/CMS SEND Command

Use the following information when sending a file to VM/CMS:

Figure 11-1 shows the command and information that you must provide. Enter it as shown (including parentheses). You can use either uppercase or lowercase letters.

Note: means to insert a space. There must *not* be a space between **h:** and **fn**.



Figure 11-1. VM/CMS SEND Command Syntax

A The PC drive and path of the file to send.

B The name of the PC file to send.

C Host session specifications for the file to be sent to the host.

- h: The short name of the session (which can be omitted if it is **a**)
- fn File name
- ft File type
- fm File mode

D Optional changes made to the file during transfer. More than one option can be selected. Valid options are:

APPEND
ASCII
CLEAR
CRLF
LRECL n
NOCLEAR
PROGRESS
QUIET
RECFM x
TIME n

The parts of the VM/CMS SEND command are:

SEND — The command.

d: — The name of the diskette or hard disk drive on which the file is located.

path — The path to the subdirectory that the file is in.

filename.ext — The name of the file to be sent, including the extension.

h: — The short name of the host session to which you want to send the file. The default is a:.

fn ft fm — The name the file is to have on your VM/CMS disk. You must specify the file name (fn) and file type (ft). You can omit file mode (fm) if you want the file placed on your A-disk. You can create a new name or use a name that is already on your disk. If you use a new name, the file that you send is added to your disk. If you use

the name of an existing file, the file that you send either replaces or is added to the old file. (Refer to the description of the APPEND option.)

(options

These options can be specified:

APPEND
Specifies that the file being sent is to be added to the end of an existing VM/CMS file. Omit this option if you want the file to replace an existing file. You cannot specify the LRECL n or RECFM x option if you use the APPEND option.

ASCII Specifies ASCII-to-EBCDIC character translation.

CLEAR
Clears the workstation window at the beginning of the file transfer. **CLEAR** is the default.

CRLF Specifies preserving of the carriage return and line feed codes. You need the ASCII and CRLF options for text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files, such as programs.

LRECL n
Specifies the file's record length. Include a record length only if you want the file to have a record length on your VM/CMS disk other than 80. Replace n with the record length you want. If you omit this option, the record length is set to 80 for fixed-length records or to a maximum of 80 for variable-length records.

NOCLEAR
Suppresses the sending of a Clear command at the beginning of the file transfer.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

RECFM x
Specifies the file record format. Use this parameter to specify variable-length or fixed-length records in the file. Replace x with V for variable or F for fixed. By default, the file has fixed-length records unless you specify the CRLF option; then the file has variable-length records unless you specify otherwise.

TIME n
Specifies the length of time n, in units of 30 seconds, that the program waits for a response from the host before it sends an error message. Replace n with an integer value in the range from 1 through 2184. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, of large block sizes, or for slow communication lines (such as SDLC and ASYNCH), 3 seconds is recommended. At least one blank space is required between TIME and n.

Examples

The following examples show the command syntax you can use to send files. The parameters of the SEND command can be combined into a single set of parentheses.

To send a PC file from your default drive and add it as a new file on your VM/CMS A-disk:

SEND pc.txt a:cmsfile script a (ASCII CRLF LRECL 72 RECFM V

Note: If you use a command that exceeds one line, do not press Enter when you fill that line; continue typing your command.

This command sends a PC file named **PC.TXT** from your default drive to your host in your host session named **a**. You do not need to specify the PC drive if the file you are sending is on the current drive. The command creates a new file, named **CMSFILE SCRIPT**, on your A-disk. The records in the file can vary in length up to 72 characters.

To send a PC file from your default drive to replace a file on your VM/CMS A-disk:

SEND pc.txt a:cmsfile script a (ASCII CRLF

This command sends a PC file named **PC.TXT** from your default drive to your VM/CMS A-disk in your host session named **a**. You do not need to name the PC drive if the file you are sending is on the default drive. The file replaces a **SCRIPT** file named **CMSFILE**. The new **CMSFILE** has the same record length and format as the old **CMSFILE**.

If you do not have a file called **CMSFILE SCRIPT** on your A-disk, **PC.TXT** is added to your A-disk as a new file called **CMSFILE SCRIPT**. The records in the file are 80 characters long and have fixed length.

To send a binary PC file from a drive other than your default drive:

SEND a:pc.exe c:cmsfile exebin b

This command sends a PC file named **PC.EXE** from a diskette in drive A to your VM/CMS B-disk in your host session named **c**. It is a new file, or it replaces a file named **CMSFILE**.

The records in the file are 80 characters long and have fixed length.

To send a file from your hard disk and add it to the end of a file on your VM/CMS A-disk:

SEND c:pc.txt cmsfile script a (ASCII CRLF APPEND

This command sends a PC file named **PC.TXT** from your hard disk to your host session. You do not need to name the host session if you are sending to the **a** session. The file is added to the end of a script file named **CMSFILE** on your VM/CMS A-disk.

To send a file from a subdirectory on your hard disk to your VM/CMS A-disk:

SEND c:\sd1\pc.txt cmsfile script a (ASCII CRLF

This command sends a file named **PC.TXT** from subdirectory **SD1** on your hard disk to your host session. It replaces a **SCRIPT** file named **CMSFILE** on your VM/CMS A-disk.

Using the VM/CMS RECEIVE Command

Use the following information when receiving a file from VM/CMS:

Figure 11-2 shows the command and information you must provide. Enter it as shown (including parentheses), except that you can use either uppercase or lowercase letters.

Note: means to insert a space. There must *not* be a space between **h:** and **fn**.



Figure 11-2. VM/CMS RECEIVE Command Syntax

A The PC drive and path of the file to be received.

B The name of the PC file to be received.

C Host session specifications for the file to be received from the host.

- h: The short name of the session (which can be omitted if it is **a**)
- fn File name
- ft File type
- fm File mode

D Optional changes made to the file during transfer. More than one option can be selected. Valid options are:

APPEND
ASCII
CLEAR
CRLF
NOCLEAR
PROGRESS
QUIET
TIME n

The parts of the VM/CMS RECEIVE command are:

RECEIVE The command.

d: The name of the diskette or hard disk drive on which the file is to be received.

path The path indicating the directory to which the file is to be stored.

filename.ext The name of the PC file, including the extension. Use a new name or one that already exists. If you use a new name, the file that you receive is added to your diskette or hard disk. If you use the name of an existing file, the file that you receive either replaces or supplements the existing file. (Refer to the APPEND option.)

h: The short name of the host session from which you want to get the file. The default is a:.

fn ft fm The name of the file you want to receive from your VM/CMS disk. The file name fn is required.

(options

These options can be specified:

APPEND
Specifies that the file being received is to be added to the end of an existing file. Omit this part of the VM/CMS file that is received to replace an existing file.

ASCII Specifies EBCDIC-to-ASCII character translation.

CRLF Specifies the carriage return and line feed codes. You need ASCII and CRLF for text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files, such as programs.

CLEAR
Clears the workstation window at the beginning of the file transfer.

NOCLEAR
Suppresses the sending of a Clear command at the beginning of the file transfer.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

TIME n
Specifies the length of time, in units of 30 seconds, that the program waits for a response from the host before it sends an error message. The value n is an integer value in the range from 1 through 99. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, of large block sizes, or for slow communication lines (such as SDLC and ASYNCH), 5 is recommended.

Examples

The following examples show the command syntax you can use to receive files from a VM/CMS host. The parameters of the RECEIVE command can be combined into a single set of parentheses.

To receive a file from your VM/CMS A-disk to your default drive for a PC session:

RECEIVE pc.txt a:cmsfile script a (ASCII CRLF

This command sends a **SCRIPT** file **CMSFILE** from your VM/CMS A-disk in a host session named **A** to your PC session. It adds the file to your default drive (diskette or hard disk) with the name **PC.TXT**.

To receive a file from your VM/CMS B-disk and replace a file on a drive other than your default:

RECEIVE a:pc.txt a:cmsfile script b (ASCII CRLF

This command sends a **SCRIPT** file named **CMSFILE SCRIPT** from your VM/CMS B-disk in a host session named **A** to a drive other than the default for your PC session. It replaces a file named **PC.TXT** on a diskette in drive A.

To receive a file from your VM/CMS A-disk and add it to the end of a file on your hard disk:

RECEIVE c:pc.txt a:cmsfile script a (ASCII CRLF APPEND

This command sends a **SCRIPT** file named **CMSFILE SCRIPT** from your VM/CMS A-disk in a host session named **A** to your PC session. It adds the contents of **CMSFILE** to the end of a file named **PC.TXT** on your hard disk.

To receive a file from your VM/CMS A-disk and place it in a subdirectory on your default drive:

RECEIVE \sd1\pc.txt a:cmsfile script a (ASCII CRLF

This command sends a **SCRIPT** file named **CMSFILE SCRIPT** from your VM/CMS A-disk to your default drive. It creates or replaces a file named **PC.TXT** in a subdirectory named **SD1**.

Using the MVS/TSO SEND Command

Use the following information when entering the SEND command to the MVS/TSO host:

Figure 11-3 shows the command and information you must provide. Enter it as shown (including parentheses), except that you can use either uppercase or lowercase letters.

Note: means to insert a space. There must *not* be a space between **h:** and **data-set-name**.



Figure 11-3. MVS/TSO SEND Command Syntax

A The PC drive and path of the file to send.

B The name of the PC file to send.

C The short name of the host session and the data set name of the file to send.

D The member name if the file is put in a partitioned data set.

E The password of the data set if it has one.

F Optional changes made to the file during transfer. More than one option can be specified. Valid options are:

APPEND
ASCII
BLKSIZE(n)
CLEAR
CRLF
LRECL(n)
NOCLEAR[1]
PROGRESS
QUIET
RECFM(x)
SPACE(n[,n1]) unit
TIME(n)

The parts of the MVS/TSO SEND command are:

SEND The command.

d: The name of the diskette or hard disk drive where the file is located.

[1] You must use the NOCLEAR option when you are transferring files while in ISPF command mode on the host.

path The path indicating the directory where the file is located.

filename.ext The name of the file to be sent. Include the extension if the file has one.

h: The name of the MVS/TSO host session to which you want to send the file. You can omit this name if you have only one host. If you have more than one host, this is the short name of the MVS/TSO host session. The default short name is **A**.

data-set-name The data set name that the file you send is to have on your MVS/TSO volume; this name is required. Enclose the data set name with the member name in single quotation marks if you are using a fully qualified data set name.

This option creates a new name or uses a data set name already on your TSO volume. If you use a new name, the file that you send is added to your MVS/TSO volume. If you use the name of an existing data set, the file you send either replaces or supplements the existing data set. Refer to the APPEND option.

(member-name) The member name if the file is to be put into a partitioned data set. If you use member-name, you cannot use LRECL(n), BLKSIZE(n), RECFM(x), and SPACE(n,[n1]) unit.

Note: If someone else is using the partitioned data set, you cannot send a file to your MVS/TSO host.

/password The password of the data set, if the data set has a password.

options

These options can be specified:

APPEND
Specifies that the file being sent is added to the end of an existing MVS/TSO data set. Omit this option if you want the file to replace an existing MVS/TSO data set. You cannot use LRECL(n), RECFM(x), SPACE(n[,n1]) unit, or BLKSIZE(n) options if you use the APPEND option.

ASCII Specifies ASCII-to-EBCDIC character translation.

BLKSIZE(n)
Specifies the size of the blocks of data in a new data set on your MVS/TSO volume. This part is optional. To set the block size for a new data set, replace n with the new size. If you omit this option, the block size is determined in the following manner:

If the record format is variable, the block size is 6233.

If the record format is fixed, the block size is the largest multiple of the record length that is less than 6233:

BLKSIZE = LRECL (6233/LRECL)

If you use the (member-name) or APPEND option, do not use this option.

CLEAR
Clears the workstation window at the beginning of the file transfer.

CRLF Specifies the global use of carriage return and line feed codes. You need to specify ASCII and CRLF options for sending text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files.

LRECL(n)
Specifies the record length for a new data set on your MVS/TSO volume, where n is a whole number from 1 through 32760 representing the number of characters per record. If you want to set the record length for a new data set, replace n with the new length. If you omit this option, the record length is set to 80 for fixed-length records and to 255 for variable-length records. If you use the (member-name) or APPEND options, do not use this option.

NOCLEAR
Suppresses the sending of a Clear command at the beginning of the file transfer. This option is required for ISPF command mode.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

RECFM(x)
Specifies the record format for a new data set on your MVS/TSO volume, where x = V, F, or U. For variable-, fixed- or undefined-length records in the data set, replace the x with V, F, or U, respectively.

If you omit this option, the record format of the host data set is determined by the setting of the CRLF parameter: if you specify CRLF, the data set has variable-length records; if you do not specify CRLF, it has fixed-length records. If you use the (member-name) or APPEND options, do not use this option.

SPACE(n[,n1]) unit
Specifies an amount of space to be set aside for a new data set on your MVS/TSO volume. To set aside a certain number of blocks, tracks, or cylinders for the new data set:

Provide unit as the type of space you want (AVBLOCK, TRACKS, or CYLINDERS).

Give n as the amount of space that you want the data set to occupy (in the unit of measure you select).

If the data set needs more space than you ask for with n, give n,n1 where n1 is the size of additional space to be used only when necessary.

These values are similar to the values on the ALLOCATE command of MVS/TSO.

If you omit this option, you get space for one block. The length of the block is set by the BLKSIZE(n) or LRECL(n) options. If you use the (member-name) or APPEND options, do not use this option.

TIME (n)

Specifies the length of time, in seconds, the program waits for a response from the host before it sends an error message. Replace n with an integer value in the range from 1 through 2184. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, of large block sizes, or for slow communication lines (such as SDLC or ASYNCH), 3 seconds is recommended.

Examples

The following examples show the command syntax you can use to send files from your PC to an MVS/TSO host:

To send a file from your default drive to replace a file on the MVS/TSO host:

SEND pc.txt g:ds.script ASCII CRLF

This command sends a PC file named **PC.TXT** from your default drive to your MVS/TSO host in a host session named **G**. It creates or replaces a data set named **DS.SCRIPT** on your MVS/TSO volume.

To send a file from a drive other than the default to your MVS/TSO host:

SEND a:pc.txt g:ds.script ASCII CRLF

This command sends a PC file named **PC.TXT** from a diskette in drive A to your MVS/TSO host in a host session named **G**. It replaces a data set named **DS.SCRIPT** on your MVS/TSO volume.

To send a file from your default drive to your MVS/TSO host and add it to the end of an MVS/TSO data set:

SEND a:pc.txt g:ds.script ASCII CRLF APPEND

This command sends a PC file named **PC.TXT** from a diskette in drive A to your MVS/TSO host in a host session named **G**. It adds the file to the end of a data set named **DS.SCRIPT** on your MVS/TSO volume.

To send a file to your MVS/TSO host and add it to the end of a data set that has a password:

SEND a:pc.txt g:ds.script/odyssey8 ASCII CRLF APPEND

This command sends a PC file named **PC.TXT** from a diskette in drive A to your MVS/TSO host in a host session named **G**. It adds the file to the end of a data set named **DS.SCRIPT** on your MVS/TSO volume. This data set has a password of odyssey8.

To send a file from a subdirectory on your hard disk to a partitioned data set on your MVS/TSO host:

SEND c:\sd1\pc.txt g:ds.script (m1) ASCII CRLF

This command sends a PC file named **PC.TXT** from a subdirectory named **\SD1** on your hard disk to your MVS/TSO host in a host session named **G**. It creates or replaces a member named **M1** in a partitioned data set named **DS.SCRIPT** on your MVS/TSO volume.

To send a file to a partitioned data set that has a password:

SEND a:pc.txt g:ds.script (m2)/ili11 ASCII CRLF APPEND

This command sends a PC file named **PC.TXT** from a diskette in drive A to your MVS/TSO host in a host session named **G**. It adds the file as a member

named **M2** to a partitioned data set named **DS.SCRIPT** on your MVS/TSO volume. This data set has a password of ili11.

To send a file from your default drive and add it as a new data set on your MVS/TSO volume:

```
SEND pc.txt g:ds.script/aeneid2  ASCII CRLF LRECL(132)
     BLKSIZE(132) RECFM(V) SPACE(2 ,1 ) TRACKS
```

This command sends a PC file named **PC.TXT** from your default drive to your MVS/TSO host. It adds the file as a new data set named **DS.SCRIPT** on your MVS/TSO volume. A password of aeneid2 is assigned. The records in the data set can vary in length up to 132 characters. Data blocks are the same length as the records. Twenty tracks are set aside for this data set. If more tracks are needed, they are added in groups of 10.

Using the MVS/TSO RECEIVE Command

Use the following information when receiving a file from MVS/TSO:

Figure 11-4 shows the command and information you must provide. Enter it as shown (including parentheses), except that you can use either uppercase or lowercase letters.

Note: ␣ means to insert a space. There must *not* be a space between **h:** and **data-set-name**.



Figure 11-4. MVS/TSO RECEIVE Command Syntax

A The PC drive and path to the directory where the file is to be stored.

B The name of the PC file to receive.

C The short name of the host session, and the data set name of the file you are receiving.

D The member name if the file is put in a partitioned data set.

E The password of the data set, if any.

F Optional changes made to the file during transfer. More than one option can be specified. Valid options are:

APPEND
ASCII
CRLF
PROGRESS
QUIET
TIME(n)

The parts of the MVS/TSO RECEIVE commands are:

RECEIVE — The command.

d: — The name of the diskette or hard disk drive where the file is to be located. Use **A:**, **B:**, **C:** or **D:**. This part is optional if the file is received on the current drive.

path — The subdirectory where you want the data set located. This part is optional.

filename.ext — The name the file is to have on your diskette or hard disk. Creates a new name or uses a name that is already on your diskette or hard disk.

If you use a new name, the data set that you receive is added to your diskette or hard disk. If you use the name of an existing file,

the data set that you receive either replaces or supplements the existing file. (Refer to the APPEND option on page 11-15.)

h: The short name of the MVS/TSO session where the data set is located. If you have only one host, this part is optional. Use this option if you have more than one host. The default short name is **A**.

data-set-name The name of the data set or the partitioned data set that contains the member you want to send to your PC session. You must use the qualified name. Enclose the data set name with the member name in single quotation marks if you are using a fully qualified data set name.

(member-name) The member name of a partitioned data set to send to your PC session. This part is optional. Use it only if the data set is a member of a partitioned data set.

/password The password of the data set. Use it only if the data set has a password.

options

These options can be specified:

APPEND
Adds the data set to the end of an existing file. Omit this part if you want the MVS/TSO data set to replace an existing PC file.

ASCII Specifies EBCDIC-to-ASCII character translation.

CRLF Specifies the use of carriage return and line feed codes. You need ASCII and CRLF for text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

TIME(n)
Specifies the length of time, in units of 30 seconds, the program waits for a response from the host before it sends an error message. Replace n with an integer value in the range from 1 through 99. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, of large block sizes, or for slow communication lines (such as SDLC and ASYNCH), 5 is recommended.

Examples

The following examples show the command syntax you can use to receive files from your MVS/TSO host to your PC:

To receive a data set from an MVS/TSO host to the default drive for your PC session:

RECEIVE pc.txt g:ds.script ASCII CRLF

This command sends a data set named **DS.SCRIPT** from your MVS/TSO volume in a host session named **G** to your OS/2 session. It creates or replaces the file on the default drive with the name **PC.TXT**.

To receive a data set from an MVS/TSO host to a drive other than your default drive:

RECEIVE A:pc.txt g:ds.script ASCII CRLF

This command sends a data set named **DS.SCRIPT** from your MVS/TSO volume in a host session named **G**. It replaces a file named **PC.TXT** on a diskette in drive A.

To receive a data set from an MVS/TSO host and add it to a PC file:

RECEIVE a:pc.txt g:ds.script ASCII CRLF APPEND

This command sends a data set named **DS.SCRIPT** from your MVS/TSO volume in a host session named **G**. It adds the data set to the end of a file named **PC.TXT** on the diskette in drive A.

To receive a data set from an MVS/TSO host and place it in a subdirectory on your hard disk:

RECEIVE c:\sd1\pc.txt ds.script ASCII CRLF

This command sends a data set named **DS.SCRIPT** from your MVS/TSO volume in a host session named **G**. It creates or replaces a file named **PC.TXT** in a subdirectory named **\SD1** on your hard disk.

To receive a data set that has a password from an MVS/TSO host to your default drive:

RECEIVE A:pc.txt g:ds.script/odyssey8 ASCII CRLF APPEND

This command sends a data set named **DS.SCRIPT** from your MVS/TSO volume in a host session named **G**. The data set has the password odyssey8. The data set is added to the end of a file named **PC.TXT** on the diskette in drive A.

To receive a member of a partitioned data set from an MVS/TSO host to your DOS session:

RECEIVE c:\sd1\pc.txt g:ds.script (m1) ASCII CRLF

This command sends a member named **M1** from a partitioned data set named **DS.SCRIPT** in a host session named **G**. The member is placed on your hard disk in a subdirectory named **\SD1**. It replaces or creates a file named **PC.TXT**.

To receive a member of a partitioned data set that has a password to your OS/2 session:

RECEIVE a:pc.txt g:ds.script (m2)/ili1 ASCII CRLF APPEND

This command sends a member named **M2** from a partitioned data set named **DS.SCRIPT** in a host session named **G**. The data set has a password of ili1. The member is added to a file named **PC.TXT** on the diskette in drive A.

Using the CICS SEND Command

Use the following information when sending a file to CICS:

Figure 11-5 shows the command and information you must provide. Enter it as shown (including parentheses), except that you can use either uppercase or lowercase letters.

Note: means to insert a space. There must *not* be a space between **h:** and **fn**.



Figure 11-5. CICS SEND Command Syntax

A The PC drive and path of the file to send.

B The name of the PC file to send.

C The short name of the host session, and the host file name of the file to send.

D Optional changes made to the file during transfer. More than one option can be specified. Valid options are:

ASCII
BINARY
CLEAR
CRLF
NOCLEAR
NOCRLF
PROGRESS
QUIET
TIME n

The parts of the CICS SEND command are:

SEND — The command.

d: — The name of the diskette or hard disk drive where the file is located.

path — The path to the subdirectory that the file is in.

filename.ext — The name of the file to be sent, including the extension.

h: — The short name of the host session where you want to send the file. If you have only one host, this part is optional. The default is session **A**.

fn — The name the file is to have on your CICS disk. You must specify the file name. You can create a new name or use a name that is already on the disk.

(options — These options can be specified:

ASCII Specifies ASCII-to-EBCDIC character translation. The default is ASCII CRLF. You need these control terms for text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files.

Notes:

1. CRLF and NOCRLF are mutually exclusive options.
2. BINARY and ASCII are mutually exclusive options.
3. The assumed defaults, if the optional parameters are omitted, are CRLF ASCII.

BINARY
Specifies that the data in the file is binary data. The data can be encrypted, compiled programs, or other data. It is not translated by the host file transfer program but copied unaltered into a temporary storage queue.

CLEAR
Clears the workstation window at the beginning of the file transfer.

CRLF Specifies carriage return and line feed codes in the text file.

NOCLEAR
Suppresses the sending of a Clear command at the beginning of file transfer. This option is required for ISPF command mode.

NOCRLF
Specifies that the PC file does not consist of logical records delimited by carriage return and line feed characters. No concatenation or splitting of records is performed by the CICS file transfer program.

The file is written into a temporary storage using one item on the queue to represent each inbound data buffer. The items on the CICS temporary storage queue can be of different lengths, but none can be more than 32767 characters.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

TIME n
Specifies the length of time, in units of 30 seconds, the program waits for a response from the host before it sends an error message. Replace n with an integer value in the range from 1 through 2184. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, large block sizes, or for slow communication lines (such as SDLC and ASYNCH), 3 seconds is recommended. A blank space is required between TIME and n.

Examples

The following examples show the command syntax you can use to send files from your PC to your CICS host:

To send a PC file from your default drive and add it as a new file on your CICS host:

SEND pc.txt a:cicsfile (ASCII CRLF)

Note: Enter the complete CICS SEND command on one line.

This command sends a PC file named **PC.TXT** from your default drive on your PC to your host session **A**. You do not need to provide the PC drive name if the file you are sending is on the current drive. The command creates a new file named **CICSFILE**.

To send a basic PC file from a drive other than your default to replace a file on your CICS host:

SEND a:myprog.exe a:basprog

This command sends a PC file named **MYPROG.EXE** from a diskette in drive A to your CICS host in your host session named **A**. It is written to a file named **BASPROG**, replacing any existing file by that name in host session **A**.

Using the CICS RECEIVE Command

Use the following information when receiving files from CICS:

Figure 11-6 shows the command and information you must provide. Enter it as shown (including parentheses), except that you can use either uppercase or lowercase.

Note: means to insert a space. There must *not* be a space between **h:** and **fn**.



Figure 11-6. CICS RECEIVE Command Syntax

A The PC drive and path where the file is to be received.

B The name of the PC file.

C The short name of the host session (h:) from which you are receiving the file, and the host file name (fn).

D Optional changes made to the file during transfer. More than one option can be specified. Valid options are:

ASCII
BINARY
CLEAR
CRLF
NOCLEAR
NOCRLF
PROGRESS
QUIET
TIME n

The parts of the CICS RECEIVE command are:

RECEIVE The command.

d: The name of the diskette or hard disk drive where the file is to be received.

path The path to the subdirectory where the file is to be located.

filename.ext The name of the PC file, including the extension. You can create a new name or use a name that is already on your PC diskette or hard disk. If you use a new name, the file that you receive is added to your diskette or hard disk. If you use the name of an existing file, the file that you receive either replaces or supplements the existing file. Refer to the APPEND option.

h: The short name of the CICS session where the data set is located. If you have only one host, this part is optional. The default session is **A**.

fn The name of the file you want to receive from your CICS host.

(options

These options can be specified:

ASCII Specifies EBCDIC-to-ASCII character translation. The default is ASCII CRLF. You need ASCII and CRLF control terms for text or source files that you want to view or edit, such as SCRIPT files. You do not need them for binary files.

Notes:

1. CRLF and NOCRLF are mutually exclusive options.
2. BINARY and ASCII are mutually exclusive options.
3. The assumed defaults, if the optional parameters are omitted, are CRLF ASCII.

BINARY
The data in the file is binary data. The data can be encrypted data, compiled programs, or other data. It is not translated by the host file transfer program but is copied without changes into the PC file.

CLEAR
Clears the workstation window at the beginning of the file transfer.

CRLF Specifies the use of the carriage return and line feed codes.

NOCLEAR
Suppresses the sending of a Clear command at the beginning of file transfer. This option is required for ISPF command mode.

NOCRLF
Specifies that the host computer file does not consist of logical records. The items in the temporary storage queue are sent in order and concatenated in your PC into a single string of data.

PROGRESS
Shows a message indicating that the file transfer is in progress or has ended. Such messages do not show the current transferred bytes.

QUIET Does not show any messages.

TIME n

Specifies the length of time, in units of 30 seconds, the program waits for a response from the host before it sends an error message. Replace n with an integer value in the range from 1 through 2184. The default is 1. To avoid a premature error message, specify an adequate value. In cases of large packet sizes, of large block sizes, or for slow communication lines (such as SDLC and ASYNCH), 3 seconds is recommended. A blank space is required between TIME and n.

Examples

The following examples show the command syntax you can use to receive files from your CICS host to your PC:

To receive a file from your CICS host to your default drive for a PC session:

RECEIVE pc.txt A:cicsfile (ASCII CRLF)

This command sends a file named **CICSFILE** from your CICS host in session **A** to your PC session. It adds the file to your default drive (diskette or hard disk) with the name **PC.TXT**.

To receive a basic file from your CICS host and replace a file on a drive other than your default:

RECEIVE a:myprog.exe a:myprog

This command sends a file named **MYPROG** from your CICS host in session **A** to a drive other than the default for your PC session. It replaces a file named **MYPROG.EXE** on a diskette in drive A.

Configuring File-Transfer Code Translation

When you transfer a file between the host and the PC using the ASCII option, the host-system file-transfer program performs translation from EBCDIC to ASCII or vice versa, according to the host and PC code pages specified during PC/3270 configuration. However, you might want to use different translation from that supplied by IBM. For the details, refer to Chapter 5, “Transferring Files” on page 5-1.

Chapter 12. Considerations for Installation and Use of PC/3270 Sessions

Additional information on Personal Communications installation and use is available in the README found on the Personal Communications Windows Mode - Diskette 1 (installation), or by double-clicking the **Readme - Please!** icon to view the **README.TXT** file after the installation.

The information in the README file supplements and supersedes information found in the Personal Communications publications.

Host-Session Window Operations

Cursor Color

PC/3270 assigns white to the cursor color as the product default, and mixes the background color (if it exists) with an exclusively-ORed operation. If you want to change this default cursor color assignment, you need to modify the PCSWIN.INI file and insert the following line into the [Session] section:

```
[Session]
 CursorColor=<red-value> <green-value> <blue-value>
```

Where <red-value>, <green-value>, and <blue-value> are integers from 0 to 255 that specify the color intensity for each color primitive respectively; 0 0 0 for black, and 255 255 255 for white.

Releasing Insert Mode with the Attention Key

As in a non-programmable terminal, if you want to be able to release insert mode with the attention key, add this parameter to the [Keyboard] section of the workstation profile (.WS):

```
[Keyboard]
ResetInsertByAttn=Y                <- Added.
```

Scroll Bar

When you select **Font** from the **Appearance** menu in the host session window and select **Fixed Size** from the Select Display Font window, if you specify **With Scroll-Bar** in the Window Setup window, the entire operator information area might not appear on the screen. The session window size is restricted to be smaller than the screen size.

© Copyright IBM Corp. 1989, 1996

Scroll-Lock Key

When the Scroll Lock keyboard indicator (lap) is turned on, the cursor movement keys, and Page Up and Page Down keys are used to scroll windows only when you specify **With Scroll-Bar** in the Window Setup window. If you specify **Without Scroll-Bar**, you cannot use the Scroll Lock key, because the entire screen is displayed. For example, cursor-movement keys in Scroll Lock mode do nothing.

3270-Session Screen-Size Control

Although you can specify the screen size of the 3270 session in PC/3270 configuration, the final screen size is determined by the host according to the SNA BIND negotiation.

Sometimes, you want to use your configured screen size when it is difficult to ask the host VTAM table to change. The following method will satisfy your requirement; however, because it violates SNA architecture rules, some applications that refer to the VTAM table only might not work.

Modify your workstation profile (.WS) to insert the following line into the [LU] section:

```
[LU]
InfScreenSize=Y
```

Personal Communications processes byte 24 of the host BIND image correctly and according to the SNA architecture. Byte 24 is the last 2 bytes of

PSERVIC=X' 28 3 ' (3 in this case)

in the log mode.

If byte 24 is X'03', the default screen size is 24 x 80 and the alternate is what you configured with PC/3270.

If byte 24 is X'00' or X'02', the default and alternate screen sizes are 24 x 80.

If byte 24 is X'7E' or X'7F', bytes 20–23 in the BIND control the default and alternate screen sizes.

If you have X'03' in the BIND image, you can customize whatever screen size you want. The host will query Personal Communications and use the alternate screen size.

The following table shows the details of the BIND image processing:

	Byte in BIND by Host ==>					Result(Screen size)	
	24	2	21	22	23	Default	Alternate
	==	==	==	==	==	=======	=========
a)	--	--	--	--	==>	24 x 8	24 x 8
b)	2	--	--	--	-- ==>	24 x 8	24 x 8
c)	3	--	--	--	-- ==>	24 x 8	R x C
d)	7E	Rd	Cd	--	-- ==>	Rd x Cd	Rd x Cd
e)	7F	Rd	Cd	Ra	Ca ==>	Rd x Cd	Ra x Ca

Legend: RxC: Screen Size defined by PC/327 3. configuration
(R,C) = (24,8) , (32,8) , (43,8) or (27,132)

Rd: Rows in the default screen size mode
Cd: Columns in the default screen size mode
(Rd,Cd) = (24,8) , (32,8) , (43,8) or (27,132)
Rd Cd <= R C

Ra: Rows in the alternate screen size mode
Ca: Columns in the alternate screen size mode
(Ra,Ca) = (24,8) , (32,8) , (43,8) or (27,132)
Ra Ca <= R C

PC/3270 supports Query Replies. Make sure that the Query Reply of Implicit Partition returns the final screen size upon receipt of the BIND command.

Customizing a Display Translation Table

PC/3270 displays the host EBCDIC character using the PC (ANSI) graphic symbol so that the character defined by the S/390 EBCDIC host code page is displayed correctly using the same graphic symbol defined by ANSI. However, you might need your original translation, because your host or workstation application is not designed to use the standard translation.

You can use your original translation table if you refer to the following procedure as an example. Note that the data integrity caused by the user-defined table is your responsibility.

The following procedure is an example of how to remap left and right brackets.

1. Terminate all running 3270 sessions
2. Modify the PC/3270 workstation profile (.WS).

   [Translation]
   IBMDefaultView=N
   DefaultView=C:\PCOMWIN\PRIVATE\BRACKET.XLT
3. Create the display translation table file (**.XLT**). For this example, the following **C:\PCOMWIN\PRIVATE\BRACKET.XLT** file is created.

```
[Profile]
id=XLT
Description=User-defined Display Translation Table

[Option]
Replace=Y

[SB Xlate]
; EBCDIC=ANSI
; The next line displays EBCDIC X'AD' as
; an ANSI X'5B' (left bracket)
AD=5B
; The next line displays EBCDIC X'BD' as
; an ANSI X'5D' (right bracket)
BD=5D
```

4. Create your own keyboard layout (.KMP) if you need to enter your new left and right brackets graphic symbols:

   ```
   [KEYBOARD]
   KEY27=ansi dd
   KEY28=ansi a8
   ```

   The information on the right should be lowercase characters. PC/3270 translates ANSI X'dd' into EBCDIC X'ad'. It is displayed as [by the table created in step 3, and so on.

5. Click on the PC/3270 icon corresponding to the modified workstation profile.

Edit Function

Edit-Function Restrictions with CUT Attachment

When you use the CUT attachment, you can use only the Copy and CopyAppend edit functions in the host-session window.

Edit-Function Restrictions with Home3270 Attachment

When you use the Home3270 attachment, the following edit functions are restricted:

Undo function

You cannot execute the Undo function after using the CUT, Paste, PasteNext, or Clear functions because these functions modify display areas in the protocol converter.

Cut and Clear functions

When an area to be cut or cleared contains a field attribute character or protected field, or each line in that area ends at the end of an unprotected field, the following things might happen:

Characters in an unprotected field outside the area to be cut or cleared might also be cleared.

An alarm might sound.

The cursor might not appear at the initial position.

When you execute the Cut or Clear function, specify only the minimum area required (for example, some words or one field in one line), then confirm that the frame exists in an unprotected field.

Paste and PasteNext functions

When the area to be pasted contains a field attribute character or protected field, or the end of the paste area on each line is at the end of an unprotected field, the following things might occur:

The character to be pasted might not be written to the expected position.

An alarm might sound.

The cursor might not appear at the initial position.

When you use the paste function, paste the shortest character string possible (for example, a character string, but excluding CR/LF). Confirm that the area to be pasted is in an unprotected field.

File Transfer Function in a DOS Box

Host File Name and Reserved Words

You should not use the following words as a VM file name or file type, as a MVS data set name, or as a CICS file name, because they are reserved for use as option commands:

ASCII
APPEND
TIME
CLEAR
NOCLEAR
SILENT
QUIET
PROGRESS
JISCII
SO
NOSO
BLANK
USER

However, if it is essential for you to use them for files, you must add a \ (backslash), as a separate word, immediately after the file name and so on, even if you do not specify any options.

Changing the Packet Size When Import/Export Is Idle

When import/export is idle, select **Setup** from the Transfer menu. When you change the packet size on the Miscellaneous Settings window, end import/export, and then rerun it.

WAIT Option for Multiple File Transfer

If multiple file transfers do not succeed, insert the following statement into the [Transfer] section of your .WS file:

```
[Transfer]
WAIT=1
```

This parameter causes a 1000 msec (1 sec) delay between file transfers. If this does not help, you might need to increase the value again.

NOTRUNC and BLANK Options for Host File Transfer Program

If you want to add trailing blanks (spaces) to fill the logical record length for each record when downloading a text file, use the following options in the **Additional Options** edit field of the Transfer-Type Definition window.

NOTRUNC : for VM/CMS (PTF# UR35492)
NOTRUNC : for MVS/TSO (PTF# UR34797)
BLANK : for CICS

Graphic Functions

Graphic Protocol

PC/3270 allows you to use host-graphics applications such as GDDM and others. Two protocols are supported: ***advanced*** and ***native***.

Advanced Protocol

Select the advanced protocol when you have GDDM Version 2 Release 3 or higher and are using any of the following operating system:

MVS
VSE
VM/SP
VM/XA SP

Note that the advanced protocol is not supported by the CICS pseudo-conversational mode with versions of GDDM earlier than Version 3. It is not supported by IMS/VS. It is supported by the CICS pseudo-conversational mode with GDDM Version 3 Release 1 or later.

The advanced protocol mode is equivalent to that used by OS/2 Link and by PC/3270 Version 3.0 and 3.1, so it supports the same subsystems. However, no download of code from the host system is required for PC/3270, because all the OS/2 Link graphics modules are integrated into the program.

Native Protocol

Select the native protocol when you intend to use any GDDM versions or non-GDDM host graphics applications, such as those originally intended to use 3270 nonprogrammable terminals such as the 3179G, 3192G, or 3472G.

The native protocol also allows IMS/VS users to display the GDDM graphics.

Note: A 3174 controller requires a terminal to respond within a certain period; if it does not, Machine Check 207 message appears. If you are using a coaxial-cable attachment for graphics in Native mode, this might happen for various reasons such as the complexity of the graphics drawing orders or the speed of your workstation. In this case, change to advanced mode.

Enabling Programmed Symbol Sets

PC/3270 provides up to six sets of triple-plane programmed symbols, depending on the type of graphics support that you choose.

If you select both programmed symbols and vector graphics, two sets of single-plane programmed symbols (PSA and PSB) are usable.

If you select programmed symbols, but not vector graphics, three sets of single-plane programmed symbols (PSA, PSB, and PSE) and three sets of triple-plane programmed symbols (PSC, PSD, and PSF) are usable.

Handling Errors Caused by Insufficient Memory

Graphic execution module PCSGRP.DLL uses a large amount of global memory for graphic drawing or printing. When the workstation has insufficient installed memory, results might not be correct. For example, an area might not be clearly shaded.

In this case, increase the amount of installed workstation memory by at least 1 MB. For host graphic printing, add another 1 MB. Memory might have to be further extended depending on the host graphic application and printer driver used.

Drawing Buffer Size

The drawing buffer size varies depending on the contents set for Redraw of a graphic function.

To set **Redraw**, select **Display Setup** from the Appearance menu in the session window. On the continuously displayed Display Setup window, select **Graphic** from **Category**.

Selecting **Host** from the optional items of **Redraw** requires no buffer.

If you select **Retained**, the graphic execution module stores all redrawing data into a buffer. Such a buffer is called a *retained buffer*. The buffer size varies depending on the complexity of the graphic data from an application program.

Example:

Simple table ... 10K to 20K bytes
Complicated graphic image... 200K to 300K bytes

When you select **Bitmap** to set **Redraw**, the buffer size will be the same as the sum of the retained buffer size and compatible bit map size. For example:

(Height) x (Width) x (Number of planes) x (Bits/Pixel) / 8 bytes

Example:
When you select a 7x12 font for a VGA 16-Color Display Model 2 (24x80), the bitmap size is:
Bitmap size = (7x80) x (12x24) x 1 x 4 / 8 = 80 KB

When you select a 12x20 font for an IBM PS/55 High-Resolution 256-Color Display Model 2, the bitmap size is as follows:
Bitmap size = (12x80) x (20x24) x 1 x 8 / 8 = 460 KB

Using Bitmaps for Drawing

The graphic execution module uses a bit map compatible with the display unit to draw an area instruction in overpaint mode. An image instruction requires one plane bit map.

(Buffer for area) = (Area width) x (Area height) x (Number of planes) x (Bits/Pixel) / 8

(Image buffer) = (Image width) x (Image height) / 8

Print Buffer Size

The retained buffer must be used for printing. The retained buffer is the same size as that used for redrawing. This is also applied when you specified **Bit Map** for **Redraw** on the Display Setup window.

If graphic printing is called in Bitmap mode, the graphic printing module generates a bitmap compatible with the connected printer, draws an image on the bitmap, and transfers the bit image to the printer.

This operation is generally performed quickly. When memory is frequently swapped, the process slows down in proportion to the number of swap operations. If a large bit map is not allocated, the graphic printing module prints a graphic image normally using only the retained buffer.

Example: Proprinter (240x144 DPI) character size:
Bitmap size = (240x8) x (144x11) x 1 x 1 / 8 = 380 KB

Example: EPSON (ESC/P) (360x180 DPI color) character size:
Bitmap size = (360x8.5) x (180x11) x 3 x 1 / 8 = 2.3 MB

Note: With some printers, different printing results might be obtained in bitmap mode and non-bitmap mode. If the desired results are not obtained, change the current bitmap mode. For example, specify non-bitmap mode to print in bitmap mode.

Edit-Copy Buffer

An editing operation causes the graphic execution module to copy a bit map and DIBitmap to the clipboard. The bit map is compatible with the display; DIBitmap is a 4-bit/pixel bit map.

Printer Fonts

The printer driver can handle two font sets, the device font and GDI font. The device font is a Mincho 6cpi hardware font built into the printer. The GDI fonts are System (without brackets) or other software fonts for Windows.

When you select a font set for graphic printing from the Printer Control window, use the GDI fonts for the following reasons:

In bitmap mode, a GDI font can be used for printing. However, the device font cannot be used, because an image cannot be drawn on a memory bit map when using the device font.

In bitmap mode, the device font cannot be used for printing when OR and exclusive OR attributes are mixed.

Plotter

Because a plotter does not support a raster, the following restrictions are imposed on drawing. Use a plotter for figures and tables that have mainly lines.

No shading is supported.

Some shading patterns cannot be distinguished.

Image order drawing requires much time, and the final printout is of poor quality.

The OR and exclusive OR are not correctly reflected.

Hole in Screen Caused by Clearing a Graphic Character

When a character overlaps a graphic image, the graphic image is cleared at the position where the character is to be displayed. When you enter a null character or space having the transparent attribute at the position where a graphic image is displayed, the graphic image in that character cell is not cleared.

If you select **Host** or **Retained** to set **Redraw** on the Display Setup window, when characters in a graphic image are cleared, a hole appears in the graphic area. This is because these two modes do not have a bitmap image, and partial redrawing cannot be performed on the screen.

If you select **Bitmap** mode as **Redraw Graphics**, you can find no hole on the graphic region by the application that overrides any alphanumeric characters (as well as NULL and SPACE) on the graphic image.

To restore the screen, perform either of the following actions:

Press the PA3 key to have the application program redraw the screen.

Minimize and restore the graphic image retained in Retained mode, then redraw it or select Bitmap mode.

Note: When you change the setting of **Redraw** in the Display Setup window, the set contents are valid from the next drawing.

Miscellaneous Restrictions for Graphic Functions

If advanced protocol is selected, graphic functions cannot be used in the IMS/VS and CICS pseudo-conversational mode with versions of GDDM earlier than Version 3.

Print Processing

Using a Printer in Non-SNA Coax Attachment

For the non-SNA coaxial-cable attachment, PC/3270 regards any print job within 30 seconds after the previous one as a continuous job with the previous one. For non-SNA attached, PC/3270 determines the job end artificially by the timeout value.

You can change the standard timeout value for your environment. Specify the following parameter in the [CNDFT] section of the workstation profile (.WS):

[CNDFT]
PrtTimeOut=nn

Note: The variable nn is the decimal value of the timeout in seconds.

Print Job Control Using SNA Timeout

PC/3270 treats the data packet, which begins with an SNA Begin Bracket (BB) and ends with an SNA End Bracket (EB), as one job, and spools to the Windows print manager. However, some applications might not use SNA BB and EB appropriately, and an unexpected page eject by the Windows print manager can occur. This section describes two timeout controls for you to customize your host print job to fit your environment.

Concatenation of Multiple Print Jobs to One Print Job

When a new print job comes from the host before the timer specified by the workstation profile expires, the print job is concatenated to the previous one, and they are regarded as one print job. You can change the timer value by specifying the following parameter in the [printers] section of the workstation profile (.WS):

[printers]
ConcatinateTime=nn

Note: The variable nn is as follows, and its unit is a second:

0	No concatenation of print jobs
1 – 32767:	Concatenation of print jobs by this timeout value

When the non-SNA attachment is used, the timer should not be specified on the workstation profile.

Termination of a Print Job: When an end of a print job (SNA End of Bracket) does not come from the host until the timer specified by the workstation profile is expired, the print job is automatically terminated. You can change the timer value by specifying the following parameter in the [printers] section of the workstation profile (.WS):

[printers]
TerminateTime=nn

Note: The variable nn is as follows, and its unit is a second:

0	No automatic termination of a print job
1 – 32767	Automatic termination of a print job by this timeout value

When the non-SNA attachment is used, the timer should not be specified on the workstation profile.

SCS TRN Command (LU 1)

Change the operation of the SCS TRN command by adding this specification to the [printers] section of the workstation profile (.WS):

ATRN=Y Transfers data of the SCS TRN command to the printer driver without conversion. In the cases below, however, this parameter is assumed to be ATRN=N.

The printer driver does not support PASSTHRU.

The printer driver supports the BANDING function.

BANDING=Y is specified in the [printers] section of the workstation profile (.WS).

When you use a printer driver for which the PASSTHRU function is incomplete, sense code X'1003' is returned to the host system for the SCS TRN command.

ATRN=N Converts data of the SCS TRN command and transfers the result to the printer device driver. You can then specify the following parameters in the [printers] section of the workstation profile (.WS).

3270TRN=Y Converts host codes 40H to FFH to workstation codes.

3270TRH=N Does not convert host codes 40H to FFH.

When either ATRN=Y or ATRN=N is specified, host codes 00H – 3FH are converted to hyphens or characters specified with the SCS SGEA command. The default value is:

ATRN=Y
327 TRN=N

Note: The SCS TRN command (LU 1) is available in PD mode only.

SCS SPD/SLD Command (LU 1)

When the selected font cannot be applied to CPI/LPI, this command temporarily switches it to a valid font.

Note: The SCS SPD/SLD command (LU 1) is available in PD mode only.

Ignoring Blank Pages

When you cannot print a blank page correctly, check for the following things:

Some printers ignore a blank page if so specified with the **Printer Setup** option (or setting the printers DIP switches). Check whether the printer is set to enable this option.

Some printer drivers ignore a blank page if so set with the **Printer Driver Setup** option. Check whether this option is supported by the printer driver.

Printing APL

When the fixed-pitch GDI font cannot be used with the specified printer driver, no APL characters are printed.

Printing with GDI Font
Some printer drivers do not support the fixed-pitch GDI font.

Printing Reverse-Display Character with GDI Font
Some printer drivers that do not support the reverse-display character printing function print reverse-display characters as spaces. To avoid this, add the **REVERSE=N** line to the [printers] section of the workstation profile (.WS).

CPI/LPI of Device Font
When the printer driver cannot print the device font for the specified CPI/LPI, data can be printed by another CPI/LPI.

Printing Reverse-Display Characters with Device Font
Most printer drivers do not support reverse-display character printing with the device font.

Simultaneous Printing Request
Because some printer drivers cannot correctly process a request for two or more print operations, an irrecoverable application error can occur in the print execution module.

PCSERR999 Error Messages
Message PCSERR999 - This is an internal error of the personal communications might appear when there is insufficient memory. Because the print job otherwise remains in the print manager, delete the print job.

Printable Area
Characters might not be printed over the entire paper depending on the printer driver used. When using a printer driver that allows you to set the margins, specify the minimum margins to maximize the printable area.

SVF Control Code
If the maximum print line (MPL) is shorter than the paper size in the SVF control code, a page feed is performed when the printing position reaches MPL.

Note: The SVF control code is available in PD mode only.

Notes on Using a Printer Session
When you print without using the Windows print manager and the printer is temporarily disabled (for example, the printer has no paper or the power is not turned on), a message appears on the Windows screen. The host system is not notified.

If you select **Cancel** on the window, the PC/3270 sends the **Cancel Printing** command to the host system, and printing is canceled.

PDT Mode
Printing using the PDT file is restricted as follows:

A graphic image is printed through the Windows printer driver specified in "Printer Setup", regardless of the PDT mode.

No APL character can be printed.

The Postscript printer is not supported.

Using ZipPrint

Keep the following considerations and restrictions in mind when using ZipPrint:

ZipPrint uses the Personal Communications File-Transfer function to print VM/CMS notes and files. On slower communication lines such as SDLC, Async (IIN), or Home3270 attachment, or when using a large packet or block size, you might experience a file-transfer timeout. If this happens, you should increase the *timeout delay* as follows:

1. Select **Transfer** from the menu bar of the session window.
2. Select **Setup - Miscellaneous Setting**.
3. Increase the timeout value to 150.

ZipPrint will not work with CUT-mode sessions because CUT mode does not support the DDE/HLLAPI interfaces.

When you hide the **ZipPrint** icon, be aware that ZipPrint is running in the background session while you exit all Personal Communications sessions. If you want to close ZipPrint and all sessions, select **Quick Exit** through the ZipPrint menu bar.

Considerations and restrictions on use of the PC/3270 and supplementary information other than the items described in this appendix are stored on the installation diskette as a file. To access this information, refer to **README.TXT** is saved in the directory the PC/3270 is installed. Also you can double-click the **Readme - Please!** icon or **How to Configure Session** icon displayed in the Personal Communications Program Group.

Considerations for PC/3270 Sessions

Personal Communications AS/400

© Copyright IBM Corp. 1989, 1996

Chapter 13. Using Virtual Printers

The virtual printer function lets you use a printer attached to an AS/400 as though it were directly connected to your workstation.

You can send print data to an AS/400 system by the following printer data types:

SNA Character String (SCS) data
PC code to SCS
PC code

If you have OS/400 Version 3, Release 1 or later, you can also use the following AS/400 resources:

Printer device
Spooled file

Note: You can operate these resources only if a specified local port (LPT) is connected with the Network Print Server transaction program, which is available with OS/400 V3R1 or later versions. If the Virtual Printers program (PCSVPRT.EXE) fails to connect with the Network Print Server transaction program, it tries to connect with the Virtual Printer transaction program, which is supported by the following versions of OS/400:

Version 3 Release 1 or later versions (available on all)
For the earlier versions V2R2, V2R3, or V3R0.5 (available on an AS/400 system with Client Access/400 or PC Support/400 installed)

The following printer operations are not available for an LPT connected through the Virtual Printer transaction program:

Start Printer...
End Printer...
Output Queue...
Network Print Server...

Starting Virtual Printers

To use the virtual printer function, complete these steps:

1. Click on the AS/400 Utilities icon in the Personal Communications folder.

   The AS/400 Utilities window appears.

2. Click on the Virtual Printer start **( )** button.

© Copyright IBM Corp. 1989, 1996

Chapter 14. Building a Printer Definition Table (PDT) for PC400

This chapter explains how to create and change the printer definition table (PDT file) used for PC400. The PDT file is created by converting the printer definition file (PDF file). The file defines how characters and control codes are sent to the printer and how printer output is formatted. You can create this file by using a text editor that produces an ASCII file or by modifying one of the printer definition tables provided by PC400.

Creating and Changing the Printer Definition Table (PDT File)

To use the PDT file:

1. Select **File** from the menu bar of the workstation window.
2. Select **Printer Setup** from the File menu.

   The Printer Setup window appears.
3. Select the **Use PDT file** check box and **Select PDT**.

   The Select PDT file window appears.



4. Select **Convert PDF**. Select the PDF file to be converted from the list in the Convert PDF to PDT window; then select **Convert**. After the file has been converted, control is returned to the Select PDT file window, and the converted PDT file is listed. Select the PDT file; then select **OK**.
5. Select **OK** on the Printer Setup window.

   After printer setup is complete, the Printer Setup window is closed.

Printer Definition File (PDF File) Format

A printer definition file consists of a macro definitions section and a definitions section. In the macro definitions section, you can equate a sequence of hexadecimal and decimal numbers and ASCII characters with the name used in place of the sequence in the definitions sections. In the definitions section, the left side of each statement contains the name of a character or control command. You enter a string of hexadecimal or decimal numbers, ASCII characters, or predefined macro names on the right side of each statement, which defines the character or the command sent to a printer.

© Copyright IBM Corp. 1989, 1996

Different printer manuals define printer control strings in different ways. Some printer manuals describe control sequences in hexadecimal, while others use symbols such as esc J1 K. You can use either format and define macros to make the file more readable. In the definitions section of a printer definition file, the following items can be specified to the right of each statement:

A single character is treated as an ASCII value.
Two digits are treated as a hexadecimal number.
Three or more digits are treated as a decimal number.
A predefined macro is expanded by the printer table compiler.

If you leave the right side of a statement blank or if you delete it, the character or the control code is interpreted as a null string. If a character or a control code is defined more than once in a file, the last definition is used. If an error is detected in a statement, the printer table compiler ignores the statement and proceeds to the next statement.

After a printer definition file has been created, convert it to a PDT file using the printer table compiler. A file having the **.PDT** extension can be created.

The / symbol indicates the beginning of a comment. The / symbol indicates the end of a comment. A comment can be placed anywhere within a printer definition file. It is ignored by the printer table compiler.

A macro definition cannot contain another macro definition.

Example of Printer Definition Files

The PC400 distribution diskette contains the following PDF files:

ACTLZR2.PDF
BJ300.PDF
CPQPM20.PDF
EAP2250.PDF
EAP3250.PDF
EAP5500.PDF
EFX1170.PDF
EFX5000.PDF
EFX850.PDF
ELQ1070.PDF
ELQ2550.PDF
ELQ510.PDF
ELQ860.PDF
ELX810.PDF
EPLPCL4.PDF
EPLPCL5.PDF
ESQ1170.PDF
HPDJ550C.PDF
HPDSKJT.PDF
HPLJII.PDF
HPLJIII.PDF
HPLJIIID.PDF
HPLJ4.PDF
IBM3812.PDF
IBM3816.PDF
IBM38521.PDF

IBM38522.PDF
IBM4019.PDF
IBM4070.PDF
IBM4070E.PDF
IBM4072.PDF
IBM4201.PDF
IBM4202.PDF
IBM4207.PDF
IBM4208.PDF
IBM4212.PDF
IBM4226.PDF
IBM5152.PDF
IBM5182.PDF
IBM5201.PDF
IBM5202.PDF
IBM5216.PDF
IBM5223.PDF
LBP4.PDF
LQ870.PDF
NEC6300.PDF
PANLBP4.PDF
PANLBP5.PDF
PAN1123.PDF
PAN1124.PDF
PAN1180.PDF
PAN1695.PDF
PAN2123.PDF
PAN2124.PDF
PAN2180.PDF
PAN2624.PDF

The PDF files contained in the PC400 installation diskette can be used as is. However, it might be advantageous to change the definitions of some fields. To do so, copy an existing PDF file, modify it, and then convert it to a new PDT file.

The contents of each PDT file are shown below. Do not attempt to change the statements in a field for which modification is specifically prohibited. If a PDT file created according to a changed PDF file is used, the results of printing cannot be guaranteed.

IBM4019.PDF File Contents

```
/                                                                  /
/                                                                                  /
/       PRINTER SESSION DEFINITION FILE FOR: LaserPrinter 4 19/4 19-E      /
/                                                                                  /
/                                                                  /
/                                                                  /
/                                  Macro  Definitions                                  /
/ Define values here that will be used commonly throughout your          /
/ definitions.    Then use the left hand side of the equate as you         /
/ define your characters and control strings.    The printer compiler    /
/ will substitute the right hand side of the equate for each              /
/ occurrence of the left hand side throughout the file.                   /
/                                                                                  /
/ Macro names must be at least three characters long and may not         /
/ begin with a number.                                                          /
/                                                                                  /
/ Format                                                                         /
/ A Macro Name is associated with a value or string of values by the  /
/ EQU statement.    The right hand side of an EQU statement must be a     /
/ string of zero or more two digit hexadecimal numbers.    If a macro     /
/ definition is more than one line long, you may extend it to the        /
/ next line by ending the first line with a comma.    In this manner      /
/ you may define a macro which is many lines long by terminating each /
/ line except the last with a comma.    No macro names are allowed on     /
/ right hand side.                                                              /
/                                                                  /
BEGIN_MACROS
/ The following values are standard for most printers.    Check your      /
/ printer manual to verify that these are correct for your printer       /
NUL EQU                    / Nul character                        /
BEL EQU  7                 / Beeper                                 /
BAK EQU  8                 / Back Space                             /
TAB EQU  9                 / Tab                                    /
LFF EQU  A                 / Line Feed                             /
VTB EQU  B                 / Vertical Tab                          /
FFF EQU  C                 / Form Feed                              /
CRR EQU  D                 / Carriage Return                       /
P 5 EQU 1B 57  1           / 5 Pitch-Characters/inch         /
                           / Same as Double Wide                /
SEL EQU 11                 / Select Printer                       /
P1  EQU 12                 / 1  Pitch-Characters/inch        /
CDW EQU 1B 57              / Cancel Double Wide contin.     /
CDL EQU 14                 / Cancel Double Wide line         /
ESC EQU 1B                 / Escape                                 /
CAN EQU 18                 / Cancel Data                            /
SPA EQU 2                  / Space                                  /
P17 EQU 12  F              / 17.1 Pitch-Characters/inch     /
CS2 EQU 1B 36              / Select Character Set 2          /
CS1 EQU 1B 37              / Select Character Set 1          /
P12 EQU 1B 3A              / 12 Pitch-characters/inch        /
SVT EQU 1B 42              / Set Vertical Tabs                 /
SFL EQU 1B 43              / Set Form Length                    /
SHT EQU 1B 44              / Set Horizontal Tabs               /
SDS EQU 1B 47              / Start Double Strike               /
CDS EQU 1B 48              / Cancel Double Strike              /
SSP EQU 1B 4E              / Set skip perforation              /
CSP EQU 1B 4F              / Cancel skip perforation          /
CAT EQU 1B 52              / Cancel all tabs Clears VT       /
                           / and sets HT every 8 position /
CSS EQU 1B 54              / Cancel Subscript or Superscr /
SSO EQU 1B 53              / Set Superscript over             /
SSU EQU 1B 53  1           / Set Subscript under              /
SUL EQU 1B 2D  1           / Start Underline                   /
CUL EQU 1B 2D              / Cancel Underline                  /
SCP EQU 1B 5B 54  4        / ESC   T : select code page                  /
CP8 EQU 1B 5B 54  4         3 52         / select code page 85           /
CP4 EQU 1B 5B 54  4         1 B5         / select code page 437           /
LL2 EQU 1B 41 24 1B 32 /  Setline length 2 lines/inch /
LL3 EQU 1B 41 18 1B 32 /  Setline length 3 lines/inch /
LL4 EQU 1B 41 12 1B 32 /  Setline length 4 lines/inch /
LL6 EQU 1B 41  C 1B 32 /  Set line length 6 lines/inch /
```

```
LL8 EQU 1B 41  9 1B 32 /  Set line length 8 lines/inch /
LL  EQU 1B 41  7 1B 32 /  Set line length 1  lines/inc /
                                / actually 7/72 inch                /
SD1 EQU 1B 5B 46  5       1  1      /  Select Drawer 1  /
SD2 EQU 1B 5B 46  5       1  2      /  Select Drawer 2  /
ENV EQU 1B 5B 46  5       2         /  Select Envelope  /
FRM EQU 1B 64               /  Forward Relative Movement      /
VLF EQU 1B 4A               /  Vertical Line Feed 1/216 inch units              /
SPO EQU 1B 6B               /  Set Portrait Orientation             /
SLO EQU 1B 6C               /  Set Landscape Orientation           /
SFG EQU 1B 5B 49  8   /  Set Font Global                          /
END_MACROS
/                               Session  Parameters                                        /
/  These parameters determine the way in which output will be               /
/  formatted for your printer.                                                  /
/  Numeric Parameters                                                                    /
/  These parameters should be defined with a two digit hex number          /
/  or a three digit decimal number.    The range of the number is zero     /
/  to 255 (decimal).                                                                  /
MAXIMUM_PAGE_LENGTH= 66                   /  Printed lines per page           /
MAXIMUM_PRINT_POSITION= 8                 /  Printed characters per line  /
INTERV_REQ_TIMER=  1
RESELECT_TIME_EXCPT_52 4=  1
INTERV_TIMER_ON_PE_ONLY?=NO
HORIZONTAL_PEL=12
VERTICAL_PEL=216
LINE_SPACING_RATIO= 72
PAGE_LENGTH_TYPE?=INCH                    /  SET_PAGE_LENGTH "value" is     /
                                                /  values                                  /
/  YES/NO Parameters                                                                     /
/  These parameters should be defined with either "YES" or "NO" on the /
/  right hand side of the '='                                                          /
COMPRESS_LINE_SPACING?=NO                 /  Should blank or null lines     /
                                                /  be printed?                          /
FORM_FEED_ANY_POSITION?=YES               /  Should the form feed be          /
                                                /  valid in any position?           /
OVERRIDE_FORMATTED_PRINT?=YES             /  Should nulls be printed as     /
                                                /  blanks?                              /
AUTO_NEWLINE_AT_MAX_POS?=NO
/                                       Control  Codes                                     /
/  These definitions tell the emulator what control strings to send to /
/  your printer to issue control commands.                                      /
/                                                                                          /
/  Format                                                                                  /
/  The name of the control command should always be at the beginning     /
/  of a line followed by a '=' and then a definition string.                /
/  A Definition String is any combination of macro names, hexadecimal  /
/  numbers, and characters separated by blanks.    A macro must have        /
/  previously defined in the macro definitions section above. A             /
/  hexadecimal number must be two digits ( ,..,F) long. and a               /
/  character must be preceded and followed by a blank.    If a               /
/  definition string will not fit on a line, it may be continued            /
/  as many lines as you wish by ending each line except the last with  /
/  a comma;    ','.      You made add any comments you wish to by including /
/  them between a slash     and a  slash where slash is the symbol /.       /

/  START_JOB is the control string which will be sent to your printer  /
/  at the beginning of each print job.                                          /
START_JOB=SEL CDW CDL CUL CDS CP8 CS2
/  END_JOB is the string which will be sent to your printer at the end /
/  of each print job.                                                                  /
END_JOB=CAT CDW CDL CUL CDS CP4 FFF
BACKSPACE=BAK
BEL=BEL
CARRIAGE_RETURN=CRR
NEW_LINE=CRR LFF
LINE_FEED=LFF
FORM_FEED=FFF
HORIZONTAL_TAB=TAB
VERTICAL_TAB=VTB
START_SUBSCRIPT=SSU
END_SUBSCRIPT=CSS
```

```
START_SUPERSCRIPT=SSO
END_SUPERSCRIPT=CSS
DUP=
FIELD_MARK=;
/  The following commands specify control codes for which most PC          /
/  printers require command strings which contain a variable value        /
/  or values somewhere in the middle of the string.                        /
/  Place the word "value(s)" in the position of your definition            /
/  string where the Personal Communications 525  should fill in            /
/  the hexadecimal value(s) indicated.                                     /
/  For example, on the IBM Proprinter, the SET_HORIZONTAL_TABS             /
/  definition is:                                                          /
/  SET_HORIZONTAL_TABS=ESC D values NUL                                                  /
SET_HORIZONTAL_TABS=SHT values NUL     /  "values" are the tab stops     /
                                       /  in column numbers              /
SET_VERTICAL_TABS=SVT values NUL       /  "values" are the tab stops     /
                                       /  in line numbers                /
SET_HORIZONTAL_MARGINS=
SET_PAGE_LENGTH=SFL value              /  "value"=inch of the page       /
SET_AUTO_PERFORATION_SKIP=SSP value
                                       /  "value"=number of lines to     /
                                       /  skip over the perforation      /
                                       /  between pages.    Used to set  /
                                       /  top and bottom margins.        /
SET_VARIABLE_LINE_DENSITY=ESC A value ESC 2
                                       /  "value"=number of points.      /
                                       /  A point is                     /
                                       /  1/(LINE_SPACING_RATIO) inch.   /
SET_CHARACTER_SET=
/ SET_CHARACTER_SET=ESC I NULL    selects the normal font                 /
/ SET_CHARACTER_SET=ESC I  2    selects the NLQ (near letter quality)     /
/ SET_CHARACTER_SET=ESC I  4    selects the normal downloaded font        /
/ SET_CHARACTER_SET=ESC I  6    selects the NLQ downloaded font           /
/ SET_CHARACTER_SET=CS1           selects the Character set 1             /
/ SET_CHARACTER_SET=CS2           selects the Character set 2             /

/  These control codes set the printer lines per inch and characters     /
/  per inch to fixed amounts.                                                    /
/  If your printer does not support setting the line density in points /
/  then you can enter control strings for the following commands.          /
/  When Personal Communications 525  gets a command from the host to     /
/  set the lines per    inch, it will round it to the closest line per     /
/  inch setting that you provide.    Note that if you provide a command  /
/  for the SET_VARIABLE_LINE_DENSITY command above that it will be        /
/  used and any control strings you provide for the set lines per inch /
/  commands below will not be used.                                              /

SET_2_LINES_PER_INCH=LL2
SET_3_LINES_PER_INCH=LL3
SET_4_LINES_PER_INCH=LL4
SET_6_LINES_PER_INCH=LL6
SET_8_LINES_PER_INCH=LL8
SET_1 _LINES_PER_INCH=LL               /  7/72 inch or 9/96 inch          /
SET_1 _CHARACTERS_PER_INCH=P1
SET_12_CHARACTERS_PER_INCH=P12
SET_13_CHARACTERS_PER_INCH=            /                                  /
SET_15_CHARACTERS_PER_INCH=            /  The proprinter does not         /
                                       /  support 15 pitch except in     /
                                       /  graphs mode                    /
SET_17_CHARACTERS_PER_INCH=P17         /  Condensed mode                  /
SET_2 _CHARACTERS_PER_INCH=
START_DOUBLE_WIDTH_CHARACTERS=P 5
END_DOUBLE_WIDTH_CHARACTERS=CDW

/  These control codes are used to select the source drawer number        /
/  when your printer has the dual drawer sheetfeed option.                /
SELECT_DRAWER1=SD1
SELECT_DRAWER2=SD2
SELECT_DRAWER3=
SELECT_ENVELOPE=ENV                    /  Envelop                         /
```

```
/ These control codes select the print mode (quality of print).          /
SELECT_DRAFT_QUALITY=
SELECT_LETTER_QUALITY=
SELECT_ENHANCED_QUALITY=
SELECT_SETUP_QUALITY=

/ These control codes                                                    /
SET_DUPLEX=
SET_DUPLEX_TUMBLE=
RESET_DUPLEX=

/ These control codes set page orientation                               /
SET_PORTRAIT_ORIENT=SPO
SET_LANDSCAPELEFT_ORIENT=SLO
SET_PORTRAITUPDWN_ORIENT=SPO
SET_LANDSCAPERGHT_ORIENT=SLO

/ These control codes move the print position (Horizontal/Vertical)    /
FORWARD_HORIZONTAL_SKIP=FRM word-value(LH)
FORWARD_VERTICAL_STEP_FEED=VLF byte-value

/ These control codes select the printer font via global font ID       /
SET_FONT_GLOBAL=
SET_GFID_  3=SFG    3   9  1  1  3 52 CDW    / OCR-B.1                  /
SET_GFID_  5=SFG    5   9  1  1  3 52 CDW    / Orator.1                 /
SET_GFID_ 11=SFG    B   9  1  1  3 52 CDW    / Courier.1                /
SET_GFID_ 12=SFG    C   9  1  1  3 52 CDW    / Prestige.1               /
SET_GFID_ 13=SFG    B   9  1  1  3 52 CDW    / Artisan.1                /
SET_GFID_ 18=SFG   12   9  1  1  3 52 CDW    / Courier.Italic.1    /
SET_GFID_ 19=SFG   13   9  1  1  3 52 CDW    / OCR-A.1                  /
SET_GFID_  2 =SFG   14   9  1  1  3 52 CDW    / Pica.1                   /
SET_GFID_  3 =SFG   1E   9  1  1  3 52 CDW    / Math-Symbol.1            /
SET_GFID_ 38=SFG   26   9  1  1  3 52 CDW    / Orator.Bold.1            /
SET_GFID_ 39=SFG   27   9  1  1  3 52 CDW    / Gothic.Bold.1            /
SET_GFID_  4 =SFG   28   9  1  1  3 52 CDW    / Gothic-Text.1            /
SET_GFID_ 41=SFG   29   9  1  1  3 52 CDW    / Roman-text.1             /
SET_GFID_ 42=SFG   2A   9  1  1  3 52 CDW    / Serif-text.1             /
SET_GFID_ 43=SFG   2B   9  1  1  3 52 CDW    / Serif-text.Italic.1  /
SET_GFID_ 44=SFG   2C   9  1  1  3 52 CDW    / Katakana-gothic.1    /
SET_GFID_ 45=SFG   2D   9  1  1  3 52 CDW    / APL.1                    /
SET_GFID_ 46=SFG   2E   9  1  1  3 52 CDW    / Courier.Bold.1           /
SET_GFID_  5 =SFG   32   9  1  1  3 52 CDW    / Shalom.1                 /
SET_GFID_ 66=SFG   42   78  1  1  3 52 CDW    / Gothic-text.12           /
SET_GFID_ 68=SFG   44   78  1  1  3 52 CDW    / Gothic-text.Italic.12 /
SET_GFID_ 69=SFG   45   78  1  1  3 52 CDW    / Gothic.Bold.12           /
SET_GFID_  7 =SFG   46   78  1  1  3 52 CDW    / Serif-text.12            /
SET_GFID_ 71=SFG   47   78  1  1  3 52 CDW    / Serif-text.Italic.12 /
SET_GFID_ 72=SFG   48   78  1  1  3 52 CDW    / Serif.Bold.12            /
SET_GFID_  8 =SFG   73   78  1  1  3 52 CDW    / Math-Symbol.12           /
SET_GFID_ 84=SFG   54   78  1  1  3 52 CDW    / Script.12                /
SET_GFID_ 85=SFG   55   78  1  1  3 52 CDW    / Courier.12               /
SET_GFID_ 86=SFG   56   78  1  1  3 52 CDW    / Prestige.12              /
SET_GFID_ 87=SFG   57   78  1  1  3 52 CDW    / Letter-gothic.12     /
SET_GFID_ 91=SFG   7    78  1  1  3 52 CDW    / Light.Italic.12      /
SET_GFID_ 1 7=SFG   55   78  1  1  3 52 CDW    / Courier.12               /
SET_GFID_ 11 =SFG   6E   78  1  1  3 52 CDW    / Letter-Gothic.Bold.12 /
SET_GFID_ 111=SFG   6F   78  1  1  3 52 CDW    / Prestige-Elite.Bold.12 /
SET_GFID_ 112=SFG   7    78  1  1  3 52 CDW    / Prestige.Italic.12  /
SET_GFID_ 115=SFG   73   78  1  1  3 52 CDW    / Math-Symbol.12           /
SET_GFID_ 155=SFG   9B   78  2  1  3 52 CDW    / Boldface.Italic.PSM /
SET_GFID_ 158=SFG   9E   78  2  1  3 52 CDW    / Modern.PSM               /
SET_GFID_ 159=SFG   9F   78  2  1  3 52 CDW    / Document.PSM             /
SET_GFID_ 16 =SFG   A    78  2  1  3 52 CDW    / Essay.PSM                /
SET_GFID_ 162=SFG   A2   78  2  1  3 52 CDW    / Essay.Italic.PSM     /
SET_GFID_ 163=SFG   A3   78  2  1  3 52 CDW    / Essay.Bold.PSM           /
SET_GFID_ 168=SFG   A8   78  2  1  3 52 CDW    / Barak.PSM                /
SET_GFID_ 173=SFG   AD   78  2  1  3 52 CDW    / Essay.Light.PSM          /
SET_GFID_ 175=SFG   AF   78  2  1  3 52 CDW    / Document.PSM             /
SET_GFID_ 176=SFG   B    78  2  1  3 52 CDW    / Boldface.PSM             /
SET_GFID_ 177=SFG   9B   78  2  1  3 52 CDW    / Boldface.Italic.PSM /
SET_GFID_ 193=SFG   73   78  1  1  3 52 CDW    / Math-Symbol.12           /
SET_GFID_ 198=SFG   1E   9  1  1  3 52 CDW    / Math-Symbol.1            /
```

```
SET_GFID_ 2 4=SFG   CC   6C  1  1  3 52 CDW    / Gothic-text.13        /
SET_GFID_ 221=SFG   DD   6   1  1  3 52 CDW    / Prestige.15           /
SET_GFID_ 222=SFG   E6   6   1  1  3 52 CDW    / Gothic-text.15        /
SET_GFID_ 223=SFG   DF   6   1  1  3 52 CDW    / Courier.15            /
SET_GFID_ 225=SFG   E1   6   1  1  3 52 CDW    / Math-symbol.15        /
SET_GFID_ 229=SFG   E5   6   1  1  3 52 CDW    / Serif-text.15         /
SET_GFID_ 23 =SFG   E6   6   1  1  3 52 CDW    / Gothic-text.15        /
SET_GFID_ 245=SFG   2E   9   1  1  3 52 P 5    / Courier.Bold.5        /
SET_GFID_ 252=SFG   FC   54  1  1  3 52 CDW    / Courier.15            /
SET_GFID_ 253=SFG   FD   54  1  1  3 52 CDW    / Courier.Bold.17       /
SET_GFID_ 254=SFG   FE   55  1  1  3 52 CDW    / Courier.17            /
SET_GFID_ 28 =SFG  1 18   48  1  1  3 52 CDW    / APL.2                 /
SET_GFID_ 281=SFG  1 19   48  1  1  3 52 CDW    / Gothic-text.2         /
SET_GFID_ 29 =SFG  1 22   36  1  1  3 52 CDW    / Gothic-text.27        /
SET_GFID_ 751=SFG 11 37   A   1  3  3 52 CDW    / Sonoran-serif.8pt     /
SET_GFID_1 51=SFG 11 37   C8  1  3  3 52 CDW    / Sonoran-serif.1 pt    /
SET_GFID_1 53=SFG 11 4B   C8  1  3  3 52 CDW    / Sonoran-serif.bold.1 pt /
SET_GFID_1 56=SFG 11 B7   C8  1  3  3 52 CDW    / Sonoran-serif.italic.1 pt /
SET_GFID_1351=SFG 11 37   F   1  3  3 52 CDW    / Sonoran-serif.12pt    /
SET_GFID_1653=SFG 11 4B  1 4   1  3  3 52 CDW   / Sonoran-serif.Bold.16pt /
SET_GFID_21 3=SFG 11 4B  1 E   1  3  3 52 CDW   / Sonoran-serif.Bold.24pt /

/                              Color  Specifications                        /
START_COLOR_BLUE=
END_COLOR_BLUE=
START_COLOR_GREEN=
END_COLOR_GREEN=
START_COLOR_CYAN=
END_COLOR_CYAN=
START_COLOR_RED=
END_COLOR_RED=
START_COLOR_MAGENTA=
END_COLOR_MAGENTA=
START_COLOR_YELLOW=
END_COLOR_YELLOW=
START_COLOR_BLACK=
END_COLOR_BLACK=
START_COLOR_WHITE=
END_COLOR_WHITE=

/                              Highlight  Specifications                    /
/  These definitions will determine how things which are sent by the     /
/  host to be displayed or printed as underlined, reverse video, or      /
/  blinking will be highlighted on your printer.                         /

START_HIGHLIGHT_INTENSE=SDS              / This is double strike         /
END_HIGHLIGHT_INTENSE=CDS
START_HIGHLIGHT_UNDERLINE=SUL
END_HIGHLIGHT_UNDERLINE=CUL
START_HIGHLIGHT_REVERSE_VIDEO=
END_HIGHLIGHT_REVERSE_VIDEO=
START_HIGHLIGHT_BLINK=
END_HIGHLIGHT_BLINK=

/                              Character  Definitions                       /
SPACE=SPA
EXCLAMATION_POINT=21
QUOTATION_MARKS=22
NUMBER_SIGN=23
DOLLAR_SIGN=24
PERCENT_SIGN=25
AMPERSAND=26
APOSTROPHE=27
LEFT_PARENTHESIS=28
RIGHT_PARENTHESIS=29
ASTERISK=2A
PLUS_SIGN=2B
COMMA=2C
HYPHEN=2D
PERIOD=2E
SLASH=2F
ZERO=
```

```
ONE=1
TWO=2
THREE=3
FOUR=4
FIVE=5
SIX=6
SEVEN=7
EIGHT=8
NINE=9
COLON=3A
SEMICOLON=3B
LESS_THAN_SIGN=3C
EQUAL_SIGN=3D
GREATER_THAN_SIGN=3E
QUESTION_MARK=3F
AT_SIGN=4
A_CAPITAL=A
B_CAPITAL=B
C_CAPITAL=C
D_CAPITAL=D
E_CAPITAL=E
F_CAPITAL=F
G_CAPITAL=G
H_CAPITAL=H
I_CAPITAL=I
J_CAPITAL=J
K_CAPITAL=K
L_CAPITAL=L
M_CAPITAL=M
N_CAPITAL=N
O_CAPITAL=O
P_CAPITAL=P
Q_CAPITAL=Q
R_CAPITAL=R
S_CAPITAL=S
T_CAPITAL=T
U_CAPITAL=U
V_CAPITAL=V
W_CAPITAL=W
X_CAPITAL=X
Y_CAPITAL=Y
Z_CAPITAL=Z
LEFT_BRACKET=5B
BACKSLASH=5C
RIGHT_BRACKET=5D
CIRCUMFLEX_ACCENT=5E
UNDERLINE=5F
GRAVE_ACCENT=6
A_SMALL=a
B_SMALL=b
C_SMALL=c
D_SMALL=d
E_SMALL=e
F_SMALL=f
G_SMALL=g
H_SMALL=h
I_SMALL=i
J_SMALL=j
K_SMALL=k
L_SMALL=l
M_SMALL=m
N_SMALL=n
O_SMALL=o
P_SMALL=p
Q_SMALL=q
R_SMALL=r
S_SMALL=s
T_SMALL=t
U_SMALL=u
V_SMALL=v
W_SMALL=w
X_SMALL=x
```

Y_SMALL=y
Z_SMALL=z
LEFT_BRACE=7B
VERTICAL_BAR=7C
RIGHT_BRACE=7D
TILDE_ACCENT=7E
C_CEDILLA_CAPITAL=8
U_DIAERESIS_SMALL=81
E_ACUTE_SMALL=82
A_CIRCUMFLEX_SMALL=83
A_DIAERESIS_SMALL=84
A_GRAVE_SMALL=85
A_OVERCIRCLE_SMALL=86
C_CEDILLA_SMALL=87
E_CIRCUMFLEX_SMALL=88
E_DIAERESIS_SMALL=89
E_GRAVE_SMALL=8A
I_DIAERESIS_SMALL=8B
I_CIRCUMFLEX_SMALL=8C
I_GRAVE_SMALL=8D
A_DIAERESIS_CAPITAL=8E
A_OVERCIRCLE_CAPITAL=8F
E_ACUTE_CAPITAL=9
AE_DIPTHONG_SMALL=91
AE_DIPTHONG_CAPITAL=92
O_CIRCUMFLEX_SMALL=93
O_DIAERESIS_SMALL=94
O_GRAVE_SMALL=95
U_CIRCUMFLEX_SMALL=96
U_GRAVE_SMALL=97
Y_DIAERESIS_SMALL=98
O_DIAERESIS_CAPITAL=99
U_DIAERESIS_CAPITAL=9A
O_SLASH_SMALL=9B
POUND_SIGN=9C
O_SLASH_CAPITAL=9D
MULTIPLY_SIGN=9E
A_ACUTE_SMALL=A
I_ACUTE_SMALL=A1
O_ACUTE_SMALL=A2
U_ACUTE_SMALL=A3
N_TILDE_SMALL=A4
N_TILDE_CAPITAL=A5
ORDINAL_INDICATOR_FEMININE=A6
ORDINAL_INDICATOR_MASCULINE=A7
QUESTION_MARK_INVERTED=A8
REGISTERED_TRADEMARK_SYMBOL=A9
LOGICAL_NOT=AA
ONE_HALF=AB
ONE_QUARTER=AC
EXCLAMATION_POINT_INVERTED=AD
LEFT_ANGLE_QUOTES=AE
RIGHT_ANGLE_QUOTES=AF
A_ACUTE_CAPITAL=B5
A_CIRCUMFLEX_CAPITAL=B6
A_GRAVE_CAPITAL=B7
COPYRIGHT_SYMBOL=B8
CENT_SIGN=BD
YEN_SIGN=BE
A_TILDE_SMALL=C6
A_TILDE_CAPITAL=C7
INTERNATIONAL_CURRENCY_SYMBOL=CF
ETH_ICELANDIC_SMALL=D
ETH_ICELANDIC_CAPITAL=D1
E_CIRCUMFLEX_CAPITAL=D2
E_DIAERESIS_CAPITAL=D3
E_GRAVE_CAPITAL=D4
I_DOTLESS_SMALL=D5
I_ACUTE_CAPITAL=D6
I_CIRCUMFLEX_CAPITAL=D7
I_DIAERESIS_CAPITAL=D8
VERTICAL_LINE_BROKEN=DD

```
I_GRAVE_CAPITAL=DE
O_ACUTE_CAPITAL=E
SHARP_S_SMALL=E1
O_CIRCUMFLEX_CAPITAL=E2
O_GRAVE_CAPITAL=E3
O_TILDE_SMALL=E4
O_TILDE_CAPITAL=E5
MICRO_SYMBOL=E6
THORN_ICELANDIC_SMALL=E7
THORN_ICELANDIC_CAPITAL=E8
U_ACUTE_CAPITAL=E9
U_CIRCUMFLEX_CAPITAL=EA
U_GRAVE_CAPITAL=EB
Y_ACUTE_SMALL=EC
Y_ACUTE_CAPITAL=ED
OVERLINE=EE
ACUTE_ACCENT=EF
SYLLABLE_HYPHEN=F
PLUS_OR_MINUS_SIGN=F1
THREE_QUARTERS=F3
PARAGRAPH_SYMBOL=F4
SECTION_SYMBOL=F5
DIVIDE_SIGN=F6
CEDILLA=F7
DEGREE_SYMBOL=F8
DIAERESIS=F9
MIDDLE_DOT_ACCENT=FA
ONE_SUPERSCRIPT=FB
THREE_SUPERSCRIPT=FC
TWO_SUPERSCRIPT=FD
REQUIRED_SPACE=SPA
/                                        /
/                PC525  Internal Data Area.                    /
/  Do not change these statement.                              /
/                                        /
TOP_MARGIN=
LEFT_MARGIN=
DYNAMIC_START_JOB=
DYNAMIC_END_JOB=
DYNAMIC_SET_PAGE_LENGTH=
PRINTER_ID=4  19
/                        End of Definition File                /
```

ELQ2550.PDF File Contents

```
/                                                    /
/                                                                                  /
/       PRINTER SESSION DEFINITION FILE FOR: Epson   LQ255                          /
/                                                                                  /
/                                                    /
BEGIN_MACROS
NUL EQU                                              / Nul character                 /
BEL EQU  7                                           / Bell                           /
BAK EQU  8                                           / Back space                     /
TAB EQU  9                                           / Tabs                           /
LFF EQU  A                                           / Line Feed                      /
VTB EQU  B                                           / Vertical Tabs                  /
FFF EQU  C                                           / Form Feed                      /
CRR EQU  D                                           / Carriage Return                /
SCM EQU  F                                           / Select Condensed Mode          /
CCM EQU 12                                           / Cancel Condensed Mode          /
ESC EQU 1B                                           / Escape                         /
SPA EQU 2                                            / Space                          /
SIT EQU 1B 34                                        / Select Italic mode             /
CIT EQU 1B 35                                        / Cancel Italic mode             /
CS1 EQU 1B 37                                        / Select Character Set 1         /
CS2 EQU 1B 36                                        / Select Character Set 2         /
INZ EQU 1B 4                                         / Initialize Printer(Reset)      /
SHT EQU 1B 44                                        / Set horizontal tabs            /
SVT EQU 1B 42                                        / Set vertical tabs              /
SBP EQU 1B 45                                        / Start Bold Printing (Emphasize /
CBP EQU 1B 46                                        / Cancel Bold Printing(Emphasize /
SUL EQU 1B 2D  1                                     / Start Underline                /
CUL EQU 1B 2D                                        / Cancel Underline               /
SDW EQU 1B 57  1                                     / Start double width printing    /
CDW EQU 1B 57                                        / Cancel double width printing   /
SDS EQU 1B 47                                        / Start Double Strike Printing   /
CDS EQU 1B 48                                        / Cancel Double Strike Printing  /
SPS EQU 1B 7   1                                     / Select PS font                 /
CPS EQU 1B 7                                         / PS off                         /
SSU EQU 1B 53  1                                     / Start SubScript mode           /
SSO EQU 1B 53                                        / Start SuperScript mode         /
CSS EQU 1B 54                                        / Cancel SuperScript mode        /
SFL EQU 1B 43                                        / Set Page Length                /
USA EQU 1B 52                                        / Set internal char set in USA   /
CP  EQU 1B 74                                        / Set Italic character Set       /
CP1 EQU 1B 74  1                                     / Set Epson Ext Graphic Char Set /
LL2 EQU 1B 2B B4                                     / Set line length   2 lines/inch /
LL3 EQU 1B 2B 78                                     / Set line length   3 lines/inch /
LL4 EQU 1B 2B 5A                                     / Set line length   4 lines/inch /
LL6 EQU 1B 32                                        / Set line length   6 lines/inch /
LL8 EQU 1B 3                                         / Set line length   8 lines/inch /
LL  EQU 1B 2B 24                                     / Set line length 1  lines/inch /
P1  EQU 1B 5                                         / 1  Pitch-Characters/inch       /
P12 EQU 1B 4D                                        / 12 Pitch-Characters/inch       /
P15 EQU 1B 67                                        / 15 Pitch-Characters/inch       /
P17 EQU 1B 5   F                                     / 17 Pitch-Characters/inch       /
P2  EQU 1B 4D  F                                     / 2  Pitch-Characters/inch       /
ST  EQU 1B 6B                                        / Select TypeStyle Roman         /
ST1 EQU 1B 6B  1                                     / Select TypeStyle Sans Serif    /
ST2 EQU 1B 6B  2                                     / Select TypeStyle Courier       /
ST3 EQU 1B 6B  3                                     / Select TypeStyle Prestige      /
ST4 EQU 1B 6B  4                                     / Select TypeStyle Script        /
ST5 EQU 1B 6B  5                                     / Select TypeStyle OCR-B         /
ST6 EQU 1B 6B  6                                     / Select TypeStyle OCR-A         /
SDQ EQU 1B 78                                        / Select Draft Quality           /
SLQ EQU 1B 78  1                                     / Select Letter Quality          /
SLD EQU 1B 2B                                        / Set Variable Line Density      /
FRM EQU 1B 5C                                        / Forward Relative Movement      /
SD1 EQU 1B 19 31                                     / Select Drawer 1                /
SD2 EQU 1B 19 32                                     / Select Drawer 2                /
END_MACROS


/                                    /
/                Session  Parameters                 /
```

```
/                                                    /
MAXIMUM_PAGE_LENGTH =  66                  / Printed lines per page            /
MAXIMUM_PRINT_POSITION =  8               / Printed characters per line      /
INTERV_REQ_TIMER=  1

HORIZONTAL_PEL=18
PAGE_LENGTH_TYPE?=LINE
LINE_SPACING_RATIO= 36

/  YES/NO Parameters                                                          /
COMPRESS_LINE_SPACING? = NO              / Should blank or null lines       /
                                         / be printed?                      /
FORM_FEED_ANY_POSITION? = YES            / Should the form feed be          /
                                         / valid in any position?           /
OVERRIDE_FORMATTED_PRINT? = YES          / Should nulls be printed as       /
                                         /  blanks?                         /
ESC/P_LINE_FEED? = YES

/                                                    /
/                                Control  Codes                             /
/                                                    /
START_JOB = INZ CBP CUL CIT CDW CDS CSS CP1 USA CS2 LL6 P1
END_JOB = CBP CUL CIT CDW CDS CSS FFF
HORIZONTAL_TAB = TAB
VERTICAL_TAB = VTB
SET_HORIZONTAL_TABS = SHT values NUL   / "values" are the tab stops       /
                                       / in column numbers                /
SET_VERTICAL_TABS = SVT values NUL     / "values" are the tab stops       /
                                       / in line numbers                  /
BACKSPACE = BAK
BEL = BEL
CARRIAGE_RETURN = CRR
LINE_FEED = LFF                        / Form feed is occurred after      /
                                       / line feed.                       /
FORM_FEED = FFF
NEW_LINE = CRR LFF
DESELECT =
DUP =
FIELD_MARK = ;
START_SUBSCRIPT = SSU
END_SUBSCRIPT = CSS
START_SUPERSCRIPT = SSO
END_SUPERSCRIPT = CSS
SET_AUTO_PERFORATION_SKIP =

SET_HORIZONTAL_MARGINS =
SET_PAGE_LENGTH = SFL value            / "value" is the number of         /
                                       / lines in the page                /

/                                                    /

SET_VARIABLE_LINE_DENSITY= SLD byte-value

SET_2_LINES_PER_INCH = LL2
SET_3_LINES_PER_INCH = LL3
SET_4_LINES_PER_INCH = LL4
SET_6_LINES_PER_INCH = LL6
SET_8_LINES_PER_INCH = LL8
SET_1 _LINES_PER_INCH = LL
SET_1 _CHARACTERS_PER_INCH = P1
SET_12_CHARACTERS_PER_INCH = P12
SET_13_CHARACTERS_PER_INCH =
SET_15_CHARACTERS_PER_INCH = P15
SET_17_CHARACTERS_PER_INCH = P17
SET_2 _CHARACTERS_PER_INCH = P2

START_DOUBLE_WIDTH_CHARACTERS = SDW
END_DOUBLE_WIDTH_CHARACTERS = CDW

/ These control codes are used to select the source drawer number      /
/ when your printer has the dual drawer sheetfeed option.              /
```

```
SELECT_DRAWER1=SD1
SELECT_DRAWER2=SD2

/ These control codes select the print mode (quality of print).          /
SELECT_DRAFT_QUALITY = SDQ
SELECT_LETTER_QUALITY = SLQ
SELECT_ENHANCED_QUALITY =
SELECT_SETUP_QUALITY =

/ These control codes move the print position (Horizontal/Vertical)    /
FORWARD_HORIZONTAL_SKIP=FRM word-value(LH)

/ These control codes select the printer font via global font ID        /
SET_GFID_   3=CPS CDW CBP CIT CCM P1  ST5
SET_GFID_   5=CPS CDW CBP CIT CCM P1
SET_GFID_  11=CPS CDW CBP CIT CCM P1  ST2
SET_GFID_  12=CPS CDW CBP CIT CCM P1  ST3
SET_GFID_  13=CPS CDW CBP CIT CCM P1  ST2
SET_GFID_  18=CPS CDW CBP CIT CCM P1  ST2 SIT
SET_GFID_  19=CPS CDW CBP CIT CCM P1  ST6
SET_GFID_  2 =CPS CDW CBP CIT CCM P1  ST3
SET_GFID_  3 =CPS CDW CBP CIT CCM P1
SET_GFID_  38=CPS CDW CBP CIT CCM P1  SBP
SET_GFID_  39=CPS CDW CBP CIT CCM P1  ST1 SBP
SET_GFID_  4 =CPS CDW CBP CIT CCM P1
SET_GFID_  41=CPS CDW CBP CIT CCM P1  ST
SET_GFID_  42=CPS CDW CBP CIT CCM P1  ST1
SET_GFID_  43=CPS CDW CBP CIT CCM P1  ST1 SIT
SET_GFID_  44=CPS CDW CBP CIT CCM P1
SET_GFID_  45=CPS CDW CBP CIT CCM P1
SET_GFID_  46=CPS CDW CBP CIT CCM P1  ST2 SBP
SET_GFID_  5 =CPS CDW CBP CIT CCM P1
SET_GFID_  66=CPS CDW CBP CIT CCM P12
SET_GFID_  68=CPS CDW CBP CIT CCM P12 SIT
SET_GFID_  69=CPS CDW CBP CIT CCM P12 SBP
SET_GFID_  7 =CPS CDW CBP CIT CCM P12 ST1
SET_GFID_  71=CPS CDW CBP CIT CCM P12 ST1 SIT
SET_GFID_  72=CPS CDW CBP CIT CCM P12 ST1 SBP
SET_GFID_  8 =CPS CDW CBP CIT CCM P12
SET_GFID_  84=CPS CDW CBP CIT CCM P12 ST4
SET_GFID_  85=CPS CDW CBP CIT CCM P12 ST2
SET_GFID_  86=CPS CDW CBP CIT CCM P12 ST3
SET_GFID_  87=CPS CDW CBP CIT CCM P12 ST1
SET_GFID_  91=CPS CDW CBP CIT CCM P12 SIT
SET_GFID_ 1 7=CPS CDW CBP CIT CCM P12 ST2
SET_GFID_ 11 =CPS CDW CBP CIT CCM P12 ST1 SBP
SET_GFID_ 111=CPS CDW CBP CIT CCM P12 ST3 SBP
SET_GFID_ 112=CPS CDW CBP CIT CCM P12 ST3 SIT
SET_GFID_ 115=CPS CDW CBP CIT CCM P12
SET_GFID_ 155=CPS CDW CBP CIT CCM P12 SPS SIT
SET_GFID_ 158=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 159=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 16 =CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 162=CPS CDW CBP CIT CCM P12 SPS SIT
SET_GFID_ 163=CPS CDW CBP CIT CCM P12 SPS SBP
SET_GFID_ 168=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 173=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 175=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 176=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 177=CPS CDW CBP CIT CCM P12 SPS
SET_GFID_ 193=CPS CDW CBP CIT CCM P12
SET_GFID_ 198=CPS CDW CBP CIT CCM P1
SET_GFID_ 2 4=CPS CDW CBP CIT CCM P15
SET_GFID_ 221=CPS CDW CBP CIT CCM P15 ST3
SET_GFID_ 222=CPS CDW CBP CIT CCM P15 ST1
SET_GFID_ 223=CPS CDW CBP CIT CCM P15 ST2
SET_GFID_ 225=CPS CDW CBP CIT CCM P15
SET_GFID_ 229=CPS CDW CBP CIT CCM P15 ST1
SET_GFID_ 23 =CPS CDW CBP CIT CCM P15
SET_GFID_ 245=CPS CDW CBP CIT CCM P1  ST2 SDW SBP
SET_GFID_ 252=CPS CDW CBP CIT CCM P17 ST2
SET_GFID_ 253=CPS CDW CBP CIT CCM P17 ST2 SBP
```

```
SET_GFID_ 254=CPS CDW CBP CIT CCM P17 ST2
SET_GFID_ 28 =CPS CDW CBP CIT CCM P2
SET_GFID_ 281=CPS CDW CBP CIT CCM P2
SET_GFID_ 29 =CPS CDW CBP CIT CCM P2

/                                       /
/                  Color  Specifications                  /
/                                       /
START_COLOR_BLUE=
END_COLOR_BLUE=
START_COLOR_GREEN=
END_COLOR_GREEN=
START_COLOR_CYAN=
END_COLOR_CYAN=
START_COLOR_RED=
END_COLOR_RED=
START_COLOR_MAGENTA=
END_COLOR_MAGENTA=
START_COLOR_YELLOW=
END_COLOR_YELLOW=
START_COLOR_BLACK=
END_COLOR_BLACK=
START_COLOR_WHITE=
END_COLOR_WHITE=

/                                       /
/                Highlight  Specifications              /
/                                       /
START_HIGHLIGHT_INTENSE = SBP          / select stroke weight          /
END_HIGHLIGHT_INTENSE = CBP
START_HIGHLIGHT_UNDERLINE = SUL        / Select underlined font        /
END_HIGHLIGHT_UNDERLINE = CUL
START_HIGHLIGHT_REVERSE_VIDEO =
END_HIGHLIGHT_REVERSE_VIDEO =
START_HIGHLIGHT_BLINK =
END_HIGHLIGHT_BLINK =

/                                       /
/                  Character  Definitions                 /
/                                       /
SPACE=SPA
EXCLAMATION_POINT=21
QUOTATION_MARKS=22
NUMBER_SIGN=23
DOLLAR_SIGN=24
PERCENT_SIGN=25
AMPERSAND=26
APOSTROPHE=27
LEFT_PARENTHESIS=28
RIGHT_PARENTHESIS=29
ASTERISK=2A
PLUS_SIGN=2B
COMMA=2C
HYPHEN=2D
PERIOD=2E
SLASH=2F
ZERO=
ONE=1
TWO=2
THREE=3
FOUR=4
FIVE=5
SIX=6
SEVEN=7
EIGHT=8
NINE=9
COLON=3A
SEMICOLON=3B
LESS_THAN_SIGN=3C
EQUAL_SIGN=3D
GREATER_THAN_SIGN=3E
QUESTION_MARK=3F
```

```
AT_SIGN=4
A_CAPITAL=A
B_CAPITAL=B
C_CAPITAL=C
D_CAPITAL=D
E_CAPITAL=E
F_CAPITAL=F
G_CAPITAL=G
H_CAPITAL=H
I_CAPITAL=I
J_CAPITAL=J
K_CAPITAL=K
L_CAPITAL=L
M_CAPITAL=M
N_CAPITAL=N
O_CAPITAL=O
P_CAPITAL=P
Q_CAPITAL=Q
R_CAPITAL=R
S_CAPITAL=S
T_CAPITAL=T
U_CAPITAL=U
V_CAPITAL=V
W_CAPITAL=W
X_CAPITAL=X
Y_CAPITAL=Y
Z_CAPITAL=Z
LEFT_BRACKET=5B
BACKSLASH=5C
RIGHT_BRACKET=5D
CIRCUMFLEX_ACCENT=5E
UNDERLINE=5F
GRAVE_ACCENT=6
A_SMALL=a
B_SMALL=b
C_SMALL=c
D_SMALL=d
E_SMALL=e
F_SMALL=f
G_SMALL=g
H_SMALL=h
I_SMALL=i
J_SMALL=j
K_SMALL=k
L_SMALL=l
M_SMALL=m
N_SMALL=n
O_SMALL=o
P_SMALL=p
Q_SMALL=q
R_SMALL=r
S_SMALL=s
T_SMALL=t
U_SMALL=u
V_SMALL=v
W_SMALL=w
X_SMALL=x
Y_SMALL=y
Z_SMALL=z
LEFT_BRACE=7B
VERTICAL_BAR=7C
RIGHT_BRACE=7D
TILDE_ACCENT=7E
C_CEDILLA_CAPITAL=8
U_DIAERESIS_SMALL=81
E_ACUTE_SMALL=82
A_CIRCUMFLEX_SMALL=83
A_DIAERESIS_SMALL=84
A_GRAVE_SMALL=85
A_OVERCIRCLE_SMALL=86
C_CEDILLA_SMALL=87
E_CIRCUMFLEX_SMALL=88
```

```
E_DIAERESIS_SMALL=89
E_GRAVE_SMALL=8A
I_DIAERESIS_SMALL=8B
I_CIRCUMFLEX_SMALL=8C
I_GRAVE_SMALL=8D
A_DIAERESIS_CAPITAL=8E
A_OVERCIRCLE_CAPITAL=8F
E_ACUTE_CAPITAL=9
AE_DIPTHONG_SMALL=91
AE_DIPTHONG_CAPITAL=92
O_CIRCUMFLEX_SMALL=93
O_DIAERESIS_SMALL=94
O_GRAVE_SMALL=95
U_CIRCUMFLEX_SMALL=96
U_GRAVE_SMALL=97
Y_DIAERESIS_SMALL=98
O_DIAERESIS_CAPITAL=99
U_DIAERESIS_CAPITAL=9A
O_SLASH_SMALL=o BAK 2F
POUND_SIGN=9C
O_SLASH_CAPITAL=O BAK 2F
MULTIPLY_SIGN=1B 2A 28 24   ,
                        8   8   8   8 ,
 c 1 8   c 1 8   6 3     6 3     3 6     3 6   ,
 1 8c    1 8c      d8      f8      7       7   ,
   2       7       7       f8      d8    1 8c  ,
 1 8c    3 6     3 6     6 3     6 3     c 1 8 ,
 c 1 8   8   8   8   8
A_ACUTE_SMALL=A
I_ACUTE_SMALL=A1
O_ACUTE_SMALL=A2
U_ACUTE_SMALL=A3
N_TILDE_SMALL=A4
N_TILDE_CAPITAL=A5
ORDINAL_INDICATOR_FEMININE=A6
ORDINAL_INDICATOR_MASCULINE=A7
QUESTION_MARK_INVERTED=A8
REGISTERED_TRADEMARK_SYMBOL=1B 2A 28 24   ,
          e     1 f     3 18    6 c     6 c   ,
 c 6    18  3    1   1    1   1    18  5     8  5   ,
2f fc 8  2f fc 8  28 44 8  28 4  8  28 4  8  28 4  8 ,
28 4  8  28 4  8  28 6  8  28 b  8  24 9c 8   7  d   ,
13  5    1   5    1   1    18  3     c 6     6 c   ,
 6 c     3 18    1 f       e
LOGICAL_NOT=AA
ONE_HALF=AB
ONE_QUARTER=AC
EXCLAMATION_POINT_INVERTED=AD
LEFT_ANGLE_QUOTES=AE
RIGHT_ANGLE_QUOTES=AF
A_ACUTE_CAPITAL=1B 2A 28 24   ,
      1       1       1       1       3       f ,
 6  1 f   6  3 f   6  7 1   6  e 1   6  1e 1   6 7e 1 ,
 6 f6    27 e6    27 86    27  6    26  6    66  6   ,
66  6    67  6    e3 86    e1 e6    c  f6 1  c  7e 1 ,
 c  1e 1  c   f 1  8   7 f     1 f       f       7 ,
      3       1       1       1       1
A_CIRCUMFLEX_CAPITAL=A BAK SSO 5E CSS
A_GRAVE_CAPITAL=A BAK SSO 6  CSS
COPYRIGHT_SYMBOL=1B 2A 28 24   ,
          e     1 f     3 18    6 c     6 c   ,
 c 6    18 e3    11 f1    11 11    12  9    2  9   ,
22  c 8  24  4 8  24  4 8  24  4 8  24  4 8  24  4 8 ,
24  4 8  22  c 8  22  8 8  22  8 8  2   8 8   7  9   ,
1   1    1   1    1   1    18  3     c 6     6 c   ,
 6 c     3 18    1 f       e
CENT_SIGN=c BAK 2F
YEN_SIGN=1B 2A 28 24   ,
              1       1       1       1  88   ,
1  88    1  88    18 88    1c 88    1e 88    17 88   ,
13 88 2  11 88 2     c8 2     68 2     78 2     3f e ,
  1f e     3f e     78 2     68 2     c8 2  11 c8 2 ,
```

```
 13 88 2  17 88    1e 88    1c 88    18 88    1  88   ,
 1  88    1  88    1        1        1
A_TILDE_SMALL=a BAK 7E
A_TILDE_CAPITAL=A BAK SSO 7E CSS
INTERNATIONAL_CURRENCY_SYMBOL=CF
ETH_ICELANDIC_SMALL=1B 2A 28 24   ,
                              e      3f 8 ,
   3f 8     71 c    e e  2  8  6  2  8  2  2  8  2 ,
 24 8  2  35 8  3  15    1  19    1  19    1  19    1 ,
  9    1  9    1  19    1  15    1  35    1  27 8  3 ,
 23 8  2   3 8  2   1 8  2     c  6     e  e     71 c ,
   3f 8     3f 8      e
ETH_ICELANDIC_CAPITAL=1B 2A 28 24   ,
               1     2  1  6  2  1  6  2  1  6  2 ,
 1  6  2  1f ff e  1f ff e  1f ff e  1  6  2  1  6  2 ,
 1  6  2  1  6  2  1  6  2  1  6  2  1  6  2  1  6  2 ,
 1  6  2  1  6  2  1  6  2  1     2  1     2  18    6 ,
  8    4   c    c   e  1 c   7  3 8   3  3     3 87   ,
  1 fe       fc       78
E_CIRCUMFLEX_CAPITAL=E BAK SSO 5E CSS
E_DIAERESIS_CAPITAL=1B 2A 28 24   ,
                     6    3   6    3   6    3 ,
  6    3  46    3  e7 ff f  e7 ff f  e7 ff f  e7 ff f ,
 e6 18 3  46 18 3   6 18 3   6 18 3   6 18 3   6 18 3 ,
  6 18 3   6 18 3   6 18 3   6 7e 3   6 7e 3  46    3 ,
 e6    3  e6    3  e6    3  e6    3  46    3   7 8  f ,
  7 8  f   7 8  f
E_GRAVE_CAPITAL=E BAK SSO 6  CSS
I_DOTLESS_SMALL=SSU l CSS
I_ACUTE_CAPITAL=1B 2A 28 24   ,
                                 ,
                     6    3   6    3  26    3 ,
 26    3  26    3  26    3  66    3  67 ff f  67 ff f ,
 e7 ff f  e6    3  c6    3  c6    3  c6    3  c6    3 ,
 86    3   6    3                          ,

I_CIRCUMFLEX_CAPITAL=I BAK SSO 5E CSS
I_DIAERESIS_CAPITAL=1B 2A 28 24   ,
                                 ,
        4       e       e6    3  e6    3  e6    3 ,
 e6    3  46    3   6    3   6    3   7 ff f   7 ff f ,
  7 ff f   6    3   6    3   6    3   6    3  46    3 ,
 e6    3  e6    3  e       e       4              ,

VERTICAL_LINE_BROKEN=1B 2A 28 24   ,
                                       ,
                                       ,
                              7f e1 ff 7f e1 ff,
 7f e1 ff                                    ,
                                       ,

I_GRAVE_CAPITAL=I BAK SSO 6  CSS
O_ACUTE_CAPITAL=1B 2A 28 24   ,
                                    3e   ,
    7f       ff 8     e3 8   1 81 c   1 8  c   3    6 ,
  3    6   2    2  26    3  26    3  24    1  24    1 ,
 64    1  64    1  64    1  e4    1  e4    1  c6    3 ,
 c6    3  c2    2  c3    6  83    6   1 8  c    1 c1 c ,
    e3 8     ff 8     7f       3e
SHARP_S_SMALL=E1
O_CIRCUMFLEX_CAPITAL=O BAK SSO 5E CSS
O_GRAVE_CAPITAL=O BAK SSO 6  CSS
O_TILDE_SMALL=o BAK 7E
O_TILDE_CAPITAL=O BAK SSO 7E CSS
MICRO_SYMBOL=E6
THORN_ICELANDIC_SMALL=1B 2A 28 24   ,
                           1 2      1 2      1,
 2      1 2      1 3f ff ff 3f ff ff 3f ff ff 3f ff ff,
 3f ff ff    81  1  1 81 81  1 81 81  1    81  3    c1,
  3    c1  2    41  2    41  2    4   2    4   2    4 ,
  2    4   2    4   3    c   3    c   1    8   1 81 8 ,
```

```
 1 81 8    ff     ff     7e     3c
THORN_ICELANDIC_CAPITAL=1B 2A 28 24  ,
                    1  8   1  8   1 ,
 8   1  8   1  f ff f  f ff f  f ff f  f ff f ,
 f ff f   84 1  1 86 1  1 86 1  1  2 1  3  3 1 ,
 3  3 1  2  1 1  2  1 1  2  1   2  1   2  1  ,
 2  1   2  1   3  3   3  3   1  2   1 86  ,
 1 86     fc     fc     78     3
U_ACUTE_CAPITAL=1B 2A 28 24  ,
            6      6      6      6     ,
 7 ff 8  7 ff c  7 ff c  7 ff c  6   e  6   6 ,
 6   2 26   2 26   3 2   3 2   3 6   3 ,
6   3 6   3 e   3 e   3 c6  3 c6   2 ,
c6   2 c6   6 86   e  7 ff c  7 ff c  7 ff c ,
 7 ff 8  6      6      6      6
U_CIRCUMFLEX_CAPITAL=U BAK SSO 5E CSS
U_GRAVE_CAPITAL=U BAK SSO 6  CSS
Y_ACUTE_SMALL=1B 2A 28 24  ,
                 1 8    1 8    1 8   1,
 1 8   1  1 c   1  1 e   1  1 e   1  1 f   3  1 b8  7,
 1 98  7  1 9c  f  1 8e 1f  8  6 19  8  7 39  8  3 f1,
 8  1 e  18  1 e  18  1 c  18  1 8  38  3 8  38  7  ,
 3  6   31 8e   31 9c   31 98   21 b8    1 f   ,
 1 e    1 e    1 c    1 8    1 8    1 8
Y_ACUTE_CAPITAL=1B 2A 28 24  ,
             4      4      4      4     ,
 6      7      7 8    7 c    5 c    4 e  1 ,
 4 7  1  24 38 1  2  38 1  2  1c 1  2  f f  6  7 f ,
 6  7 f  6  f f  e  1c 1  e  38 1  c4 38 1  c4 7  1 ,
 c4 e  1  c5 c    87 c    7 8    7      6     ,
 4      4      4      4
OVERLINE=1B 2A 28 24  ,
 6      6      6      6      6      6     ,
 6      6      6      6      6      6     ,
 6      6      6      6      6      6     ,
 6      6      6      6      6      6     ,
 6      6      6      6      6      6     ,
 6      6      6      6      6      6
ACUTE_ACCENT=1B 2A 28 24  ,
                                    ,
                                    ,
        8      8      8      8     18    ,
 18     18     38     38     3      3     ,
 3      3      2                          ,

SYLLABLE_HYPHEN=SSO 2D CSS
PLUS_OR_MINUS_SIGN=F1
THREE_QUARTERS=1B 2A 28 24  ,
                  3  62   3  62   2  32  ,
 4  12   4  16   4  14   42 14   42 14   42 1c  ,
 67 38   25 28   3d e8   18 d8 2   1  6   1  6 ,
   1  e   31 a   21 a   23 2   26 2   66 2 ,
   4c 2   48 2   5  2   df fc   9f fc   9f fc,
   8  2  1 8  2  1   2  1   2  1
PARAGRAPH_SYMBOL=1B 2A 28 24  ,
             3 c    7 e    f f    f f   ,
 f f    1f f8   1f f8   1f f8   1f f8  1 1f f8  1,
 3f fc  1 3f fc  1 3f fc  1 3f fc  1 3f fc  1 3f ff ff,
 3f ff ff 37 ff ff 3    1 3      3      3     ,
 3f ff ff 3f ff ff 3f ff ff 2    1 2    1 2    1,
 2    1 2    1 2    1 2    1      1
SECTION_SYMBOL=1B 2A 28 24  ,
                          6      e   ,
   f  7   1 9  78  7 1  78  f 18 18  f 88 18 19 88 18,
 18 88 18 18 cc 18 18 44 18 18 44 18 18 46 18 18 62 18,
 18 22 18 18 22 18 18 33 18 18 11 18 18 11 18 18 11 9 ,
 18 18 f  1e  8 f  1e  9 e   e  f      7      6  ,

DIVIDE_SIGN=F6
CEDILLA=1B 2A 28 24  ,
                                    ,
                       2      2      3,
```

```
      3      3      1      1      21      31,
     31     31     19      b      f       e,
      6      6                            ,

DEGREE_SYMBOL=F8
DIAERESIS=1B 2A 28 24   ,
                                  ,
       1      38     38     38     38     ,
 38     1                              ,
                                  1     ,
 38     38     38     38     1            ,

MIDDLE_DOT_ACCENT=FA
ONE_SUPERSCRIPT=SSO 1 CSS
THREE_SUPERSCRIPT=SSO 3 CSS
TWO_SUPERSCRIPT=SSO 2 CSS
REQUIRED_SPACE=SPA

/                                                  /
/                    Internal Data Area.                                  /
/  Do not change these statement.                                       /
/                                                  /
PRINTER_ID=FF FF
TOP_MARGIN=
LEFT_MARGIN=
/                                                  /
/                              End of Definition File                   /
/                                                  /
```

Field Names of Printer Definition Files

The following table lists the field names of the printer definition files (PDF files) and their meanings:

Table 14-1 (Page 1 of 5). Field Names of PDF Files

Field Name	Meaning	Remarks
MAXIMUM_PAGE_LENGTH	Default MPL	
MAXIMUM_PRINT_POSITION	Default MPP	
DEFAULT_CPI?	Default CPI	
DEFAULT_LPI?	Default LPI	
COMPRESS_LINE_SPACING?	Specifies whether to print a line containing only space characters or nonprint characters.	
FORM_FEED_ANY_POSITION?	Specifies whether to validate the FF control code on the first line.	Do not change this field.
OVERRIDE_FORMATTED_PRINT?	Specifies whether to print NULL characters as blanks.	Do not change this field.
HORIZONTAL_PEL	FORWARD_HORIZONTAL_SKIP length unit	
VERTICAL_PEL	FORWARD_VERTICAL_SKIP length unit	
IMAGE_HORIZONTAL_PEL	IMAGE_TRANSMISSION horizontal length unit	
IMAGE_VERTICAL_PEL	IMAGE_TRANSMISSION vertical length unit	
LINE_SPACING_RATIO	SET_VARIABLE_LINE_DENSITY length unit	
PAGE_LENGTH_TYPE?	SET_PAGE _LENGTH page length parameter type	
FIRST_LEFT_POSITION	Distance from left paper edge	
FIRST_TOP_POSITION	Distance from top paper edge	
DRAWER1_ORIENTATION	Default page orientation for drawer 1	
DRAWER2_ORIENTATION	Default page orientation for drawer 2	
AUTOMATIC_ORIENTATION	Specifies whether to calculate the page orientation.	
START_JOB	Printer control code sent to a printer to start printing	If the control code specifying LPI/CPI is defined, also change DEFAULT_CPI, DEFAULT_LPI.
END_JOB	Printer control code sent to a printer when printing ends	
BACKSPACE	Backspace control code	
BEL	Bell control code	
CARRIAGE_RETURN	Carriage return control code	
NEW_LINE	New line (CR/LF) control code	
LINE_FEED	New line control code	
FORM_FEED	Form feed (FF) control code	
HORIZONTAL_TAB	Horizontal tab control code	
VERTICAL_TAB	Vertical tab control code	
DESELECT	Device control 3 control code	
START_SUBSCRIPT	Subscript character specification	
END_SUBSCRIPT	Subscript character specification release	
START_SUPERSCRIPT	Superscript character specification	
END_SUPERSCRIPT	Superscript character specification release	

Table 14-1 (Page 2 of 5). Field Names of PDF Files

Field Name	Meaning	Remarks
DUP	Character used for printing DUP codes	
FIELD_MARK	Character used for printing FIELD MARK characters	
SET_HORIZONTAL_TABS	Horizontal tab setup	Do not change this field.
SET_VERTICAL_TABS	Vertical tab setup	Do not change this field.
SET_HORIZONTAL_MARGINS	Right and left margin setup	Do not change this field.
SET_PAGE_LENGTH	Page length setup	Assign the unit used for the defined control code page length to the PAGE_LENGTH_TYPE field. When single sheets are to be used, delete this field.
SET_VARIABLE_LINE_DENSITY	Line density setup	Assign the unit used for the control code length defined to LINE_SPACING_RATIO field.
SET_2_LINES_PER_INCH	New line pitch (2LPI) setup	
SET_3_LINES_PER_INCH	New line pitch (3LPI) setup	
SET_4_LINES_PER_INCH	New line pitch (4LPI) setup	
SET_6_LINES_PER_INCH	New line pitch (6LPI) setup	
SET_8_LINES_PER_INCH	New line pitch (8LPI) setup	
SET_10_LINES_PER_INCH	New line pitch (10LPI) setup	
SET_10_CHARACTERS_PER_INCH	Character pitch (10CPI) setup	
SET_12_CHARACTERS_PER_INCH	Character pitch (12CPI) setup	
SET_13_CHARACTERS_PER_INCH	Character pitch (13CPI) setup	
SET_15_CHARACTERS_PER_INCH	Character pitch (15CPI) setup	
SET_17_CHARACTERS_PER_INCH	Character pitch (17CPI) setup	
SET_20_CHARACTERS_PER_INCH	Character pitch (20CPI) setup	
IMAGE_TRANSMISSION	Image data setup (vertical 24-dot image)	
SELECT_DRAWER1	Page tray (Primary) setup	
SELECT_DRAWER2	Page tray (Alternate) setup	
SELECT_ENVELOPE	Envelope tray setup	
SELECT_DRAFT_QUALITY	Draft print quality setup	
SELECT_LETTER_QUALITY	Letter print quality setup	
SELECT_ENHANCED_QUALITY	Enhanced print quality setup	
SET_DUPLEX	Duplex printing setup	
SET_DUPLEX_TUMBLE	Duplex (tumble) printing setup	
RESET_DUPLEX	Duplex printing release	
SET_PORTRAIT_ORIENT	Page orientation (Normal portrait (upright)) setup	
SET_LANDSCAPELEFT_ORIENT	Page orientation (Landscape left (270 degree clockwise rotation of text)) setup	
SET_PORTRAITUPDWN_ORIENT	Page orientation (Portrait upside down (180 degree clockwise rotation of text)) setup	
SET_LANDSCAPERGHT_ORIENT	Page orientation (Landscape right (90 degree clockwise rotation of text)) setup	

Table 14-1 (Page 3 of 5). Field Names of PDF Files

Field Name	Meaning	Remarks
FORWARD_HORIZONTAL_SKIP	Variable skip (relative position/dot unit)	Assign the unit of the defined control code length to the HORIZONTAL_PEL field.
FORWARD_VERTICAL_STEP_FEED	Variable line feed (relative position/dot unit)	Assign the unit of the defined control code length to the VERTICAL_PEL field.
SET_FONT_GLOBAL	Global font ID setup	Do not change this field.
SET_GFID_0003	GFID 3 (OCR-B) setup	
SET_GFID_0005	GFID 5 (Orator) setup	
SET_GFID_0011	GFID 11 (Courier 10) setup	
SET_GFID_0012	GFID 12 (Prestige Pica) setup	
SET_GFID_0013	GFID 13 (Artisan 10) setup	
SET_GFID_0018	GFID 18 (Courier Italic 10) setup	
SET_GFID_0019	GFID 19 (OCR-A) setup	
SET_GFID_0020	GFID 20 (Pica) setup	
SET_GFID_0030	GFID 30 (Math Symbol 10) setup	
SET_GFID_0038	GFID 38 (Orator Bold) setup	
SET_GFID_0039	GFID 39 (Gothic Bold 10) setup	
SET_GFID_0040	GFID 40 (Gothic Text 10) setup	
SET_GFID_0041	GFID 41 (Roman Text 10) setup	
SET_GFID_0042	GFID 42 (Serif Text 10) setup	
SET_GFID_0043	GFID 43 (Serif Italic 10) setup	
SET_GFID_0044	GFID 44 (Katakana 10) setup	
SET_GFID_0045	GFID 45 (APL 10) setup	
SET_GFID_0046	GFID 46 (Courier Bold 10) setup	
SET_GFID_0050	GFID 50 (Shalom 10) setup	
SET_GFID_0066	GFID 66 (Gothic Text 12) setup	
SET_GFID_0068	GFID 68 (Gothic Italic 12) setup	
SET_GFID_0069	GFID 69 (Gothic Bold 12) setup	
SET_GFID_0070	GFID 70 (Serif Text 12) setup	
SET_GFID_0071	GFID 71 (Serif Italic 12) setup	
SET_GFID_0072	GFID 72 (Serif Bold 12) setup	
SET_GFID_0080	GFID 80 (Math Symbol 12) setup	
SET_GFID_0084	GFID 84 (Script 12) setup	
SET_GFID_0085	GFID 85 (Courier 12) setup	
SET_GFID_0086	GFID 86 (Prestige Elite) setup	
SET_GFID_0087	GFID 87 (Letter Gothic 12) setup	
SET_GFID_0091	GFID 91 (Light Italic 12) setup	
SET_GFID_0110	GFID 110 (Letter Gothic Bold 12) setup	
SET_GFID_0111	GFID 111 (Prestige Elite Bold) setup	
SET_GFID_0112	GFID 112 (Prestige Elite Italic) setup	
SET_GFID_0115	GFID 115 (Math Symbol 12) setup	
SET_GFID_0155	GFID 155 (Boldface Italic) setup	
SET_GFID_0158	GFID 158 (Modern) setup	

Table 14-1 (Page 4 of 5). Field Names of PDF Files

Field Name	Meaning	Remarks
SET_GFID_0159	GFID 159 (Boldface) setup	
SET_GFID_0160	GFID 160 (Essay) setup	
SET_GFID_0162	GFID 162 (Essay Italic) setup	
SET_GFID_0163	GFID 163 (Essay Bold) setup	
SET_GFID_0168	GFID 168 (Barak PSM) setup	
SET_GFID_0173	GFID 173 (Essay Light) setup	
SET_GFID_0175	GFID 175 (Document) setup	
SET_GFID_0176	GFID 176 (Boldface) setup	
SET_GFID_0177	GFID 177 (Boldface Italic) setup	
SET_GFID_0193	GFID 193 (Math Symbol 12) setup	
SET_GFID_0198	GFID 198 (Math Symbol 10) setup	
SET_GFID_0204	GFID 204 (Gothic Text 13) setup	
SET_GFID_0221	GFID 221 (Prestige 15) setup	
SET_GFID_0222	GFID 222 (Gothic Text 15) setup	
SET_GFID_0223	GFID 223 (Courier 15) setup	
SET_GFID_0225	GFID 225 (Math Symbol 15) setup	
SET_GFID_0229	GFID 229 (Serif Text 15) setup	
SET_GFID_0230	GFID 230 (Gothic Text 15) setup	
SET_GFID_0245	GFID 245 (Courier Bold 5) setup	
SET_GFID_0252	GFID 252 (Courier 17) setup	
SET_GFID_0253	GFID 253 (Courier Bold 17) setup	
SET_GFID_0254	GFID 254 (Courier 17 (sub/super)) setup	
SET_GFID_0280	GFID 280 (APL 20) setup	
SET_GFID_0281	GFID 281 (Gothic Text 20) setup	
SET_GFID_0290	GFID 290 (Gothic Text 27) setup	
SET_GFID_0751	GFID 751 (Sonoran-Serif 8-pt Roman Medium) setup	
SET_GFID_1051	GFID 1051 (Sonoran-Serif 10-pt Roman Medium) setup	
SET_GFID_1053	GFID 1053 (Sonoran-Serif 10-pt Roman Bold) setup	
SET_GFID_1056	GFID 1056 (Sonoran-Serif 10-pt Italic Medium) setup	
SET_GFID_1351	GFID 1351 (Sonoran-Serif 12-pt Roman Medium) setup	
SET_GFID_1653	GFID 1653 (Sonoran-Serif 16-pt Roman Bold) setup	
SET_GFID_2103	GFID 2103 (Sonoran-Serif 24-pt Roman Bold) setup	
START_HIGHLIGHT_INTENSE	Highlight printing setup	
END_HIGHLIGHT_INTENSE	Highlight printing release	
START_HIGHLIGHT_UNDERLINE	Underline setup	
END_HIGHLIGHT_UNDERLINE	Underline release	
TOP_MARGIN	Default top margin	Do not change this field.
LEFT_MARGIN	Default left margin	Do not change this field.

Table 14-1 (Page 5 of 5). Field Names of PDF Files

Field Name	Meaning	Remarks
DYNAMIC_START_JOB	Printer control code sent to a printer to start printing (internal use)	Do not change this field.
DYNAMIC_END_JOB	Printer control code sent to a printer to stop printing (internal use)	Do not change this field.
DYNAMIC_SET_PAGE_LENGTH	Page length setup control code sent to a printer at the start of printing (internal use)	Do not change this field.
PRINTER_ID	Printer ID	Do not change this field.

The following table lists the session parameter field names and their effective values:

Table 14-2. Effective Values for PDF File Field Names

Field Name	Effective Value
MAXIMUM_PAGE_LENGTH	001 to 255
MAXIMUM_PRINT_POSITION	001 to 255
DEFAULT_CPI?	010/012/015
DEFAULT_LPI?	004/006/008
COMPRESS_LINE_SPACING?	YES/NO
FORM_FEED_ANY_POSITION?	YES/NO
OVERRIDE_FORMATTED_PRINT?	YES/NO
HORIZONTAL_PEL	FORWARD_HORIZONTAL_SKIP length unit
VERTICAL_PEL	FORWARD_VERTICAL_ STEP_FEED length unit
IMAGE_HORIZONTAL_PEL	IMAGE_TRANSMISSION horizontal unit
IMAGE_VERTICAL_PEL	IMAGE_TRANSMISSION vertical unit
LINE_SPACING_RATIO	SET_VARIABLE_LINE_DENSITY length unit
PAGE_LENGTH_TYPE?	LINE/INCH/6INCH*
FIRST_LEFT_POSITION	000 to 1440 in units of 1/1440 inch
FIRST_TOP_POSITION	000 to 1440 in units of 1/1440 inch
DRAWER1_ORIENTATION	LANDSCAPE/PORTRAIT/COR
DRAWER2_ORIENTATION	LANDSCAPE/PORTRAIT/COR
AUTOMATIC_ORIENTATION	YES/NO

* 6INCH indicates that page length should be specified in units of 1/6 inch.

Notes:

1. If one of the desired CPI/LPI settings is not exactly supported by the printer, set the nearest value. The results of printing might not be as desired.
2. If the units used to specify the control code length defined in FORWARD_HORIZONTAL _SKIP and FORWARD_VERTICAL _STEP_FEED are not the same as the units used to specify the HORIZONTAL_PEL and VERTICAL_PEL, the desired output will not be obtained.
3. If the units used to specify the control code length defined in SET_VARIABLE_LINE_DENSITY are not the same as the units used to specify the LINE_SPACING_RATIO, the desired output will not be obtained.
4. When FIRST_LEFT_POSITION and FIRST_TOP_POSITION are specified, their values are regarded as specifying the unprintable area in the page of the

printer. These values are included in the top margin and the left margin specified by the AS/400 printer control code.

Parameter Definition of Printer Control Codes

This section explains how to define the parameters, if any, of the printer control codes. Some printer control codes require that parameters be specified. Pay particular attention when defining a parameter because how this is done depends on the parameter type. If the definition method for another type is used, the desired output will not be obtained.

The following table lists printer control code parameters and their meanings:

Table 14-3. Printer Control Code Parameters

Parameter Type	Meaning
byte-value	One-byte parameter.
byte-values	Multibyte parameter. Used if operands are fixed.
word-value(HL)	One-word parameter (higher and lower bytes).
word-value(LH)	One-word parameter (lower and higher bytes).
length(HL)-values	Multibyte parameter requiring operands. An operand consists of a higher and lower byte. Used if operands are variable.
length(LH)-values	Multibyte parameter requiring operands. An operand consists of a lower and higher byte. Used if operands are variable.
length(HL)-images	Image data requiring operands. An operand consists of a higher and lower byte.
length(LH)-images	Image data requiring operands. An operand consists of a lower and higher byte.
decimal-characters	Decimal characters parameter.

Symbols of Printer Definition Files

The following table lists the symbols that are defined for printer definition files.

Table 14-4 (Page 1 of 3). Printer Symbol Definitions

Field Name	Symbol
SPACE	
EXCLAMATION_POINT	!
QUOTATION_MARKS	"
NUMBER_SIGN	#
DOLLAR_SIGN	$
PERCENT_SIGN	%
AMPERSAND	&
APOSTROPHE	'
LEFT_PARENTHESIS	(
RIGHT_PARENTHESIS	)
ASTERISK	*
PLUS_SIGN	+
COMMA	,

Table 14-4 (Page 1 of 3). Printer Symbol Definitions

Field Name	Symbol
HYPHEN	-
PERIOD	.
SLASH	/
ZERO	0
ONE	1
TWO	2
THREE	3
FOUR	4
FIVE	5
SIX	6
SEVEN	7
EIGHT	8
NINE	9

Table 14-4 (Page 2 of 3). Printer Symbol Definitions

Field Name	Symbol
COLON	:
SEMICOLON	;
LESS_THAN_SIGN	<
EQUAL_SIGN	=
GREATER_THAN_SIGN	>
QUESTION_MARK	?
AT_SIGN	@
A_CAPITAL	A
B_CAPITAL	B
C_CAPITAL	C
D_CAPITAL	D
E_CAPITAL	E
F_CAPITAL	F
G_CAPITAL	G
H_CAPITAL	H
I_CAPITAL	I
J_CAPITAL	J
K_CAPITAL	K
L_CAPITAL	L
M_CAPITAL	M
N_CAPITAL	N
O_CAPITAL	O
P_CAPITAL	P
Q_CAPITAL	Q
R_CAPITAL	R
S_CAPITAL	S
T_CAPITAL	T
U_CAPITAL	U
V_CAPITAL	V
W_CAPITAL	W
X_CAPITAL	X
Y_CAPITAL	Y
Z_CAPITAL	Z
LEFT_BRACKET	[
BACKSLASH	\
RIGHT_BRACKET	]
CIRCUMFLEX_ACCENT	^
UNDERLINE	_
GRAVE_ACCENT	`
A_SMALL	a
B_SMALL	b
C_SMALL	c
D_SMALL	d

Table 14-4 (Page 2 of 3). Printer Symbol Definitions

Field Name	Symbol
E_SMALL	e
F_SMALL	f
G_SMALL	g
H_SMALL	h
I_SMALL	i
J_SMALL	j
K_SMALL	k
L_SMALL	l
M_SMALL	m
N_SMALL	n
O_SMALL	o
P_SMALL	p
Q_SMALL	q
R_SMALL	r
S_SMALL	s
T_SMALL	t
U_SMALL	u
V_SMALL	v
W_SMALL	w
X_SMALL	x
Y_SMALL	y
Z_SMALL	z
LEFT_BRACE	{
VERTICAL_BAR	|
RIGHT_BRACE	}
TILDE_ACCENT	~
C_CEDILLA_CAPITAL	Ç
U_DIAERESIS_SMALL	ü
E_ACUTE_SMALL	é
A_CIRCUMFLEX_SMALL	â
A_DIAERESIS_SMALL	ä
A_GRAVE_SMALL	à
A_OVERCIRCLE_SMALL	å
C_CEDILLA_SMALL	ç
E_CIRCUMFLEX_SMALL	ê
E_DIAERESIS_SMALL	ë
E_GRAVE_SMALL	è
I_DIAERESIS_SMALL	ï
I_CIRCUMFLEX_SMALL	î
I_GRAVE_SMALL	ì
A_DIAERESIS_CAPITAL	Ä
A_OVERCIRCLE_CAPITAL	Å
E_ACUTE_CAPITAL	É

Table 14-4 (Page 3 of 3). Printer Symbol Definitions

Field Name	Symbol
AE_DIPTHONG_SMALL	æ
AE_DIPTHONG_CAPITAL	Æ
O_CIRCUMFLEX_SMALL	ô
O_DIAERESIS_SMALL	ö
O_GRAVE_SMALL	ò
U_CIRCUMFLEX_SMALL	û
U_GRAVE_SMALL	ù
Y_DIAERESIS_SMALL	ÿ
O_DIAERESIS_CAPITAL	Ö
U_DIAERESIS_CAPITAL	Ü
O_SLASH_SMALL	ø
POUND_SIGN	£
O_SLASH_CAPITAL	Ø
MULTIPLY_SIGN	×
A_ACUTE_SMALL	á
I_ACUTE_SMALL	í
O_ACUTE_SMALL	ó
U_ACUTE_SMALL	ú
N_TILDE_SMALL	ñ
N_TILDE_CAPITAL	Ñ
ORDINAL_INDICATOR_FEMININE	a
ORDINAL_INDICATOR_MASCULINE	o
QUESTION_MARK_INVERTED	¿
REGISTERED_TRADEMARK_SYMBOL	®
LOGICAL_NOT	¬
ONE_HALF	½
ONE_QUARTER	¼
EXCLAMATION_POINT_INVERTED	¡
LEFT_ANGLE_QUOTES	«
RIGHT_ANGLE_QUOTES	»
A_ACUTE_CAPITAL	Á
A_CIRCUMFLEX_CAPITAL	Â
A_GRAVE_CAPITAL	À
COPYRIGHT_SYMBOL	©
CENT_SIGN	¢
YEN_SIGN	¥
A_TILDE_SMALL	ã
A_TILDE_CAPITAL	Ã
E_CIRCUMFLEX_CAPITAL	Ê
E_DIAERESIS_CAPITAL	Ë
I_ACUTE_CAPITAL	Í
I_CIRCUMFLEX_CAPITAL	Î
I_DIAERESIS_CAPITAL	Ï

Table 14-4 (Page 3 of 3). Printer Symbol Definitions

Field Name	Symbol
VERTICAL_LINE_BROKEN	¦
I_GRAVE_CAPITAL	Ì
O_ACUTE_CAPITAL	Ó
O_CIRCUMFLEX_CAPITAL	Ô
O_GRAVE_CAPITAL	Ò
O_TILDE_SMALL	õ
O_TILDE_CAPITAL	Õ
MICRO_SYMBOL	µ
U_ACUTE_CAPITAL	Ú
U_CIRCUMFLEX_CAPITAL	Û
U_GRAVE_CAPITAL	Ù
ACUTE_ACCENT	´
SYLLABLE_HYPHEN	-
PLUS_OR_MINUS_SIGN	±
THREE_QUARTERS	¾
PARAGRAPH_SYMBOL	¶
SECTION_SYMBOL	§
DIVIDE_SIGN	÷
DEGREE_SYMBOL	°
ONE_SUPERSCRIPT	
THREE_SUPERSCRIPT	
TWO_SUPERSCRIPT	
REQUIRED_SPACE	
INTERNATIONAL_CURRENCY_SYMBOL	¤
ETH_ICELANDIC_SMALL	ð
ETH_ICELANDIC_CAPITAL	Ð
SHARP_S_SMALL	ß
THORN_ICELANDIC_SMALL	þ
THORN_ICELANDIC_CAPITAL	Þ
Y_ACUTE_SMALL	ý
Y_ACUTE_CAPITAL	Ý
OVERLINE	¯
CEDILLA	¸
DIAERESIS	..
MIDDLE_DOT_ACCENT	.

Using Printer Control Codes

This section explains the SNA Character String (SCS) control codes, or Final Form Text: Document Content Architecture (FFT DCA).

For details of AS/400 printer control codes, see *AS/400 Guide to Programming for Printing*, SC41-8194.

Printer Control Code Format

Some printer control codes perform single, specific functions by themselves, while others perform multiple functions according to the parameters specified after the control code.

A printer control code with parameters has the following format:

Control Code	Count	Parameter 1	Parameter 2...
1 or 2 bytes	1 byte	1 or 2 bytes	1 or 2 bytes

Normally, a control code with parameters consists of 2 bytes. (Usually, a control code without parameters, that is, functioning as a unit, has only 1 byte.)

A count consists of 1 byte, and indicates the length of the parameters (including the count) after the control code, in bytes. For example, a count and two 1-byte parameters is shown as X'03', because the count itself is included. Some control codes, such as the Printing Position (PP) control code, do not have counts.

A parameter can be 1 or 2 bytes in length. The number of bytes depends on the control codes.

Note: In this manual, counts and parameters that are actually processed in binary are all expressed in hexadecimal (0–F) to improve readability.

Supported Control Codes

Control Code	3812	5219	5224	5256
Set CGCS Through Local ID (SCGL)	Yes	Yes	Yes	No
Set Character Distance (SCD)	Yes	Yes	Yes	No
Set FID Through GCID (SFG)	Yes	Yes	Yes	No
Set GCGID Through GCID (SCG)	Yes	Yes	Yes	No
Bell (BEL)	Yes	Yes	Yes	Yes
Null (NUL)	Yes	Yes	Yes	Yes
Repeat (RPT)	Yes	Yes	No	No
Set Error Action (SEA)	Yes	Yes	Yes	No
Set Initial Condition (SIC)	Yes	No	No	No
Set Print Setup (SPSU)	Yes	Yes	Yes	No
Switch (SW)	Yes	Yes	No	No

Control Code	3812	5219	5224	5256
Begin Emphasis (BES)	Yes	No	No	No
Begin Overstrike (BOS)	Yes	No	No	No
Begin Underscore (BUS)	Yes	Yes	No	No
Enable Presentation (ENP)	Yes	No	No	No
End Emphasis (EES)	Yes	No	No	No
End Overstrike (EOS)	Yes	No	No	No
End Underscore (EUS)	Yes	Yes	No	No
Inhibit Presentation (INP)	Yes	No	No	No
Set Graphic Error Action (SGEA)	Yes	Yes	Yes	Yes
Justify Text Field (JTF)	Yes	Yes	No	No
Set Justify Mode (SJM)	Yes	Yes	No	No
Subscript (SBS)	Yes	Yes	No	No
Substitute (SUB)	Yes	No	No	No
Superscript (SPS)	Yes	Yes	No	No
Word Underscore (WUS)	Yes	Yes	No	No
Form Feed (FF)	Yes	Yes	Yes	Yes
Page Presentation Media (PPM)	Yes	Yes	Yes	No
Required Form Feed (RFF)	Yes	Yes	No	No
Set Horizontal Format (SHF)	Yes	Yes	Yes	Yes
Set Horizontal Margins (SHM)	Yes	Yes	Yes	No
Set Presentation Page Size (SPPS)	Yes	Yes	Yes	No
Set Text Orientation (STO)	Yes	No	No	No
Set Vertical Format (SVF)	Yes	Yes	Yes	Yes
Set Vertical Margins (SVM)	Yes	Yes	Yes	No
Backspace (BS)	Yes	Yes	No	No
Carriage Return (CR)	Yes	Yes	Yes	Yes
Horizontal Tab (HT)	Yes	Yes	No	No
Indent Tab (IT)	Yes	Yes	No	No
Index Return (IRT)	Yes	Yes	No	No
Interchange Record Separator (IRS)	Yes	Yes	Yes	Yes
Line Feed (LF)	Yes	Yes	Yes	Yes
New Line (NL)	Yes	Yes	Yes	Yes
Numeric Backspace (NBS)	Yes	Yes	No	No

Control Code	3812	5219	5224	5256
Presentation Position (PP)	Yes	Yes	Yes	Yes
Release Left Margin (RLM)	Yes	Yes	Yes	No
Required New Line (RNL)	Yes	Yes	No	No
Set Horizontal Tab Stops (STAB)	Yes	Yes	Yes	No
Set Indent Level (SIL)	Yes	Yes	Yes	No
Set Line Density (SLD)	Yes	Yes	Yes	No
Set Line Spacing (SLS)	Yes	Yes	Yes	No
Set Single Line Distance (SSLD)	Yes	Yes	Yes	No
Unit Backspace (UBS)	Yes	Yes	No	No
Vertical Tab (VT)	Yes	No	No	No
ASCII Transparent (ATRN)	Yes	Yes	Yes	Yes

Table 14-5. Supported Control Codes

Printer Control Codes

Table 14-6 (Page 1 of 4). Printer Control Codes

Control Code	Abbreviation	Hexadecimal Code	Function
		Character Set Control	
Set CGCS[1] Through Local ID	SCGL	2BD1nn81xx	Specifies the code page through a local ID.
Set Character Distance	SCD	2BD2nn29xxxx	Selects the pitch and font.
Set Font ID Through GFID[2]	SFG	2BD1nn05xxxxyyyyzz	Selects the font.
Set GCSGID[3] Through GCID[4]	SCG	2BD1nn01xxxxyyyy	Specifies the code page.
		Device Control	
Bell	BEL	2F	Ignored.
Null	NUL	00	Ignored.
Repeat	RPT	0A	Ignored.
Set Exception Action	SEA	2BD2nn85p1–pn	Specifies the explicit action.
Set Initial Conditions	SIC	2BD2nn45xx	Sets the environment of the EBCDIC transform.
Set Print Setup	SPSU	2BD2nn4Cp1–pn	Ignored.
Switch	SW	2A	Ignored.

Legend:
nn: Count
fp: Function parameter
ee, gg, hh, il–ix, mm, nn, p1–pn, ss, t1–tn, uu, vv, ww, xx, yy, zz: Numeric parameter

Table 14-6 (Page 2 of 4). Printer Control Codes

Control Code	Abbreviation	Hexadecimal Code	Function
Generation Control			
Begin Emphasis	BES	2BD1nn8Axx	Begins emphasis.
Begin Overstrike	BOS	2BD4nn72wwxxyyyyzzzz	Begins overstriking.
Begin Underscore	BUS	2BD4nn0Axxyy	Begins underscoring.
Enable Presentation	ENP	14	Ignored.
End Emphasis	EES	2BD1nn8Exx	Ends emphasis.
End Overstrike	EOS	2BD4nn76	Ends overstriking.
End Underscore	EUS	2BD4nn0E	Ends underscoring.
Inhibit Presentation	INP	24	Ignored.
Justify Text Field	JTF	2BD2nn03xxxxyy	Justifies the following text.
Set Graphic Error Action	SGEA	2BC8nnxxyy	Specifies how to process a received unprintable character font.
Set Justify Mode	SJM	2BD2nn0Dxxyy	Justifies each line of text between the left and right margins.
Subscript	SBS	38	Subscript.
Substitute	SUB	3F	Synonym for the graphic exception character.
Superscript	SPS	09	Superscript.
Word Underscore	WUS	23	Underscore the entire word immediately preceding the control.
Print Format Control			
Form Feed	FF	0C	Moves the printing position to the next page.
Page Presentation Media	PPM	2BD2nn48ssssuuvv wwxxyyzz	Specifies the forms setting, the source drawer, the quality, and the duplex function.
Required Form Feed	RFF	3A	Moves the printing position to the next page and restores the indent level to the left margin.
Set Horizontal Format	SHF	2BC1nnxxyyzzt1–tn	Specifies the maximum print position, the left and right margins, and the horizontal tab stops in units of 1 character.
Set Horizontal Margins	SHM	2BD2nn11xxxxyyyy	Sets the left and right margins in units of 1/1440 inch.
Set Presentation Page Size	SPPS	2BD2nn40xxxxyyyy	Specifies the presentation surface width and depth.
Set Text Orientation	STO	2BD3nnF6xxxxyyyy	Specifies the page rotation.

Legend:
nn: Count
fp: Function parameter
ee, gg, hh, il–ix, mm, nn, p1–pn, ss, t1–tn, uu, vv, ww, xx, yy, zz: Numeric parameter

Table 14-6 (Page 3 of 4). Printer Control Codes

Control Code	Abbreviation	Hexadecimal Code	Function
Set Vertical Format	SVF	2BC2nnxxyyzzt1–tn	Specifies the maximum print line, the top and bottom margins, and the vertical tab stops in units of 1 character.
Set Vertical Margins	SVM	2BD2nn49xxxxyyyy	Sets the top and bottom margins in units of 1/1440 inch.
Printing Position Control			
Backspace	BS	16	Moves the printing position to the left one font width.
Carriage Return	CR	0D	Moves the printing position to the left margin.
Horizontal Tab	HT	05	Moves the printing position right to the next tab stop.
Indent Tab	IT	39	Moves the printing position right to the next tab stops and sets the indent level one tab stop further to the right.
Index Return	IRT	33	Synonym for “Required New Line.”
Interchange Record Separator	IRS	1E	Synonym for “New Line.”
Line Feed	LF	25	Moves the printing position one line vertically.
New Line	NL	15	Moves the printing position to the left margin of the next line.
Numeric Backspace	NBS	36	Synonym for “Backspace.”
Presentation Position	PP	34fpxx	Moves the printing position.
Release Left Margin	RLM	2BD2nn0B	Ignored.
Required New Line	RNL	06	Moves the printing position to the left margin of the next line and resets any pending indent level.
Set Horizontal Tab Stops	STAB	2BD2nn01xxt1–tn	Specifies the tab stops.
Set Indent Level	SIL	2BD2nn07xx	Sets the indent level to the specific tab stop.
Set Line Density	SLD	2BC6nnxx	Specifies the line pitch in units of 1/72 inch.
Set Line Spacing	SLS	2BD2nn09xx	Specifies the number of lines spaced by a new line control.
Set Single Line Distance	SSLD	2BD2nn15xxxx	Specifies the line pitch in units of 1/1440 inch.
Unit Backspace	UBS	1A	Move the printing position 1/60 inch to the left.

Legend:
nn: Count
fp: Function parameter
ee, gg, hh, il–ix, mm, nn, p1–pn, ss, t1–tn, uu, vv, ww, xx, yy, zz: Numeric parameter

Table 14-6 (Page 4 of 4). Printer Control Codes

Control Code	Abbreviation	Hexadecimal Code	Function
Vertical Tab	VT	0B	Moves the printing position down to the next tab stop.
		Transparent Control	
ASCII Transparent	ATRN	03	Enables the printing of an ASCII data stream.

Note:

1 Coded Graphic Character Set
2 Global Font ID
3 Graphic Character Set Global Identifier
4 Graphic Character set ID

Legend:
nn: Count
fp: Function parameter
ee, gg, hh, il–ix, mm, nn, p1–pn, ss, t1–tn, uu, vv, ww, xx, yy, zz: Numeric parameter

Programming Notes

This section briefly explains how a printer reacts if a partial control code is received, or if an incomplete control code is sent.

If the transmission of a control code is interrupted, the printer waits for the remaining part of the code. If the data stream (the series of data units and control codes) sent after the interruption is consistent with the data stream sent before the interruption, (that is, if one complete printer control code is restored by chaining), the control code is processed as is.

If the two parts of the data stream are inconsistent, an error occurs. A negative response to an "Invalid Printer Parameter" is sent to the host system, or treated as a no-op (no operation: ignored because of a meaningless code).
The main point to note here is that detailed information is not sent to the host system if an error occurs in a control code. After programming, the data stream must be checked thoroughly by repeating the printing test.

Restrictions and Notes for AS/400 Printer Commands and Printer Setup

This section provides supplementary notes and explains restrictions for printing.

Printer Control Codes

<table>
<tr><th>Printer Control Code</th><th>If Use PDT file is Selected:</th><th>If a Windows Printer Driver is Used:</th></tr>
<tr><td>Set the Character Density (SCD)</td><td colspan="2">The GFID is selected for the valid character distance (CD) parameter as follows:

CD parameter | Character Pitch | GFID value
000A | 10 CPI | 11
000B | Proportional spacing | 175
000C | 12 CPI | 86
000F | 15 CPI | 230
00FF | 10 CPI | 12</td></tr>
<tr><td></td><td>If the specified font is not supported, a substitution is provided. For example, when 15 CPI font is specified but the font is not supported, the supported 17 CPI font is substituted.</td><td>See "How to Determine Font" on page 14-37.</td></tr>
</table>

<table>
<tr><th>Printer Control Code</th><th>If Use PDT file is Selected:</th><th>If a Windows Printer Driver is Used:</th></tr>
<tr><td>Set Font ID through GFID (SFG)</td><td colspan="2">Recognizable GFIDs are restricted. (See “Field Names of Printer Definition Files” on page 14-21.)
If the specified GFID is not supported and it is out of the range from 154 through 200, the closest font width of the following fonts is substituted:

Font Name — GFID value
Courier Bold 5 — 245
Courier 10 — 11
Prestige Elite 12 — 86
Gothic-text 13 — 204
Gothic-text 15 — 230
Courier 17 — 252
Gothic-text 20 — 281
Gothic-text 27 — 290

If the specified GFID is not supported and it is between 154 and 200, the following font is substituted:

Font Name — GFID value
Document — 175</td></tr>
<tr><td></td><td></td><td>See “How to Determine Font” on page 14-37.</td></tr>
<tr><td>Begin Underscore (BUS)</td><td></td><td>The selected font might not support the underscore.</td></tr>
<tr><td>Begin Emphasis (BES)</td><td></td><td>The selected font might not support the emphasis.</td></tr>
<tr><td>Set Text Orientation (STO)</td><td></td><td>The page orientation can be changed to portrait or landscape. The direction, which is up, down, left, or right on the paper, depends on the Microsoft Windows** printer driver. If the page orientation is changed, the current paper is ejected.</td></tr>
<tr><td>Page Presentation Media (PPM)</td><td colspan="2">The following parameters are supported.

Forms Control (FC)
Source Drawer (SD)
Quality (Q)
Duplex (DX)

Other parameters are ignored.

Quality (Q) has the following meaning with the original meaning of the print quality:

0: Do not change the quality setting.
1: Allow COR mode. This is the default.
2–3: Do not allow COR mode.</td></tr>
</table>

When you use the Windows printer driver, the printer job is seldom canceled during printing. In this case, you must activate the Windows print manager, or select **Use PDT file** before you execute the print job.

How to Determine Font

This section explains how PC400 determines a font when the Microsoft Windows printer driver is used.

If the specified font is available on your printer, it is selected. However, if it is not available, PC400 selects a font out of the available ones on your printer by checking the font attributes in the following order.

1. Typeface name
2. Character set
3. Fixed pitch font
4. Character width. If the specified font is a scalable one, the character width is not checked. If no available font has the same character width as the specified one, PC400 selects the font with the closest width.
5. Font family
6. Italic font
7. Bold font

PFT Migration Utility

The PFT migration utility converts the printer function table (PFT) for the PC Support/400 workstation feature to a printer definition file (PDF) for PC400.

This section describes the operator interface of the PFT migration utility.

For details of PFT, see *AS/400 PC Support: DOS and OS/2 Technical Reference*, SC21-8091.

How to Use the PFT Migration Utility

The file name of the PFT migration utility program is **PCSPFC.EXE**. It is a Windows application, and you can execute it by:

Double-clicking the program name on the File Manager list box.

Displaying the program icon of the PFT migration utility and double-clicking the icon.

Specifying the program name (and parameters) on the Run dialog box of Program Manager as follows:

```
PCSPFC [ [drive:] [path] PFT-file-name[.extension] ]
```

If no parameter is specified, PCSPFC.EXE displays the Convert PFT to PDF dialog box.

If you omit a drive name and a directory name, PCSPFC.EXE uses the current drive and the current directory. If you omit an extension, PCSPFC.EXE adds ".PFT" to the PFT file name.

When you execute the PFT migration utility, the Convert PFT to PDF dialog box appears.

On the Convert PFT to PDF dialog box, select a PFT file from the list box or type a specific PFT file name, and select **OK**. The PFT migration utility starts the conversion and displays the PFT File Converter dialog box to show the conversion status.

After the conversion, if you select **Save List** on the PFT File Converter dialog box, conversion messages in the dialog box are saved into a list file. The list file is created in the same directory and with the same name as the PFT file, except the extension. The extension of the list file is ".LS2".

If the conversion was completed successfully, you can select **Convert PDF to PDT** from the PFT File Converter dialog box to convert the PDF file to a PDT file. You can also create a PDT file by selecting **Printer Setup** from the File pull-down menu as explained in "Creating and Changing the Printer Definition Table (PDT File)" on page 14-1.

Considerations

When the base PDF file already exists, the converted PDF fields are appended to the end of the base PDF file. The name of the base PDF file is decided as follows:

Table 14-7. PDF File Name

PFT File Name	Base PDF File Name
xxxxxxxx**.PFT**	xxxxxxxx**.PDF**
IBMxxxxx**.MNL**	**MNL**xxxxx**.PDF**
zzzxxxxx**.MNL***	zzzxxxxx**.PDF***

* "zzz" is not "IBM".

Even if the same fields are already defined in the PDF file, the appended fields are effective because the last definition is always effective in a PDF file.

If the base PDF file does not exist in the directory, the PFT migration utility creates a new PDF file that has only the converted fields from the PFT file.
In this case, you should append this file to an appropriate base file manually, because the fields converted from the PFT file do not cover all of the necessary PDF fields.

Therefore, it is recommended that you prepare both the PFT file and its base PDF file in the same directory before the conversion.

Details of Migration

This section describes how the PFT migration utility migrates the printer function table (PFT) to the printer definition file (PDF).

Migration from the Printer Function Table

The following table shows the target fields of the PDF for the data in the PFT.

Table 14-8 (Page 1 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
INITIALIZATION AND RESET	
Initialization	
Initialization	START_JOB=
	When the data is defined in the Initialization field of PFT, the data is appended to the string START_JOB=.
Filename	
Filename	None
	This field is ignored.
Reset	
Reset	END_JOB=
	When the data is defined in the Reset field of PFT, the data is appended to the string END_JOB=.

Table 14-8 (Page 2 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
VERTICAL LINE SPACING	
6 lines per inch	
6 lines per inch	SET_6_LINES_PER_INCH=
	When the data is defined in the 6 lines per inch field of PFT, the data is appended to the string SET_6_LINES_PER_INCH=.
8 lines per inch	
8 lines per inch	SET_8_LINES_PER_INCH=
	When the data is defined in the 8 lines per inch field of PFT, the data is appended to the string SET_8_LINES_PER_INCH=.
Variable line spacing	
Control Sequence	SET_VARIABLE_DENSITY=
	When the data is defined in the control sequence field of the PFT for the variable line spacing, the data is appended to the string SET_VARIABLE_DENSITY=. The parameter n in the control sequence is replaced with the PDF parameter type.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	LINE_SPACING_RATIO=
	When the data is defined in the X/Y field of the PFT for the variable line spacing, the value Y/X is appended to the string LINE_SPACING_RATIO= as three-digit or four-digit numbers to indicate the decimal number. For example, when Y/X is 72, the **72** is appended to the string LINE_SPACING_RATIO= and **LINE_SPACING_RATIO= 72** is written to the output file. When the value is greater than 255, the four-digit number is migrated. When the value is less than 255, the three-digit number is migrated.
Indexing Functions	
Begin Superscript	START_SUPERSCRIPT=
	When the data is defined in the Begin Superscript field and End Superscript field of the PFT for the indexing functions, the data is appended to the string START_SUPERSCRIPT=. If the data for the End Superscript is not defined, the data for the Begin Superscript is ignored.
End Superscript	END_SUPERSCRIPT=
	When the data is defined in the End Superscript field and Begin Superscript field of the PFT for the indexing functions, the data is appended to the string END_SUPERSCRIPT=. If the data for the Begin Superscript is not defined, the data for the End Superscript is ignored.

Table 14-8 (Page 3 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Begin Subscript	START_SUBSCRIPT=
	When the data is defined in the Begin Subscript field and End Subscript field of the PFT for the indexing functions, the data is appended to the string START_SUBSCRIPT=. If the data for the End Subscript is not defined, the data for the Begin Subscript is ignored.
End Subscript	END_SUBSCRIPT=
	When the data is defined in the End Subscript field and Begin Subscript field of the PFT for the indexing functions, the data is appended to the string END_SUBSCRIPT=. If the data for the Begin Subscript is not defined, the data for the End Subscript is ignored.
Reverse 1/2 Index	START_SUPERSCRIPT= END_SUBSCRIPT=
	The data is appended to the START_SUPERSCRIPT= for all of the following conditions: When the data is not defined in the Begin Superscript field in the PFT or when the data is not defined in the End Superscript field in the PFT. When the data is defined in the Reverse 1/2 index and Forward 1/2 index field in the PFT. The data is appended to END_SUBSCRIPT= for all of the following conditions: When the data is not defined in the Begin Subscript field in the PFT or when the data is not defined in the End Subscript field in the PFT. When the data is defined in the Reverse 1/2 index and Forward 1/2 index field in the PFT.
Forward 1/2 Index	END_SUPERSCRIPT= START_SUBSCRIPT=
	The data is appended to END_SUPERSCRIPT= for all of the following conditions: When the data is not defined in Begin Superscript field in the PFT or when the data is not defined in End Superscript field in the PFT. When the data is defined in the Reverse 1/2 index and Forward 1/2 index field in the PFT. The data is appended to START_SUBSCRIPT= for all of the following conditions: When the data is not defined in the Begin Subscript field in the PFT or when the data is not defined in the End Subscript field in the PFT. When the data is defined in the Reverse 1/2 index and Forward 1/2 index field in the PFT.
Reverse Index	None
	This field is ignored.

Table 14-8 (Page 4 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
HORIZONTAL LINE SPACING	
5 pitch	
5 pitch	None
	This field is ignored.
8.55 pitch	
8.55 pitch	None
	This field is ignored.
10 pitch	
10 pitch	SET_10_CHARACTERS_PER_INCH=
	When the data is defined in the 10 pitch field of the PFT for the horizontal character spacing, the data is appended to the string SET_10_CHARACTERS_PER_INCH=.
12 pitch	
12 pitch	SET_12_CHARACTERS_PER_INCH=
	When the data is defined in the 12 pitch field of the PFT for the horizontal character spacing, the data is appended to the string SET_12_CHARACTERS_PER_INCH=.
15 pitch	
15 pitch	SET_15_CHARACTERS_PER_INCH=
	When the data is defined in the 15 pitch field of the PFT for the horizontal character spacing, the data is appended to the string SET_15_CHARACTERS_PER_INCH=.
17.1 pitch	
17.1 pitch	SET_17_CHARACTERS_PER_INCH=
	When the data is defined in the 17.1 pitch field of the PFT for the horizontal character spacing, the data is appended to the string SET_17_CHARACTERS_PER_INCH=.
Horizontal Motion Index	
Control Sequence	Ignored
	This field is ignored.
Maximum	Ignored
	This field is ignored.
Offset	Ignored
	This field is ignored.
X/Y	Ignored
	This field is ignored.

Table 14-8 (Page 5 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
HORIZONTAL RELATIVE MOVEMENT	
Forward Relative Movement	
Control Sequence	FORWARD_HORIZONTAL_SKIP=
	When the data is defined in the Forward Relative Movement field of PFT, the data is appended to the string FORWARD_HORIZONTAL_SKIP=. The parameter n in the control sequence is replaced with the PDF parameter type.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	HORIZONTAL_PEL=
	When the data is defined in the X/Y field of the PFT for the forward relative movement, the value Y/X is appended to the string HORIZONTAL_PEL= as three-digit or four-digit number to indicate the decimal number. For example, when Y/X is 120, **12** is appended to the string HORIZONTAL_PEL= and **HORIZONTAL_PEL=12** is written to the output file. When the value is greater than 255, the four-digit number is migrated. When the value is less than 255, the three-digit number is migrated.
Backward Relative Movement	
Control Sequence	None
	This field is ignored.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	None
	This field is ignored.
HIGHLIGHTING	
Begin Emphasis	
Begin Emphasis	START_HIGHLIGHT_INTENSE=
	When the data is defined in the Begin Emphasis of PFT, the data is appended to the string START_HIGHLIGHT_INTENSE=.
End Emphasis	
End Emphasis	END_HIGHLIGHT_INTENSE=
	When the data is defined in the End Emphasis of PFT, the data is appended to the string END_HIGHLIGHT_INTENSE=.
Begin Underline	

Table 14-8 (Page 6 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Begin Underline	START_HIGHLIGHT_UNDERLINE=
	When the data is defined in the Begin Underline of PFT, the data is appended to the string START_HIGHLIGHT_UNDERLINE=.
End Underline	
End Underline	END_HIGHLIGHT_UNDERLINE=
	When the data is defined in the End Underline of PFT, the data is appended to the string END_HIGHLIGHT_UNDERLINE=.
Begin Quality Print	
Begin Quality Print	None
	This field is ignored.
End Quality Print	
End Quality Print	None
	This field is ignored.
PAPER HANDLING	
Bottom Tray Feed	
Bottom Tray Feed	SELECT_DRAWER2=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control of the portrait orientation. For this, the PFT migration utility divides this control sequence into two parts and migrates the control sequence for the drawer select and paper feed. The control sequence of the portrait orientation is migrated to SET_PORTRAIT_ORIENT=. If no data is defined in any fields for LANDSCAPE PAPER HANDLING, the PFT migration utility migrates this control sequence to the SELECT_DRAWER2=. (See “Definition of PAPER HANDLING Migration” on page 14-61.)
Top Tray Feed	
Top Tray Feed	SELECT_DRAWER1=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control of the portrait orientation. For this, the PFT migration utility divides this control sequence into two parts and migrates the control sequence for the drawer select and paper feed. The control sequence of the portrait orientation is migrated to SET_PORTRAIT_ORIENT=. If no data is defined in any fields for LANDSCAPE PAPER HANDLING, the PFT migration utility migrates this control sequence to SELECT_DRAWER1=. (See “Definition of PAPER HANDLING Migration” on page 14-61.)

Table 14-8 (Page 7 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
Envelope Feed	
Envelope Feed	SELECT_ENVELOPE=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control of the portrait orientation. For this, the PFT migration utility divides this control sequence into two parts and migrates the control sequence for the drawer select and paper feed. The control sequence of the portrait orientation is migrated to SET_PORTRAIT_ORIENT=. If no data is defined in any fields for LANDSCAPE PAPER HANDLING, the PFT migration utility migrates this control sequence to SELECT_ENVELOPE=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Manual Feed	
Manual Feed	SELECT_DRAWER3=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control of the portrait orientation. For this, the PFT migration utility divides this control sequence into two parts and migrates the control sequence for the drawer select and paper feed. The control sequence of the portrait orientation is migrated to SET_PORTRAIT_ORIENT=. If no data is defined in any fields for LANDSCAPE PAPER HANDLING, the PFT migration utility migrates this control sequence to SELECT_DRAWER3=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Continuous Feed	
Continuous Feed	None
	This field is ignored.
Ignore Paper End Sensor	
Ignore Paper End Sensor	None
	This field is ignored.
Enable Paper End Sensor	
Enable Paper End Sensor	None
	This field is ignored.
Eject Automatic Cut Sheet	
Eject automatic Cut Sheet	None
	This field is ignored.
Eject Manual Cut Sheet	
Eject Manual Cut Sheet	None
	This field is ignored.
Collate	

Table 14-8 (Page 8 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Collate	None
	This field is ignored.
PAPER POSITIONING	
Continuous Forms	
Dist. from Top Paper Edge	None
	This field is ignored.
Dist. from Left Paper Edge	None
	This field is ignored.
Location of First Print Column	None
	This field is ignored.
Manual Feed	
Dist. from Top Paper Edge	None
	This field is ignored.
Dist. from Left Paper Edge	None
	This field is ignored.
Location of First Print Column	None
	This field is ignored.
Automatic Feed	
Dist. from Top Paper Edge	None
	This field is ignored.
Dist. from Left Paper Edge	None
	This field is ignored.
Location of First Print Column	None
	This field is ignored.
SET PAGE LENGTH (INCHES)	
Control Sequence	PAGE_LENGTH_TYPE?=INCH SET_PAGE_LENGTH=
	When the data is defined in the control sequence for SET PAGE LENGTH (INCHES) and any data is not defined in the control sequence for SET PAGE LENGTH (LINES), this field is migrated.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	None
	This field is ignored.

Table 14-8 (Page 9 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Top Margin Size	None
	This field is ignored.
Bottom Margin Size	None
	This field is ignored.
SET PAGE LENGTH (LINES)	
Control Sequence	PAGE_LENGTH_TYPE?=LINE SET_PAGE_LENGTH=
	When the data is defined in the control sequence for SET PAGE LENGTH (LINES), this field is migrated.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	None
	This field is ignored.
Top Margin Size	None
	This field is ignored.
Bottom Margin Size	None
	This field is ignored.
SET LEFT MARGIN (INCHES)	
Control Sequence	None
	This field is ignored.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
X/Y	None
	This field is ignored.
SET LEFT MARGIN (COLUMNS)	
Control Sequence	SET_HORIZONTAL_MARGIN=
	When the data is defined in the control sequence field for SET LEFT MARGIN (COLUMNS), this field is migrated.
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.

Table 14-8 (Page 10 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
CARRIER RETURN/LINE FEED	
Continuous Forms	
Carrier Return (Continuous Forms)	CARRIAGE_RETURN=
	This field is migrated for the following cases: Case 1 – When the data is defined in the Carrier Return field for the Continuous Forms and – Any data is not defined in the Carrier Return field for the Manual Feed and Automatic Feed. Case 2 – When the data is defined in the Carrier Return field for the Continuous Forms and – The same data is defined in the Carrier Return field for the Manual Feed and – Any data is not defined in the Carrier Return field for the Automatic Feed. Case 3 – When the data is defined in the Carrier Return field for the Continuous Forms and – The same data is defined in the Carrier Return field for the Automatic Feed and – Any data is not defined in the Carrier Return field for the Manual Feed. Case 4 – When the data is defined in the Carrier Return field for the Continuous Forms and – The same data is defined in the Carrier Return field for the Automatic Feed and Manual Feed.

Table 14-8 (Page 11 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
Line Feed (Continuous Forms)	LINE_FEED= This field is migrated for the following cases: Case 1 – When the data is defined in the Line Feed field for the Continuous Forms and – Any data is not defined in the Line Feed Line field for the Manual Feed and Automatic Feed. Case 2 – When the data is defined in the Line Feed field for the Continuous Forms and – The same data is defined in the Line Feed field for the Manual Feed and – Any data is not defined in the Line Feed field for the Automatic Feed. Case 3 – When the data is defined in the Line Feed field for the Continuous Forms and – The same data is defined in the Line Feed field for the Automatic Feed and – Any data is not defined in the Line Feed field for the Manual Feed. Case 4 – When the data is defined in the Line Feed field for the Continuous Forms and – The same data is defined in the Line Feed field for the Automatic Feed and Manual Feed.

Table 14-8 (Page 12 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
Manual Feed	
Carrier Return (Manual Feed)	CARRIAGE_RETURN= This field is migrated for the following cases: Case 1 – When the data is defined in the Carrier Return field for the Manual Feed and – Any data is not defined in the Carrier Return field for the Continuous Feed and Automatic Feed. Case 2 – When the data is defined in the Carrier Return field for the Manual Feed and – The same data is defined in the Carrier Return field for the Continuous Forms and – Any data is not defined in the Carrier Return field for the Automatic Feed. Case 3 – When the data is defined in the Carrier Return field for the Manual Feed and – The same data is defined in the Carrier Return field for the Automatic Feed and – Any data is not defined in the Carrier Return field for the Continuous Forms. Case 4 – When the data is defined in the Carrier Return field for the Manual Feed and – The same data is defined in the Carrier Return field for the Automatic Feed and Continuous Forms.

Table 14-8 (Page 13 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
Line Feed (Manual Feed)	LINE_FEED= This field is migrated for the following cases: Case 1 – When the data is defined in the Line Feed field for the Manual Feed and – Any data is not defined in the Line Feed Line field for the Continuous Forms and Automatic Feed. Case 2 – When the data is defined in the Line Feed field for the Manual Feed and – The same data is defined in the Line Feed field for the Continuous Forms and – Any data is not defined in the Line Feed field for the Automatic Feed. Case 3 – When the data is defined in the Line Feed field for the Manual Feed and – The same data is defined in the Line Feed field for the Automatic Feed and – Any data is not defined in the Line Feed field for the Continuous Forms. Case 4 – When the data is defined in the Line Feed field for the Manual Feed and – The same data is defined in the Line Feed field for the Automatic Feed and Continuous Forms.

Table 14-8 (Page 14 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name Description
Automatic Feed	
Carrier Return (Automatic Feed)	CARRIAGE_RETURN= This field is migrated for the following cases: Case 1 – When the data is defined in the Carrier Return field for the Automatic Feed and – Any data is not defined in the Carrier Return field for the Continuous Feed and Manual Feed. Case 2 – When the data is defined in the Carrier Return field for the Automatic Feed and – The same data is defined in the Carrier Return field for the Continuous Forms and – Any data is not defined in the Carrier Return field for the Manual Feed. Case 3 – When the data is defined in the Carrier Return field for the Automatic Feed and – The same data is defined in the Carrier Return field for the Manual Feed and – Any data is not defined in the Carrier Return field for the Continuous Forms. Case 4 – When the data is defined in the Carrier Return field for the Automatic Feed and – The same data is defined in the Carrier Return field for the Manual Feed and Continuous Forms.

Table 14-8 (Page 15 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Line Feed (Automatic Feed)	LINE_FEED=
	This field is migrated for the following cases: Case 1 – When the data is defined in the Line Feed field for the Automatic Feed and – Any data is not defined in the Line Feed Line field for the Continuous Forms and Manual Feed. Case 2 – When the data is defined in the Line Feed field for the Automatic Feed and – The same data is defined in the Line Feed field for the Continuous Forms and – Any data is not defined in the Line Feed field for the Manual Feed. Case 3 – When the data is defined in the Line Feed field for the Automatic Feed and – The same data is defined in the Line Feed field for the Manual Feed and – Any data is not defined in the Line Feed field for the Continuous Forms. Case 4 – When the data is defined in the Line Feed field for the Automatic Feed and – The same data is defined in the Line Feed field for the Manual Feed and Continuous Forms.
MULTIPLE COPIES	
Print without Clearing Page from	
Top Tray	None
	This field is ignored.
Bottom Tray	None
	This field is ignored.
Envelope Tray	None
	This field is ignored.
Manual Tray	None
	This field is ignored.
Clear Page Buffer	None
	This field is ignored.
Multiple Copies Variable Control	
Control Sequence	None
	This field is ignored.

Table 14-8 (Page 16 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Maximum	None
	This field is ignored.
Offset	None
	This field is ignored.
LANDSCAPE PAPER HANDLING	
Bottom Tray Feed	
Bottom Tray Feed	SET_LANDSCAPELEFT_ORIENT=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control sequence for the landscape orientation. For this, the PFT migration utility divides the control sequence into two parts. The control sequence for the drawer select and paper feed is ignored because this control sequence is migrated when the data for PAPER HANDLING is processed. The control sequence for landscape orientation is migrated to SET_LANDSCAPE_ORIENT=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Top Tray Feed	
Top Tray Feed	SET_LANDSCAPELEFT_ORIENT=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control sequence for the landscape orientation. For this, the PFT migration utility divides the control sequence into two parts. The control sequence for the drawer select and paper feed is ignored because this control sequence is migrated when the data for PAPER HANDLING is processed. The control sequence for landscape orientation is migrated to SET_LANDSCAPE_ORIENT=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Envelope Feed	
Envelope Feed	SET_LANDSCAPELEFT_ORIENT=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control sequence for the landscape orientation. For this, the PFT migration utility divides the control sequence into two parts. The control sequence for the drawer select and paper feed is ignored because this control sequence is migrated when the data for PAPER HANDLING is processed. The control sequence for landscape orientation is migrated to SET_LANDSCAPE_ORIENT=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Manual Feed	

Table 14-8 (Page 17 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Manual Feed	SET_LANDSCAPELEFT_ORIENT=
	If the data is defined in some fields for LANDSCAPE PAPER HANDLING, the PFT migration utility assumes that this control sequence includes the control sequence for the landscape orientation. For this, the PFT migration utility divides the control sequence into two parts. The control sequence for the drawer select and paper feed is ignored because this control sequence is migrated when the data for PAPER HANDLING is processed. The control sequence for landscape orientation is migrated to SET_LANDSCAPE_ORIENT=. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
TYPESTYLE DEFINITION	
Default TypeStyle Definition	
PC Character Set	None
	This field is ignored.
Initial Control Sequence	None
	This field is ignored.
Ending Control Sequence	None
	This field is ignored.
Individual Typestyle Definition	
Typestyle number	SET_GFID_
	This number is appended as a four-digit number after the string SET_GFID_. For example, when the typestyle number **9** is defined, **9** is appended after the string SET_GFID_ and SET_GFID_0009= is migrated. And the numbers supported by PC400 are migrated. The numbers not supported by PC400 are ignored.
PC Character Set	None
	This field is ignored.
Initial Control Sequence	SET_GFID_xxxx=
	This control sequence is appended after the string SET_GFID_xxxx=, where xxxx is the four-digit number defined in the typestyle number field.
Ending Control Sequence	None
	This field is ignored.
Characters	None
	This field is ignored.
Initial Control Sequence	None
	This field is ignored.
Ending Control Sequence	None
	This field is ignored.

Table 14-8 (Page 18 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Symbols	None
	This field is ignored.
Initial Control Sequence	None
	This field is ignored.
Ending Control Sequence	None
	This field is ignored.
Group Typestyle Definition	
Group Identifier	None
	This field is ignored.
Group Identifier Comment	None
	This field is ignored.
Typestyle number	SET_GFID_
	This number is appended as a four-digit number after the string SET_GFID_. For example, when the typestyle numbers 1, 2, 3, and 4 are defined, **1**, **2**, **3**, and **4** are appended after the string SET_GFID_ and SET_GFID_0001=, SET_GFID_0002=, SET_GFID_0003=, and SET_GFID_0004= are migrated because the PC400 does not have the group typestyle definition. The typestyle numbers that are not supported by the PC400 are not migrated.
PC Character Set	None
	This field is ignored.
Initial Control Sequence	SET_GFID_xxxx=
	This control sequence is appended after the string SET_GFID_xxxx=, where xxxx is the four-digit number defined in the typestyle number field.
Ending Control Sequence	None
	This field is ignored.
Characters	None
	This field is ignored.
Initial Control Sequence	None
	This field is ignored.
Ending Control Sequence	None
	This field is ignored.
Symbols	None
	This field is ignored.
Initial Control Sequence	None
	This field is ignored.

Table 14-8 (Page 19 of 23). Migration from the Printer Function Table to the Printer Definition File	
PFT Field Name	**PDF Field Name**
	Description
Ending Control Sequence	None
	This field is ignored.
Character Set Number	
Character Set Number	None
	This field is ignored.
SLOT SELECTION	
Slot 1 Sequence	
Slot 1 Sequence	None
	This field is ignored.
Slot 2 Sequence	
Slot 2 Sequence	None
	This field is ignored.
Slot 3 Sequence	
Slot 3 Sequence	None
	This field is ignored.
Stop Sequence	
Stop Sequence	None
	This field is ignored.
USER DEFINED CONTROL	
Parameters of SET ENVELOP SIZE Command	
Control Number: 984	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
ESC Sequence of SET ENVELOP SIZE Command	
Control Number: 985	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
Parameters of SET PAGE SIZE Command	
Control Number: 986	None
	This field is ignored.

Table 14-8 (Page 20 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
ESC Sequence of SET PAGE SIZE Command	
Control Number: 987	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
Printer Data Stream	
Control Number: 988	None
	This field is ignored.
Control Sequence	SET_FONT_GLOBAL=1B 5B 49 word-value(LH) word-value(HL) word-value(HL) byte-value word-value(HL)
	When **4** is defined in this field, SET_FONT_GLOBAL=1B 5B 49 ... word-value(HL) is migrated. When the other value is defined, this field is ignored. **4** means IBM Personal Printer Data Stream Level 2 or higher. When the migration is done for PAPER HANDLING, use this information. (See "Definition of PAPER HANDLING Migration" on page 14-61.)
Control Sequence File Name	None
	This field is ignored.
Duplex long edge	
Control Number: 989	None
	This field is ignored.
Control Sequence	SET_DUPLEX=
	When the data is defined in the control sequence for the duplex long edge, the data is appended to the string SET_DUPLEX=.
Control Sequence File Name	None
	This field is ignored.
Duplex short edge	
Control Number: 990	None
	This field is ignored.
Control Sequence	SET_DUPLEX_TUMBLE=
	When the data is defined in the control sequence for the duplex short edge, the data is appended to the string SET_DUPLEX_TUMBLE=.

Table 14-8 (Page 21 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Control Sequence File Name	None
	This field is ignored.
Simplex	
Control Number: 991	None
	This field is ignored.
Control Sequence	RESET_DUPLEX=
	When the data is defined in the control sequence for the simplex, the data is appended to the string RESET_DUPLEX=.
Control Sequence File Name	None
	This field is ignored.
Jog the output tray	
Control Number: 992	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
Normal portrait orientation	
Control Number: 993	None
	This field is ignored.
Control Sequence	SET_PORTRAIT_ORIENT=
	When the data is defined in the control field for the normal portrait orientation, the data is appended to the string SET_PORTRAIT_ORIENT=.
Control Sequence File Name	None
	This field is ignored.
Landscape left	
Control Number: 994	None
	This field is ignored.
Control Sequence	SET_LANDSCAPELEFT_ORIENT=
	When the data is defined in the control field for the landscape left, the data is appended to the string SET_LANDSCAPELEFT_ORIENT=.
Control Sequence File Name	None
	This field is ignored.
Portrait upside down orientation	
Control Number: 995	None
	This field is ignored.

Table 14-8 (Page 22 of 23). Migration from the Printer Function Table to the Printer Definition File

PFT Field Name	PDF Field Name
	Description
Control Sequence	SET_PORTRAITUPDWN_ORIENT=
	When the data is defined in the control field for the portrait upside down orientation, the data is appended to the string SET_PORTRAITUPDWN_ORIENT=.
Control Sequence File Name	None
	This field is ignored.
Landscape right	
Control Number: 996	None
	This field is ignored.
Control Sequence	SET_LANDSCAPERGHT_ORIENT=
	When the data is defined in the control field for the landscape right, the data is appended to the string SET_LANDSCAPERGHT_ORIENT=.
Control Sequence File Name	None
	This field is ignored.
COR in 10 pitch	
Control Number: 997	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
COR in 12 pitch	
Control Number: 998	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
COR in 15 pitch	
Control Number: 999	None
	This field is ignored.
Control Sequence	None
	This field is ignored.
Control Sequence File Name	None
	This field is ignored.
FUNCTION SELECTION TEST RESPONSES	

Table 14-8 (Page 23 of 23). Migration from the Printer Function Table to the Printer Definition File	
PFT Field Name	**PDF Field Name**
	Description
Superscript /Subscript	None
	This data is ignored.
Underline	None
	This data is ignored.
Emphasis (Bold)	None
	This data is ignored.
Form Feed	None
	This data is ignored.
Back Space	BACKSPACE=
	This field is migrated when you type YES or NO in response to the prompt during the Backspace Function Selection Test.
Mid-line pitch change	None
	This data is ignored.
Horizontal Character spacing	None
	This data is ignored.
First character position	None
	This data is ignored.
PSM	None
	This data is ignored.
Cursor Draw	None
	This data is ignored.

Note: When you migrate **IBM3812.PFT** and **IBM3812.MNL**, the following fields are added to **IBM3812.PDF**:

```
FORWARD_VERTICAL_STEP_FEED=1B 5B 43  3    E3 word-value(LH)
VERTICAL_PEL=24
```

Definition of PAPER HANDLING Migration

The PFT migration utility migrates the data for PAPER HANDLING and LANDSCAPE PAPER HANDLING as follows:

1. The PFT migration utility checks whether the LANDSCAPE PAPER HANDLING controls are defined.
2. If the LANDSCAPE PAPER HANDLING controls are defined, the PFT migration utility assumes that the PAPER HANDLING control sequences include controls to set the page orientation to portrait. Each LANDSCAPE PAPER HANDLING control sequence has the controls to set the page orientation to landscape in addition to the tray select and feed controls.
3. If the LANDSCAPE PAPER HANDLING controls are not defined, the PAPER HANDLING controls do not have the controls to set the page orientation to portrait. If a personal printer supports normal portrait, landscape left, portrait

upside down, and landscape right orientation, the page orientation controls are defined in the appropriate user-defined controls.

If the LANDSCAPE PAPER HANDLING controls are not defined: When the PAPER HANDLING controls are defined, the controls are migrated as follows:

PFT Fields		PDF Fields
Bottom Tray Select & Feed	——	SELECT_DRAWER2=
Top Tray Select & Feed	——	SELECT_DRAWER1=
Envelope Tray Select & Feed	——	SELECT_ENVELOPE=
Manual Select & Feed	——	SELECT_DRAWER3=

If the LANDSCAPE PAPER HANDLING controls are defined: When the PAPER HANDLING controls are defined, these controls have the controls to set the page orientation to portrait. The LANDSCAPE PAPER HANDLING controls have the controls to set the page orientation to landscape. The PFT migration utility migrates the controls as follows:



CASE 1

Since both of the fields are not defined, no data is migrated.

Example:
No data is migrated to SELECT_DRAWER2= under the following conditions. For this, SELECT_DRAWER2= is not written in the output file.

- No data is defined in the bottom tray select and feed for PAPER HANDLING.
- No data is defined in the bottom tray select and feed for LANDSCAPE PAPER HANDLING.

CASE 2

Since no data is defined in the field for PAPER HANDLING, the PFT migration utility cannot compare the data in the corresponding field with the data for LANDSCAPE PAPER HANDLING. The data for LANDSCAPE PAPER HANDLING is migrated to the drawer selection field of PDF regardless, including control of the landscape orientation.

Example:
The control of the top tray select and feed for LANDSCAPE PAPER HANDLING is migrated to SELECT_DRAWER1= under the following conditions.

- No data is defined in the top tray select and feed for PAPER HANDLING.
- The control is defined in the top tray select and feed for LANDSCAPE PAPER HANDLING.

CASE 3

Since no data is defined in the field for LANDSCAPE PAPER HANDLING, the PFT migration utility cannot compare the data in the corresponding field with the data for PAPER HANDLING. The data for PAPER HANDLING is migrated to the drawer selection field of PDF regardless, including the control of the portrait orientation.

Example:
The control of the manual select and feed for PAPER HANDLING is migrated to SELECT_DRAWER3= under the following conditions.

- The control is defined in the manual select and feed for PAPER HANDLING.
- No data is defined in the top tray select and feed for LANDSCAPE PAPER HANDLING.

CASE 4

Since the length is different, no data is migrated.

Example:
No data is migrated to SELECT_DRAWER2= under the following conditions. For this, SELECT_DRAWER2= is not written in the output file.

- The data is defined in the bottom tray select and feed for PAPER HANDLING and the length is 8.
- The data is defined in the bottom tray select and feed for LANDSCAPE PAPER HANDLING and the length is 10.

CASE 5

The PFT migration utility compares the data for PAPER HANDLING with the data for LANDSCAPE PAPER HANDLING as follows:

- If a different value is found in the data, search the control backward for the escape character X'1B'.
- If the escape character is found in the middle of the control, divide the control into two parts. The PFT migration utility assumes that the first part

is the control for the tray select and feed, and the second part is the control for the page orientation. The PFT migration utility migrates the first part of the PAPER HANDLING control into the tray select and feed, the second part of the PAPER HANDLING control into the SET_PORTRAIT_ORIENT=, and the second part of the LANDSCAPE PAPER HANDLING control into SET_LANDSCAPELEFT_ORIENT=.

– If the escape character is found at the top of the control and 03 (= HP PCL) is defined in the user-defined control 988, the PFT migration utility assumes that the controls are combined. For this, the control begins with the escape character and the two shared characters. For this, the PFT migration utility assumes that the last character of the first part is a lowercase letter and converts it to an uppercase letter to indicate that it is a terminating character.

  The PFT migration utility divides the controls into the two parts as follows:

  < Control for the PAPER HANDLING >



  < Control for LANDSCAPE PAPER HANDLING >



– If the escape character is found, but the data stream is not HP PCL, the PFT migration utility displays the error message to indicate that the PFT migration utility cannot migrate the data.

– If the escape character is not found, the PFT migration utility displays the error message to indicate that the PFT migration utility cannot migrate the data.

– If a different value is not found, the same control is defined for PAPER HANDLING and LANDSCAPE PAPER HANDLING.

The PFT migration utility migrates the data in the following order:

1. Top Tray Select and Feed
2. Bottom Tray Select and Feed

3. Manual Select and Feed
4. Envelope Tray Select and Feed

The migration stops for the page orientation, SET_PORTRAIT_ORIENT= and SET_LANDSCAPELEFT_ORIENT=, when the controls for the page orientation are found. For example, the controls for the page orientation are found when the data is migrated for the Bottom Tray Select and Feed. The PFT migration utility does not care about the page orientation when migrating the data Manual Select and Feed, and Envelop Tray Select and Feed.

Building PC400 PDTs

Chapter 15. Field Attribute Codes

The following table explains the field attribute codes used in PC400.

Table 15-1. Meanings of Field Attribute Codes

Hex Code	Meaning
20	Green
21	Green, reversed image
22	White
23	White, reversed image
24	Green, underlined
25	Green, underlined, reversed image
26	White, underlined
27	Nondisplay
28	Red
29	Red, reversed image
2A	Red
2B	Red, reversed image
2C	Red, underlined
2D	Red, underlined, reversed image
2E	Red, underlined
2F	Nondisplay
30	Sky blue with column delimiter
31	Sky blue, column delimiter, reversed image
32	Yellow with column delimiter
33	Yellow, column delimiter, reversed image
34	Sky blue, underlined, with column delimiter
35	Sky blue, underlined, reversed image, with column delimiter
36	Yellow, underlined, with column delimiter
37	Nondisplay with column delimiter
38	Purple
39	Purple, reversed image
3A	Blue
3B	Blue, reversed image
3C	Purple, underlined
3D	Purple, underlined, reversed image
3E	Blue, underlined
3F	Nondisplay with column delimiter

© Copyright IBM Corp. 1989, 1996

Chapter 16. AS/400 Utilities

This chapter describes the AS/400 Utilities, which can be accessed by an icon in the Program Manager window.

About the AS/400 Utilities

You can start the following AS/400 utilities from the AS/400 utilities window:

Data Transfer Transfer data from an AS/400 system to your workstation, or from your workstation to an AS/400 system, in the form of fields and records.

Shared Folders Store and share information in AS/400 folders by assigning a workstation drive to a folder.

PCS/400 Router API Establish communications to start PC Support/400 Router API applications from the DOS prompt.

Virtual Printers Use a printer attached to an AS/400 system as a workstation printer. You can control the virtual printer from your workstation.

Note: You can start each of the AS/400 Utilities by clicking on its icon when this window is in its smaller screen size.

Buttons on the Utilities Window

The main panel has five kinds of buttons and the Option Switch Box:

Main power button

This is the main power button for all of the AS/400 utilities. Make sure the power is on (green) before you continue. If you turn the main power off, all currently active functions are stopped.

Lock button

You can lock the power and the on and off buttons. This is useful to avoid switching the main power off by mistake while you are still working with AS/400 Utilities.

Turn-On-Function button

To start a function, click this button.

Turn-Off-Function button

To exit from a function, click this button.

Keyboard lamp

This lamp is effective only when you operate AS/400 Utilities with the keyboard, using the AS/400 Utilities Control Panel. The lamp flashes red when a keyboard command from the control panel is sent successfully to the main window.

© Copyright IBM Corp. 1989, 1996

Option-Switch Box

In this box, you can save the current on and off status of all the utilities. Set the auto-start button to return to the same settings the next time you open the utilities. You can also see at a glance the number of communication links you currently have open.

1. **Save button**

   You can save the current on and off status for each functions.

2. **Auto-Start button**

   All functions return to the same on and off status when you exit from each function.

3. **Indicator On/Off button**

   You can turn the communication link indicator on and off.

4. **Indicator Switch**

   Indicator Switch - Up

   The red indicator bar moves horizontally when communication links are established. The movement of R and L bars indicates the following:

Both of the red bars in R and L move horizontally:	All the communication links have been established successfully.
Only the red bar in R moves horizontally:	Not all the communication links were established; some did not connect.
Neither of the bars in R and L moves:	No communication links are established.

   Indicator Switch - Down

   Indicator R shows you the number of communication links that each function is trying to establish. Two red bars indicate one link.

   Indicator L shows you the number of communication links that have been established. If all the communication links have been established successfully, the number of red blocks in L is the same as in R.

AS/400 Utilities Control Panel

You cannot start AS/400 Utilities functions from the main window by means of the keyboard. Instead, choose **Open AS/400 Utilities Control Panel** from the system menu of the AS/400 Utilities main window; you can start the utilities from this panel. The buttons on the control panel are equivalent to those on the AS/400 Utilities main window. When you select a button on the control panel, the equivalent button or function is turned on in the main window. You will see a flashing red on the keyboard lamp on the main window when your command from the control panel is sent successfully.

The Control Panel	The Main Window
Power(Alt+P)	**Main Power button**
Lock(Alt+L)	**Lock button**
Select(Alt+S)	Each function is selected. (Select the function you want to work with, and the name of the function is displayed in the window.)
Turn On(Alt+U)	**Turn On Function button**
Turn Off(Alt+N)	**Turn Off Function button**
Option Box	**Option Switch Box**
Open/Close(Alt+E/Alt+C)	**Option Switch Box cover latch button**
Save(Alt+A)	**Save button**
Auto Start On/Off(Alt+O)	**Auto-Start button**
Indicator On/Off(Alt+F)	**Indicator On/Off button**
Indicator Switch(Alt+W)	**Indicator Switch - Up**
	Indicator Switch - Down

AS/400 Utilities

Chapter 17. Data Transfer for PC400

This chapter explains file description files and data conversions for the data transfer function.

Data Transfer Function Overview

The PC400 data transfer function transfers data to or from an AS/400 system and a workstation.

Transferring data, described in this chapter, is quite different from transferring files, which is described in Chapter 18. The main differences are listed below:

Type of Transfer	Products required on an AS/400 system	Access Method	Sending and receiving unit	Type of connection to an AS/400 system
File Transfer	Personal Communications Tools (APVAFILE)	Transfer menu in session window	Entire file	Display session
Data Transfer	PC Support/400 V2R2 or V2R3 or OS/400 V3R1 or later[1]	AS/400 Utilities or the Data Transfer Function choice on the Transfer menu	Field, record, or file in a database	No display or printer session required
Note 1: OS/400 provides the host transaction program for Data Transfer.				

Note

When you first configure a PC400 session, the Transfer menu and the corresponding tool bar icons let you do **file** transfer as defined in the preceding table. You can change the function to **data** transfer by selecting **Data Transfer Function** from the Transfer → Setup menu.

The Data Transfer Utility program provides two features: one to establish communication links with the host via the Communication Stack Manager, and another to allow you to view, change, and execute a data transfer request file by the drag-and-drop method.

The Communication Stack Manager establishes communication links for APPC applications without a Router session. The Data Transfer Utility program registers workstation profiles (.ws) in its profile (PCSDT.INI), and these WS files are used to establish communication links by the Communication Stack Manager.

The Data Transfer Utility uses drag-and-drop to transfer the requested file (or a transfer request list). You can drag one file from the list box and drop it to the

© Copyright IBM Corp. 1989, 1996

command button, or to the request list. The cursor shape changes depending upon its position, which signals you if you can drop the file to a particular position.

Transferring Files from an AS/400 System to a Workstation

When using a workstation, you can retrieve and use data from the following file types on an AS/400 system:

Physical database
Logical database
Distributed data management (DDM)

When retrieving files, you can:

Control which records (and which fields within a record) are retrieved.
Control the ordering of records and the ordering of fields within the record.
Select a subset of the records.
Group records into summary records.
Join two or more files.
Specify formats and separators of data and time fields.
Specify the decimal separator character.

The following output destinations can be specified:

Display
Disk
Printer

In addition, you can specify when to receive data (date and time) and the numeric value format.

Transferring Files from a Workstation to an AS/400 System

The PC-to-AS/400 transfer function enables the transfer of data from a workstation to an AS/400 physical file. Data can be transferred to any of the following destinations:

Existing members in an existing AS/400 physical file
New members in an existing AS/400 physical file
New members in a new AS/400 physical file

Note: Data cannot be transferred from a workstation file to an AS/400 logical file.

Note the following when transferring data.

Transferring Data to Existing Members in an Existing File

Note the following when transferring data from a workstation to an existing AS/400 member.

When data is transferred to an existing member, data in that member is replaced with that transferred from a workstation.

When AS/400 members already contain data, a message appears, warning that the data in the existing members will be replaced with the data that is about to be transferred.

Consider the effect of returning data that was previously transferred from the AS/400 (such as when an AS/400 master file is updated on a workstation).

For example, you can transfer only the field subset of an AS/400 file by issuing a transfer request from the AS/400 to a workstation In this case, when returning data from the workstation to the AS/400, only the subset included in that AS/400 file can be transferred. Other fields that had been defined in the AS/400 file but not transferred are filled with blanks if they are character fields or, if they are numeric fields, with zeros or the values specified at file creation.

Therefore, the data must be transferred to another AS/400 file and the transferred data must be embedded in the AS/400 file by running the AS/400 application program. Follow this procedure to control the update processing for an AS/400 master file.

To prevent users from transferring data to a certain AS/400 file, check that the authority level for that file is defined correctly.

Transferring Data to New Members in an Existing File

You can transfer the data in a workstation file to new members in an existing AS/400 file. The transfer function automatically creates these members in the specified file in the specified library. New members are created according to the file description in the existing file.

Be particularly careful when only the field subset of the AS/400 file can be transferred from the AS/400 to a workstation by the previous transfer request. When data is returned to the AS/400, new members can receive only the subset defined in that AS/400 file. Other character fields that are defined, but not transferred are filled with blanks. Numeric fields are filled with zeros or the valued specified at file creation. The date, time, and time-stamp fields use AS/400 default values.

Transferring Data to New Members in a New File

By using a transfer request from a workstation to the AS/400, you can transfer data to new members in a new AS/400 file. This is one of the safest transfer methods, because data already stored in the AS/400 file is not replaced with that transferred from the workstation.

There are two ways of transferring data to new members in a new AS/400 file. The method used depends on the data to be transferred.

For data that is broken up into fields, correct conversion is achieved by transferring it in units of fields. Specify use of the workstation file description file at file transfer. In addition, specify data as the type of the AS/400 file.

When an AS/400 file and its members are created, the transfer function must access the description of the format of each field to be transferred in the AS/400 file. You can get this description, called a field reference file, from the AS/400 file. To create an AS/400 file and its members, specify the name of this AS/400 field reference file, as well as the parameters for the other files and members. Note that only the fields to be transferred are defined in a new file.

For data consisting only of text or source statement records, it is not necessary to break up the records into fields. In addition, the workstationfile description file is not required to transfer data. In other words, an AS/400 physical source file is created.

Transferring Data to an AS/400 Data File and Source File

You can transfer data to the following two types of AS/400 physical file.

Physical data file The members of a physical data file can contain numeric and character data of any AS/400 data type. To transfer data to a physical data file define, use the workstation file description file to define how data is stored in a workstation data file. Besides this definition, the file description of the AS/400 file is required to ensure correct conversion of the data.

When data is transferred to an existing AS/400 file, the file description becomes part of the AS/400 file. When data is transferred to a new AS/400 file, the file description is included in the AS/400 field reference file.

Physical source file Normally, a physical source file stores no data. It contains only text or source statements, as follows:

- The first part (field) of a source file always contains numbers indicating the order.
- The second part (field) of a source file always contains the date on which the file was created.
- The third part (field) of a source file contains the text of the file. This part can contain data fields of character type or zoned type only. Physical source files provide the optimum means of transferring text or source statements with a workstation.

Note the following when transferring data to and from an AS/400 physical source file:

- To transfer text from the AS/400 to a workstation, specify the name of the source file and members in **FROM**. Specify an asterisk (*) in SELECT. This informs the AS/400 that only text is transferred from the source file, with the order number and date fields excluded.
- The AS/400 text must be stored in the workstation code text file. Normally, a workstation text editing program can be used to manipulate this workstation code text file.
- Specify that the file description file is not to be stored for that workstation file. Because text is assumed to be a record consisting only of character data, it is not necessary to define fields.
- To return text from a workstation file to an AS/400 file, specify the type of the workstation file containing the text. This is almost always workstation code text. Specification of the file description file is not required.
- To create a new AS/400 file and its members, specify a valid record length. This record length must be equal to the maximum record length of the workstation file, plus 12. This is because the transfer function automatically creates the order number and date fields when the file is transferred to the AS/400 members. The order number and date fields together occupy 12 bytes.

Preparing for Data Transfer

The following topics describe the software products required to transfer data and the points you must understand before transferring data with PC400.

Required Software Products

To use Data Transfer, IBM PC Support/400 (5738-PC1) must be installed on the AS/400. IBM PC Support/400 is not required with OS/400 Version 3 or later.

Transfer Function

You can transfer only source programs, records, and the information listed below can be transferred:

Information organized for analysis
Information used for decision making
Information suited for computer processing

When using a spreadsheet, for example, you might want to use inventory data to create a cost analysis report. If there is no way to copy the data into the workstation, you must print the data from the AS/400 and manually type it into a workstation file. With the transfer function, however, you can access the inventory database directly, select only the data needed for the report, process the data as required, then complete the report using that data.

Data can also be sent from the workstation to the host system for processing by AS/400 application. When a remote user is authorized to access the AS/400 directly, he or she can access the created cost analysis report to compare with their results.

The following example outlines the joining of two files, transferring the information to the workstation, and creating a report.



To transfer data by using PC400, you must create a transfer request. A transfer request provides the necessary information about the data you want to transfer.

Before creating a transfer request, you must have the answers to the following questions:

Where is the data located?
How much of the data do you want to transfer?
How should the data be sorted?
Where do you want data to be transferred?

When transferring data from the AS/400 to a workstation, PC400 allows you to specify which data is to be transferred and whether the data is to be displayed or written to a workstation file.

In addition, a transfer request can be saved to a workstation file, allowing you to easily perform the same transfer at a later date. After a transfer request is saved, you can call the request to make changes or to run it again.

Data Transfer Program

PC400 data transfer is classified into two types, depending on the direction of the transfer:

Transferring data from the workstation to the AS/400 is called data sending.

Transferring data from the AS/400 to the workstation is called data receiving.

Data transfer can also be classified according to how the program is started, as follows:

Data is transferred by interactively entering information such as *what data is transferred from which file to which file* on the screen. In this case, the interactive screen for sending is called the PC→AS/400 Transfer window, and that for receiving is called the AS/400→PC Transfer window.

Data is transferred according to the information that has already been registered. The interactive screen is not necessary. This is called the *automatic transfer* of data.

In both cases, data transfer is performed by **PCSFT5.EXE** on the workstation and by the *PC Support/400* transfer program on the AS/400.

The **Data Transfer** icon is registered in the PC400 folder by installing PC400. Double-clicking on this icon displays the AS/400→PC Transfer window (for receiving). This icon includes the following:

```
\PCOMOS2\PCSFT5.EXE -R
```

The PC→AS/400 Transfer window (for sending) appears when the registered contents are changed as follows:

```
\PCOMOS2\PCSFT5.EXE -S
```

The AS/400→PC Transfer and PC→AS/400 Transfer windows have a **Switch to SEND** button and **Switch to RECEIVE** button, respectively. By clicking either of these buttons, the window for sending can be switched to the window for receiving, and vice versa.

To perform *automatic transfer*, transfer information must be created, using the interactive screen window, and then saved. Data transfer can then be performed automatically by specifying the file name in which the data was saved.

For example, if transfer information is saved to file **TENSOU.TTO**, contained in directory **C:\PCOMOS2\PRIVATE**, run *automatic transfer* as follows:

```
C:\PCOMOS2\PCSFT5.EXE C:\PCOMOS2\PRIVATE\TENSOU.TTO
```

When you save the transfer information, register it as an icon in the PC400 folder. You can then transfer data automatically simply by double-clicking on this icon.

Data Concepts of AS/400 and Your Workstation

The basic components of data management are files, records, and fields. A *file* is an aggregate of records, referenced by a single name. Each record in a file contains one or more items of correlated information. Each item of information is called a *field*.

AS/400 and your workstation use different functions to store and group data, and to set the format.

Workstation Files

To transfer data from a workstation to the AS/400, the transfer function uses a special-format workstation file, called a *file description file*. Using this file, data is stored in a valid format and converted into a valid type.

A file description file identifies the format of a workstation data file and contains a description of the fields in the data file. The file description file also contains a name list of all the fields in the data file. This list reflects the order, as well as the names, in which each field appears within the data file. In addition, this list includes a description of the data type, length, and decimal position of each field. Using this information, the transfer function can recognize not only how data has been modified but also where a certain field exists in a file record.

When data is transferred from the AS/400 to a workstation, you can use the transfer function to automatically create the file description file. In this case, the information in the file description file depends on the file description in the AS/400 file.

You must create a file description file with the same name as the workstation data file to transfer a workstation data file to the AS/400.

Distributed Data Management (DDM) Files

Distributed data management (DDM) is one of the functions supported by the AS/400. This function is used to access database files that are stored on remote AS/400 systems. To use the transfer function to access these database files, specify a DDM file name as the name of the AS/400 file to be transferred. Refer to the *DDM Guide* for details of how to use DDM files.

AS/400 Files

The following list provides a simple explanation of the requirements for transferring data between the AS/400 and a workstation.

Library The AS/400 library contains related objects that are used to generate significant groups. For example, the objects might be all the programs and files related to credit sales management. Using the library, you can group objects and find a desired file by name. The transfer function uses the library to locate an AS/400 file.

File AS/400 files that you can manipulate consist of a file description and data stored in the file. PC400 processes an AS/400 file, called a database file. The database file can be either a physical file or a logical file.

A *physical file* is a database file that contains data stored in records. It includes a description of the record format in addition to the data itself.

A *logical file* is a database file, which you can use to access data stored in one or more physical files. Logical files, like physical files, contain a file description. However, logical files do not contain any actual data. Instead, you can access fields in one or more physical files by using the record format included in the logical file description. When a logical file is transferred from the AS/400 to a workstation, data is obtained from one or more physical files. You need only specify a logical file as the file to be transferred. The AS/400 recognizes which physical file contains the actual data to be transferred.

Note: Data cannot be transferred from a workstation to logical files.

Member Data records in a database file are grouped into several members. At least one member must be included in one file.

When data is transferred to and from the AS/400, actual data transfer is done between file members. For example, a certain workstation file can be transferred to the AS/400. In this case, the file members become new members of a new or existing AS/400 file, or substitute for existing members in an existing AS/400 file.

Record format

A record format describes the fields contained in a file record and the order in which these fields appear in the record. Record formats are stored in the file description. Both physical and logical database files can have one or more record formats.

Creating a Workstation-to-AS/400 Transfer Request

To create a request for data transfer from a workstation to the AS/400, do the following.

1. Using the router session, establish attachment to the AS/400 to which data is to be transferred.
2. Select the **Data Transfer** icon.
3. When the AS/400→PC Transfer window has been displayed, select **Switch to SEND**. The display is switched to the PC→AS/400 Transfer window.

   To choose additional settings, select **Advanced**.
4. Specify each item. Refer to “Items to Be Specified” for details.

Items to Be Specified

The following explains the items specified in the PC→AS/400 Transfer window. Those items that are specified by selecting **Advanced**, are indicated by the addition of “(Advanced)” at the end of the corresponding item name.

FROM

PC file name

This item is always required. It specifies the name of the PC, or workstation, file containing the data to be transferred to the AS/400. Specify this item using the following format. (Items inside brackets [ ] can be omitted.)

[*d*:][*path-name*]*file-name*[.*ext*]

A list of workstation files can be displayed by selecting **Browse**. You can limit the number of names listed. To limit the listing, specify a combination consisting of part of a file name and a global file name character (* or ?) in the input area of the workstation file list. An example is shown below:

When you select **OK** with A: specified, the displayed listing contains the names of all files in the current directory of the diskette inserted into drive A.

When you select **OK** with **A:\SUPPLY** specified, the displayed listing contains the names of all files under the **SUPPLY** path of the diskette inserted into drive A.

When you select **OK** after specifying **B:*.XLS**, the displayed listing contains the names of all files having extension **XLS** in the current directory of the diskette inserted into drive B.

TO

System name

This item is always required. When the router program is active, this item specifies the default system name.

Library/File (Member)

This item is always required. It specifies the name of the AS/400 physical file that will receive the data to be transferred from the workstation. Either an existing file name or new file name can be specified.

Specify this item using the following format. (Items inside brackets [ ] can be omitted.)

[*library-name/*]*file-name*[(*member-name*[,*record-format-name*])]

library-name

This is the name of the AS/400 library containing the AS/400 file to which data is to be transferred. If no library is specified, ***LIBL** is used. To create a new file to receive transferred data, specify the library name.

When the input field is null and **Browse** is selected, the AS/400 displays a list of all libraries defined in ***USRLIBL** of the AS/400 job library list. This list can be modified by changing the job description. Run a change job description (**CHGJOBD**) command on the AS/400.

file-name

This is the name of an AS/400 physical database file. When data is transferred to an existing file, the data in that file is replaced with the transferred data. To create a new file to receive transferred data, specify a new file name of 1 to 10 characters.

To list the available files, do one of the following:

To list all files within all libraries defined in ***USRLIBL** of the AS/400 job library list, specify ***USRLIBL** followed by a slash (/), then select **Browse**. If a slash (/) is not specified after the library name, the AS/400 displays a list of library names rather than the file names.

To list the names of the files in a certain library, specify the library name followed by a slash (/), then select **Browse**. You can also specify a part of a file name followed by an asterisk (*), then select

Browse. The AS/400 lists all the files whose names begin with the specified character string.

member-name

This is the name of a member in the specified AS/400 file to which data is to be transferred. If this member name is not specified, data is transferred to the first member, ***FIRST**, in the AS/400 file. When the specified member already exists, the data in that member is replaced with the transferred data.

To transfer data to an existing file, specify the member name. The data within that file member is replaced with the transferred data.

To create a new member in an existing file or in a new file, specify a new member name of 1 to 10 characters.

By selecting **Browse** with a file name specified, the names of the members in that file are listed. When a left parenthesis, part of a member name, an asterisk (*), and a right parenthesis are specified, in this order, and then **Browse** is selected, the AS/400 can list all member names beginning with the specified character string.

record-format-name

This is the name of the record format in the specified AS/400 file. The record format name need not be specified except when a physical file contains more than one record format. Most physical files have only one record format. Before specifying a record format name, a member name or ***FIRST** must be specified as the member name.

When you transfer data to an existing file without specifying a record format name, it is assumed that the file has only one record format (***ONLY**). Therefore, that record format is used.

When a new file is created with no record format name, **QDFTFMT** is used as the record format name.

Note: A library name, file name, member name, and record format name can be specified using up to 10 characters each. Each name must begin with one of characters A to Z, ¥, #, and @. For characters subsequent to the first, 0 to 9, underscores, and periods can also be used.

Use of File Description File (Advanced)

This item is always required. It specifies whether a file description file is used to transfer data to the AS/400. The file description file is required to transfer a workstation file, containing the data to be transferred (and converted), in fields. Such a workstation file can have either several fields or numeric data fields. To transfer a workstation file containing text (character data) only, the file description file is not required. For details on creating a file description file, see “File Description Files” on page 17-45.

Follow either of the two procedures below.

Do not specify this item in the following case: a workstation file having only one field (for example, PC code character) is specified in the **FROM**, while the AS/400 file is a physical source file having the following record format.

Field	Type	Length	Decimal Places
Order number	Zoned	6	2
Date	Zoned	6	
Data	Character or Open	1 to 4 96	

Note: When fields contain character data or zoned data only, the data portion can be broken down into several fields. The destination AS/400 file contains the fields for order number and date. The workstation file, however, does not. This method is recommended when transferring text only between the AS/400 and workstation.

Specify this item in all cases other than that described above. Two examples are shown below:

- Data is transferred from a workstation file having more than one field.
- The AS/400 file that receives the data is other than a physical source file having the record format described above.

File Description File Name (Advanced)

This item appears only when item **Use of File Description File** is specified.

This item is always required. It specifies the name of the workstation file description file that describes the data to be transferred.

Upon transferring data from the AS/400 to a workstation, a file description file might have been created.

A file description file must be created when the data has not yet been transferred from the AS/400 to a workstation or when no file description file exists.

PC File Type (Advanced)

This item appears only when **Use of File Description File** is not specified.

This item is always required. You must specify the type of the workstation file specified in the **FROM** field. The values provided by the AS/400 are recognized as workstation code text. If the file type of a data file is not converted, the file can include nothing other than data that does not require conversion.

AS/400 Object (Advanced)

This item is always required. It specifies whether the AS/400 member to which data is transferred is a new member or an existing member. When data is transferred to a new member, this item also specifies whether the file to contain the new member is an existing file.

Create New Member

This item specifies that a new member, to which data is transferred, is created in an existing AS/400 file.

Notes:

1. To create a new member, you must have the following authorities:

   ***OBJOPR**, ***OBJMGT**, and ***ADD** for the file that will include the new member

   ***READ** and ***ADD** for a library that will contain the file

See *Security Descriptions* (SC41-8083) for details of object authorities.

2. To create a member to add to a file, the transfer function uses the AS/400 default value for the add physical file member (**ADDPFM**) command.

When you specify this item, the following item must also be specified:

Member Text

This item is optional. It is used to add an explanation of a new AS/400 member. This explanation helps remind you of the contents of the member. This explanation appears, for example, when a list of all members in a file is requested (**Browse** is selected). If this item is left blank, no explanation is added to the new AS/400 member.

To specify an apostrophe (') in the explanation, enter two apostrophes (' ').

Create New Member in New File

This item specifies that a new member, to which data is to be transferred, is created in a new AS/400 file.

Notes:

1. To create a new member in a new file, ***READ** and ***ADD** authorities are required for the library that will contain that file. Authority to use the create physical file (**CRTPF**) command of the AS/400 is also required.
2. To create a new member in a new file, the transfer function uses the default value for the create physical file (**CRTPF**) command of the AS/400. It does not, however, use the following values:

   (**MAXMBRS**[***NOMAX**]). This indicates that the file can contain up to 32 767 members.

   (**SIZE**[***NOMAX**]). This indicates that each member of the file can contain an unlimited number of records.

When this item is specified, also specify the following item:

Member Text

This item is optional. It is used to add an explanation of a new AS/400 member. This explanation helps remind you of the contents of the member. This explanation appears, for example, when a list of all the members in a file is requested (**Browse** is selected). If this item is left blank, no explanation is added to the new AS/400 member.

To specify an apostrophe (') in the explanation, enter two apostrophes (' ').

AS/400 File Type

This item is always required. It specifies the type of an AS/400 file and the members to be created (same type for both).

Specify one of the following:

To create an AS/400 physical source file and its members, specify **Source**. These members are created with two fields (order number and date) added to the beginning of the data

transferred from the workstation file. A new AS/400 source file and its members have the following record format:

Field	Type	Length	Decimal Places
Order number	Zoned	6	2
Date	Zoned	6	
Data	Character or Open	1 to 32755	

Note the following: In an AS/400 physical source file, each record can be up to 32755 bytes in length. But, the maximum size of a source file created using the workstation-to-AS/400 transfer function is 4107 bytes. Also, this file must include the order and date fields. Therefore, the maximum amount of data that can be transferred is 4096 bytes per record.

The data portions of members inherit the workstation file characteristics. In other words, when a workstation file is a workstation code text file consisting of many records containing text, the created data fields will be the same.

To create an AS/400 physical data file and its members, specify **Data**. The file and members will contain only the data fields described in the file description file.

The value of the **AS/400 File Type** is assumed to be **Data** when a file description file is used to transfer data. If a file description file is not used for data transfer, the value of this item is assumed to be **Source**.

Field Reference File Name

This item appears only when **Use of File Description File** is specified for the creation of a new file.

When **Use of File Description File** is not specified, an AS/400 physical source file is created. **AS/400 File Type** and **Field Reference File Name** are not displayed. Instead, **Record Length** appears.

This item is always required. A new AS/400 file is created using the field name in a file description file and the field definitions in an AS/400 field reference file.

The format of a field reference file name is as follows. (Items inside brackets [ ] can be omitted.)

[*library-name/*]*file-name*

library-name: This is the name of an AS/400 library containing a field reference file. If this library name is not specified, ***LIBL** is assumed. If you cannot find the desired library, selecting **Browse** displays a list of all libraries in ***USRLIBL** of the AS/400 job library list. ***USRLIBL** of the library list can be changed by modifying the job description by executing a **CHGJOBD** command on the AS/400 processor.

file-name: This is the name of the AS/400 physical database file containing the field definitions. Always specify this file name. When a library name is specified

concurrently, use a slash (/) to delimit the library name and file name. If the desired file cannot be found, enter the library name and a slash, then select **Browse**. The system displays a list of files in that library. To list all the files in the libraries defined in ***USRLIBL** of the AS/400 job library list, enter ***USRLIBL**/ then select **Browse**.

If you enter part of a file name followed by an asterisk (*) and then select **Browse**, the system displays a list of available file names, each beginning with the specified part of the name.

For example, enter **ARLIB**/**AR*** in the **Field Reference File Name** item, then select **Browse**. The system displays a list of all physical file names beginning with AR in library ARLIB.

Note: You must have ***OBJOPR** authority for the field reference file to be specified. To list certain files, you must also have ***OBJOPR** authority for those files.

Record Length

This item is always required. It specifies the record length of an AS/400 physical source file. When the data receiver is an AS/400 physical source file, the specified value must include the length of the order number and date fields that are added to a workstation file at transfer (the total length of these two fields is 12 bytes).

Authority

This item is always required. It specifies the authority level of a new AS/400 file.

Specify one of the following:

Read/Write. This enables other users to read from and write to the AS/400 file and allows the file name to be displayed in lists. However, users cannot delete the file (***OBJOPR**, ***READ**, ***ADD**, ***OBJMGT**, ***UPD**, and ***DLT** authorities). If other users might be transferring data from a workstation file to the AS/400 file, specify **Read/Write** or **All**.

Read. This enables other users to read from the AS/400 file, and allows the file name to be displayed in lists. However, other users can neither write to the file nor delete it (***USE** authority).

All. This enables other users to read from and write to the AS/400 file as well as delete it. The file name is displayed in lists (***ALL** authority).

None. This prevents other users (except for the system administrator) from writing to or deleting the AS/400 file. The file name does not appear in lists (***EXCLUDE** authority).

File Text

This item is optional. It is used to add an explanation of a new AS/400 file. This explanation helps remind the user of the contents of the file. This explanation appears, for example, when a list of all files in a library is requested (**Browse** is selected). If this item is left blank, no explanation is added to the new AS/400 file.

To specify an apostrophe (') in the explanation, enter two apostrophes (' ').

Replace Existing Member
This item transfers data to an existing AS/400 member, specified in the **Library/File (Member)** item. The existing data in that AS/400 member is replaced with the transferred data.

Saving, Opening, Changing, and Executing a Transfer Request

The following explains how to save, open, change, and execute, as a file, information (transfer request) on data to be transferred.

Saving a Transfer Request

Save a transfer request when the request is likely to be executed repeatedly. This eliminates the need to create a transfer request every time data is to be transferred. To save a transfer request, do the following.

1. Specify the information needed for transfer, using the PC→AS/400 Transfer window.
2. After specifying the necessary information, select **Save** or **Save As** from the **File** menu of the menu bar.

   The Save Transfer Request File as window appears.
3. Specify each item, referring to the following explanation, then select **OK**.

   File Name Disk to which data is to be saved. Specify a file name or diskette file name. The default extension is **TFR**. Extension **TFR** identifies a file as a transfer request file.

   Description This item can be used to add an additional explanation of a transfer request, as required. The explanation can be up to 40 characters in length. This explanation is saved with the transfer request, and displayed in the list of transfer request names. It is, therefore, useful for identifying a transfer request.
4. The system asks whether the saved transfer request is to be registered in the PC400 folder.

   When **OK** is selected, the transfer request is registered as an icon. Subsequently selecting this icon transfers data according to the contents of the registered data transfer request.

Opening and Changing a Saved Transfer Request

To open and change a saved transfer request, do the following.

1. Display the PC→AS/400 Transfer window.
2. Select **Open** from the **File** menu of the menu bar.
3. Specify the name of the file to be opened using the Open Transfer Request File window, then select **OK**.

   The PC→AS/400 Transfer window reappears, and the transfer request information, saved to the specified file, appears for each item. This opens the saved transfer request.
4. The contents of the transfer request can be changed as necessary.

5. To save the changed contents, follow the procedure explained in “Saving a Transfer Request.”

Performing a Transfer Request

A transfer request can be performed in any of the following ways:

By using the OS/2 command prompt

By selecting the icon with which the transfer request has been registered

By using the PC→AS/400 Transfer window of the **Data Transfer** icon

Each method is described below:

Using the OS/2 Command Prompt:

By referring to “Data Transfer Program” on page 17-6, execute the program **PCSFT5.EXE**, specifying the saved transfer request file name as a parameter.

Selecting the Icon With Which the Transfer Request Has Been Registered:

This method can be used only when a transfer request has been saved as an icon by using the **PC→AS/400 Transfer** window.

Selecting the corresponding icon starts data transfer.

Using the* PC→AS/400 Transfer *Window:

1. Before executing a transfer request, operations such as creating, opening, and changing a transfer request must be completed.

   Note: When data is transferred from a workstation to an existing member in an AS/400 file, the transferred data replaces the existing data in that member.

2. Select **Send** from the PC→AS/400 Transfer window.

   Data transfer starts.

3. After the transfer has been completed, select the **Cancel** pushbutton or **Exit** from the menu bar **File** menu.

Conversion Errors That Can Occur during Transfer

Upon executing a transfer request, a file description file (when specified) is read from the disk or diskette to be processed. The AS/400 and workstation exchange information, if the data is transferable.

The workstation transfers records, one at a time, from the file specified in **FROM**. Transferred records are converted and stored in the AS/400 member specified in **TO**.

During this conversion process, conversion errors might occur. For example, the values in a workstation file might have to be rounded to fit the AS/400 fields. Another example is the case where the record length of a workstation file differs from that expected by the AS/400.

If such an error occurs, an error message is issued with the number of the workstation file record for which the error occurred and, sometimes, information about certain fields in that record.

If a severe error occurs, data transfer may stop. In such a case, stop the transfer request, correct the error, then rerun the transfer request.

When the error is not so severe, you can request that the system continue transferring data. By doing so, even if the same error occurs in another record, an error message does not appear and the transfer function automatically continues executing the transfer request.

Creating an AS/400-to-Workstation Transfer Request

To create a transfer request to receive data from the host, do the following.

1 Select the **Data Transfer** icon.

2 When the PC→AS/400 Transfer window is displayed, select **Switch to RECEIVE** to switch the display to the AS/400→PC Transfer window.

For the additional settings, select the **Advanced** button.

3 Which items are to be specified by the user vary with the data type, as follows:

Entire AS/400 file
Part of an AS/400 file
Data combined from several AS/400 files
Summary of record groups

Before specifying each item, while referring to “Items to Be Specified” on page 17-19, note the following points regarding the data to be received.

Receiving an Entire AS/400 File

This is the simplest way of transferring data from the AS/400 to a workstation. All records in a file and all the data in each record are transferred.

The **FROM** items that must be specified are described below.

System name:
This item specifies the name of the system.

Library/File (Member):
This item specifies the name of the AS/400 file.

SELECT: Specifying an asterisk (*) for this item indicates that all fields are to be transferred, or lists all the fields in the AS/400 file.

ORDER BY:
This item is optional. It specifies how records will be grouped. When this item is left blank, records are not grouped (data is transferred in the same order it appears in the AS/400 file).

Receiving Part of an AS/400 File

Only part of an AS/400 file is transferred to the workstation.

The **FROM** items that must be specified are described below.

System name:
This item specifies the name of the system.

Library/File (Member):
This item specifies the name of the AS/400 file.

SELECT: This item specifies a field to be transferred.

WHERE: This item specifies the requirements that must be satisfied before records can be selected for transfer.

ORDER BY:
This item is optional. It specifies how records will be grouped. When this item is left blank, records are not grouped (data is transferred in the same order it appears in the AS/400 file).

Receiving Data Combined from Several AS/400 Files

The data to be transferred can be stored in two or more AS/400 files. These files are assumed to be related. Based on this relationship, they can be linked or *joined*, as if all the data existed in a single file. The files can be transferred to the workstation after they have been joined. By using the AS/400-to-PC transfer function, this "join and transfer" function can be performed in a single step.

The **FROM** items that must be specified are described below.

System name:
This item specifies the name of the system.

Library/File (Member):
This item specifies the names of all AS/400 files from which data is to be transferred.

JOIN BY: This item specifies how to join or combine the data in each file.

SELECT: This item specifies a field to be transferred.

WHERE: This item specifies the requirements that must be satisfied before records can be selected for transfer.

ORDER BY:
This item is optional. It specifies how records will be grouped. When this item is left blank, records are not grouped (data is transferred in the same order as it appears in the AS/400 file).

Receiving a Summary of Record Groups

A summary record is a single record that includes information on each set of records grouped from one or more AS/400 files.

The **FROM** items that must be specified are described below.

System name:
This item specifies the name of the system.

Library/File (Member):
This item specifies the names of all files from which data is to be transferred.

JOIN BY: This item is optional. It specifies the join conditions that must be satisfied before records can be joined.

GROUP BY:
This item is optional. It must be specified only when the records of AS/400 files are classified into several groups. To group all records into a single group, this item need not be specified.

SELECT: Specifying this item causes a summary record to be created. The field names specified in **GROUP BY** can be specified.

WHERE: This item is optional. It specifies the requirements that each record to be grouped must satisfy. To group all records, this item need not be specified.

HAVING: This item is optional. It specifies the summary record to be transferred. To transfer all summary records, this item need not be specified.

ORDER BY:
This item is optional. It specifies how summary records will be grouped. When this item is left blank, records are not grouped (data is transferred in the same order as it appears in the AS/400 file).

Items to Be Specified

The following explains the items to be specified using the AS/400→PC Transfer window. Those items that can be specified by selecting **Advanced**, are identified by adding "(Advanced)" to the end of those item names.

FROM

System name

This item specifies the name of the host system that contains the data to be received. When the router program is active, this item specifies the default system name.

Library/File (Member)

This item is always required. It specifies the name or names of one or more files used to store data to be transferred. Up to 32 file names can be specified. To specify several files, delimit them with commas and use **JOIN BY**, displayed after all **FROM** items have been specified. Only the file name must be specified. Do not specify a comma as a part of a file name. When the other optional items are not specified, they are assumed automatically. For example, the library name, member name, and format name can be assumed to be ***LIBL**, ***FIRST**, and ***ONLY**, respectively. When the cursor is on the input field of the **FROM**, selecting **Browse** lists libraries, files, members, and formats.

Note: To transfer data from an AS/400 physical file, you must have ***USE** authority for that file. To transfer data from an AS/400 logical file, you must have ***OBJOPR** authority for that file and ***READ** authority for each subordinate file.

Specify as follows. (Items inside brackets [ ]can be omitted.) To specify several file names, delimit the names with commas.

[*library-name*/]*file-name*[(*member-name*[,*record-format-name*])],
[*library-name*/]*file-name*[(*member-name*[,*record-format-name*])],...

library-name
This is the name of the AS/400 library that contains the AS/400 file to be transferred. This AS/400 file contains the data to be transferred from the AS/400 to a workstation. If this library name is not specified, ***LIBL** is assumed. If you cannot find the desired library, selecting **Browse** displays a list of all libraries defined in ***USRLIBL** of the AS/400 job library list.

***USRLIBL** of the library list can be changed by modifying the job description by executing the **CHGJOBD** command on the AS/400.

file-name

This is the name of the AS/400 physical file, logical file, or DDM file from which data is transferred. This file name must always be specified. To specify a file name and library name concurrently, delimit them with a slash (/). If you cannot find the desired file name, enter the library name followed by a slash, then select **Browse**. The system then displays a list of files contained in that library. To display a list of all the files in the libraries defined in ***USRLIBL** of the AS/400 job library list, enter ***USRLIBL**/, then select **Browse**.

member-name

This is the name of the AS/400 member containing the data to be transferred, or ***FIRST**. If this member is not specified, the system assumes ***FIRST**, and the first member of that file is used.

record-format-name

This is the name of the record format contained in the specified AS/400 file, or ***ONLY**. Before specifying the record format name, specify the member name or ***FIRST**. If the record format name is not specified, the system assumes ***ONLY**, and the only record format for that file is used. To specify a record format name, delimit the record format name and member name with a comma.

When the specified AS/400 file has several record formats, a record format name must be specified. If the file member name is not specified, a record format name cannot be specified.

Notes:

1. A library name, file name, file member name, and record format name can be specified using up to 10 characters for each. Each name must begin with A to Z, ¥, #, or @. For characters subsequent to the first, 0 to 9, underscores, and periods can also be used.
2. When the **FROM** field remains blank or a comma is entered to specify the next file name, selecting **Browse** displays a list of libraries defined in ***USRLIBL** of the AS/400 job library list.
3. Enter part of the file name, member name, or record format name, followed by an asterisk (*), then select **Browse**. The system displays a list of names beginning with the specified characters.

Example: You might want to transfer data from file member **ITEMMBR1** (first member) of file **ITEMMAST** in library **ITEMLIB**. **ITEMFMT** is the only record format of this file. The specification will be as follows:

ITEMLIB/ITEMMAST(ITEMMBR1,ITEMFMT)

Alternatively, specify the following:

ITEMLIB/ITEMMAST

JOIN BY (Advanced)

When several files have been specified in **FROM**, specify **JOIN BY**. When only one file has been specified in **FROM**, **JOIN BY** does not appear.

JOIN BY specifies how to link or join the records of the files specified in **FROM**. Each file specified in **FROM** must be joined with at least one other file that has been specified in **FROM**.

Use **JOIN BY** to specify one or more join conditions. The join conditions indicate the similarity of two files. Therefore, they indicate which records of one file are joined with those of another.

The join conditions are as follows:

field-name = field-name

Field name is the name of the field defined in the record format specified in **FROM**. The join conditions require two field names, one for each file to be joined.

Field names must be delimited by one of the following:

=	Equal
<> or ><	Not equal
>	Greater than
>=	Greater than or equal to
<	Less than
<=	Less than or equal to

When specifying fields in **JOIN BY**, observe the following rules.

Join a numeric field to another numeric field. The field lengths and types do not have to be identical.

Join a character field to another character field. The lengths do not have to be identical.

The field name to be specified might have been defined in the files specified in **FROM**. When such a field name is used in the following items, prefix the field name with the file qualifier:

JOIN BY
GROUP BY
SELECT
WHERE
HAVING
ORDER BY

The file qualifier is the character T (uppercase or lowercase) followed by a one- or two-digit number. Use T1 for fields defined with the first record format, T2 for fields defined with the second record format, and so on. Delimit the file qualifier and field name with a period (.). See “Receiving Records Using File Qualifiers” on page 17-39 for details of the file qualifiers.

If the field name of the file specified in **FROM** cannot be found, select **Browse** when the cursor is positioned to the **JOIN BY** input area. Then, a list of file qualifiers and field names of the files appears.

To join three or more files, or to join two files based on two or more common fields, two or more link conditions must be used. To specify several join conditions, join the conditions with AND. For example:

```
T1.EMPNO = T2.EMPNO AND T2.EMPNO = T3.EMPNO
```

In this case, records having the same value as **EMPNO** are joined between the first and second files specified in **FROM**. Then, such records are joined between the second and third files specified in **FROM**.

Up to 32 join conditions can be specified.

After **JOIN BY** is specified, each of **SELECT**, **WHERE**, and **ORDER BY** can be completed, by following the procedure described earlier in this chapter. To browse a field name that has been defined in several files, prefix the field name with a file qualifier.

GROUP BY (Advanced)

This item is required only to classify AS/400 file records into several groups. When no value is specified in **GROUP BY**, all the records are treated as a single group.

If **GROUP BY** is not displayed, select **Group functions** at the bottom right of the screen. Then, **GROUP BY** appears. **GROUP BY** and **HAVING** are displayed concurrently. You can specify either, both, or neither.

When **GROUP BY** and **HAVING** are displayed but you do not want to specify either, select **Remove Group functions**. The two items disappear.

To classify several records into groups, specify one or more fields to act as the base for grouping. Records are grouped according to the field specified first, then by the field specified second, and so on. For example, suppose that the following is specified:

```
SHIFT, DEPTNO
```

In this example, the records are first grouped by **SHIFT**. Records belonging to a single group will subsequently have the same value as **SHIFT**. Then, the records in each group are grouped by **DEPTNO**. When there is only one record having a certain **SHIFT** value, the group has only one record.

Delimit field names with commas. Blanks can be specified to improve readability. Up to 50 field names can be specified. These fields must have been defined in the record format defined in **FROM**.

If a field cannot be found, selecting **Browse** displays a list of all the fields contained in the record.

With **GROUP BY** specified, specify **SELECT** to transfer the summary record of each group.

SELECT (Advanced)

This item is always required. It specifies the field to be transferred or the function that indicates the type of summary information to be transferred.

The field to be specified must have been defined in the record format specified in **FROM**.

To transfer all the fields in the specified record, specify an asterisk (*) in this input field. (Specifying an asterisk causes all fields in the record to be transferred.)

Note: Up to 256 fields can be transferred. When more than 256 fields have been defined in a file, an asterisk cannot be used. In this case, specify the names by selecting the fields to be transferred.

To transfer fields by selecting from a record, enter the field names in the order in which the fields are arranged. One or more blanks can be placed between the field names to improve readability. However, the names must be delimited by commas, as follows:

ITEMNO, QONHAND, PRIC

You can also specify the following:

ITEMNO,QONHAND,PRICE

When records are transferred from an AS/400 source file, specifying an asterisk (*) causes all fields in the file to be transferred, with the exception of the order number field and date field. (To transfer all the fields, including the order number field and date field, specify all the field names, including each data field name.)

A field can be specified repeatedly as required. However, bear in mind that no more than 256 fields can be selected. A list of field names can be displayed by selecting **Browse**.

Receiving a Summary of Record Groups:

The following information is necessary to receive summary records.

To transfer a summary record, do not leave this input area blank or specify an asterisk (*) (except when all the fields of the file specified at the prompt are specified in **GROUP BY**). The field names specified in **SELECT** (except for those specified in functions) must also have been specified in **GROUP BY**.

The functions and fields specified in **SELECT** return actual summary information for each group. Enter the field names and functions in **SELECT** in the order in which they are to be displayed.

Note: Null values are not included in the functions. When an entire value is null, the function output is set to null, except for **COUNT**. The **COUNT** output is 0.

The function format is as follows.

function (field-name)

This has the following meaning:

function:

This is one of the following:

AVG Transfers the average value of the specified fields for each record group. This function can be used only for numeric fields.

MIN Transfers the minimum or lowest value of the specified fields for each record group.

MAX Transfers the maximum or highest value of the specified fields for each record group.

SUM Transfers the total value of the specified fields for each record group. This function can be used only for numeric fields.

COUNT Transfers the total number of records that satisfy the **WHERE** condition for each record group. Specify **COUNT(*)**.

field-name:

This is the field name defined with the record format specified in **FORM**.

Each function returns one value for each record group. In **SELECT**, several functions can be specified. To do so, delimit the functions by commas, as follows:

SUPPNO, AVG(PRICE), MIN(PRICE), MAX(PRICE)

This indicates that the average, minimum, and maximum values for **PRICE** are calculated for each supplier after **SUPPNO** has been selected. A summary record is transferred according to the function selection. Specify **SUPPNO** in **GROUP BY**, because **SUPPNO** has not been used for the functions.

WHERE (Advanced)

This item is optional. It specifies one or more conditions that records to be transferred must satisfy.

To transfer summary records, use this item to specify which records are to be grouped, then group the records. Using this item, you can specify one or more conditions that the record must satisfy to belong to a certain group. When **WHERE** is not specified, all records are grouped.

As the *conditions*, specify the test to be applied to the records in the specified file member. All the records in the specified file member are tested for the conditions specified here. Only those records that pass this test are transferred.

When **WHERE** is not specified, all records in the specified file member are transferred.

The condition format is as follows:

field-name test value

field-name:

This must be a field substring or field name defined in the record format.

Fields or constants can be manipulated by specifying a supported function, with the results being used for comparison. The supported functions and usage are as follows:

SUBSTR Returns the specified part of a character string. This function contains three parameters: the field name, starting position, and length of the returned substring.

The following example returns the 20 characters starting from the 10th character of the **FULLNAME** field.

SUBSTR(FULLNAME 10 20)

VALUE Returns the first non-null value in the parameter list. (If all parameters are null, null is returned.)

VALUE(DEPOSIT WITHDRAW BALANCE)

CURRENT Returns **DATE**, **TIME**, **TIMEZONE**, or **TIMESTAMP** for the current system.

CURRENT(TIMEZONE)

DIGITS Returns a character string representation of a numeric field.

DIGITS(EMPLOYEE#)

CHAR Returns a character string representation of the date field, time field, or time-stamp field. The second parameter is used to specify the format of the Systems Application Architecture (SAA) of the string to be returned (supported values are **USA**, **EUR**, **ISO**, or **JIS**).

CHAR(DATEHIRE USA)

DATE Returns the date of the time-stamp field.

DATE(TIMECRTD)

TIME Returns the time of the time-stamp field.

TIME(TIMECRTD)

TIMESTAMP Returns the time-stamp, combining the date field and time field.

TIMESTAMP(DATESEND TIMESEND)

YEAR Returns the year of the date field or time-stamp field.

YEAR(DATEHIRE)

MONTH Returns the month of the date field or time-stamp field.

MONTH(DATEHIRE)

DAY Returns the date of the date field or time-stamp field.

DAY(DATEHIRE)

DAYS Returns the day of the year, counted from January 1, of the date field or timestamp field.

DAYS(DATEHIRE)

HOUR Returns the time of the time field or time-stamp field.

HOUR(TIMESEND)

MINUTE Returns the minute of the time field or time-stamp field.

MINUTE(TIMESEND)

SECOND Returns the second of the time field or time-stamp field.

SECOND(TIMESEND)

MICROSECOND Returns the microsecond of the time field or time-stamp field.

MICROSECOND(TIMECRTD)

test: This is the comparison type to be applied to fields or functions.

The following tests can be used. One or more blanks can be placed before and after these tests.

=	Equal
<> or ><	Not equal (See the note.)
>	Greater than
>=	Greater than or equal to
<	Less than
<=	Less than or equal to
LIKE	The field is similar to the specified value.
BETWEEN	The field is equal to one of two constants, or to a value between them.
IN	The field is the same as one of the values in the constant list.
IS	The field contains null values.
ISNOT	The field contains no null values.

Using the **LIKE** Test

The **LIKE** test checks the field specified with the field name for a character pattern specified as a value. The field to be specified must be a character field.

The values to be tested must be character-string constants. This string can contain any characters. A percent (%) character (both SBCS% and DBCS%) indicates a character string consisting of zero or more characters. A 1-byte underscore (_) character indicates any single 1-byte character. A 2-byte underscore (_) character indicates any single 2-byte character.

The following example explains how to use the **LIKE** test:

```
NAME LIKE '%ANNE%'
```

The previous example searches for names containing character string **ANNE**, such as **ANNE**, **ANNETTE**, and **SUZANNE**.

The following example searches for names beginning with character string **ANNE**, such as **ANNE** and **ANNETTE**.

```
NAME LIKE 'ANNE%'
```

The following example searches for names ending with character string **ANNE**, such as **ANNE** and **SUZANNE**.

```
NAME LIKE '%ANNE'
```

The following example searches for all names whose second character is A.

```
NAME LIKE '_A%'
```

The following example searches for all last names beginning with character J.

```
LSTNAM LIKE 'J%'
```

This has the same effect as the following example:

```
SUBSTR (LSTNAM,1,1) = 'J'
```

When the pattern does not include a percent character (%), the length of the character string must be identical to that of the field.

Note: Values are searched according to the exact characters specified by the user. In other words, when the user's specification consists only of uppercase characters, only uppercase character strings are returned. Similarly, when the specification consists only lowercase characters, only lowercase character strings are returned.

Using the **BETWEEN** Test

The **BETWEEN** test checks the fields specified in the field name for character strings or numeric values that are equal to or between the specified constants. The values to be tested must be two character-string constants or two numeric constants. The types of these constants must be identical to that of the field name specified by the user. Delimit the two constants with **AND**.

The following example searches for those records for which the price is between 50.35 and 75.3, inclusive:

```
PRICE BETWEEN 5 .35 AND 75.3
```

The following example searches for those records for which the name begins with C:

```
NAME BETWEEN 'C' AND 'CZZZZZZZZZ'
```

The following example searches for those records for which the balance is between 0 and 5 000.

```
BALDUE BETWEEN   AND 5
```

This has the same meaning as the following expression.

```
BALDUE >=   AND BALDUE <= 5
```

Note: Specify the values to be tested in the form of **BETWEEN** (minimum) **AND** (maximum). For instance, **BETWEEN 1 AND 1** is a valid specification. However, **BETWEEN 1 AND 1** returns no records.

Using the **IN** Test

The **IN** test checks the fields specified in the field name for the character strings or numeric values in the list specified as the value. The value to be tested must be a list of character-string constants or numeric constants. In addition, the types of these constants must be identical to that of the specified field. Delimit the constants with blanks and enclose them in parentheses. Up to 100 constants can be specified. The following example shows how to use the **IN** test:

```
NAME IN ('SMITH' 'JONES' 'ANDERSON')
```

The above example searches for those records for which the name is **SMITH**, **JONES**, or **ANDERSON**.

The following example searches for the values in the **STATE** field for which the value is other than **NY**, **MN**, or **TX**:

```
NOT STATE IN ('NY' 'MN' 'TX')
```

Note: Values are searched according to the exact characters specified by the user. In other words, when the user's specification consists of only uppercase characters, only uppercase character strings are returned. Similarly, when the specification consists of only lowercase characters, only lowercase character strings are returned.

Using the **IS** Test

The **IS** test checks the fields specified in the field name for null values.

The following example searches for those records for which the commission field contains null values:

```
COMMISSIONS IS NULL
```

Using the **ISNOT** Test

The **ISNOT** test checks the fields specified in the field name for non-null values.

The following example searches for those records for which the commission field does not contain null values:

```
COMMISSIONS ISNOT NULL
```

In the test, logical **AND** and logical **OR** can be combined. When both **AND** and **OR** are specified, **AND** comparison is performed first. Up to 50 conditions can be specified. For example:

```
MONTH=2 AND LOC='MIAMI' OR LOC='CHICAGO'
```

In this example, each record to be selected must satisfy the following condition:

```
MONTH=2 AND LOC='MIAMI'
```

or must satisfy the following condition:

```
LOC='CHICAGO'
```

This command can be modified by using parentheses. For example:

```
MONTH=2 AND (LOC='MIAMI' OR LOC='CHICAGO')
```

In this example, each record to be selected must satisfy the following condition:

```
MONTH=2
```

and it must satisfy the following condition:

```
LOC='MIAMI' OR LOC='CHICAGO'
```

NOT can also be used. The following shows an example where data is transferred not only from those records in which the **DEPT** field is not equal to 470, but also from those records for which the **DEPT** field is equal to 470 and, additionally, **STATE** is equal to **NY**.

```
NOT (DEPT = 47 ) OR (DEPT = 47  AND
   STATE = 'NY')
```

Comparison can start from a certain line and end at the next line. However, a field name cannot start from a certain line and end at the next line. Field names must not exceed one line.

When a value to be tested is a character string enclosed in quotation marks, the value can start from a certain line and continue to the next line.

value Field names or constants can be specified as values. To use constants, enclose number or character strings in single quotation marks.

Note: Do not specify commas between numbers because the system recognizes these as decimal points.

When a character field or substring is specified in the field name, the character field name or character string constant must be specified as the *value*. If the field length differs from the value length, the shorter field is extended to the value length by adding blanks on the right.

When a numeric field is specified as the field name, a numeric field name, numeric constant, or expression must be specified as the *value*. The transfer function performs decimal alignment for numeric fields prior to comparison. Zeros are added wherever numeric values are missing.

When a date field is specified in the field name, the name of a date field, character field (when the **CHAR** function is used for date field conversion), or character string constant must be specified as the *value*. To use the character string constant, use a value in a form other than SAA (**USA**, **EUR**, **ISO**, or **JIS**).

Using Constants

A character string, numeric value, or keyword **NULL** can be specified as a constant.

Note: **NULL** can be used only when operators **IS** and **ISNOT** are used.

Using Character Strings

A character string must be enclosed in apostrophes, as follows:

'JOHN'

Use two apostrophes to represent one apostrophe in a character string, as follows:

'JOHN''S'

Note: The transfer function supports only right apostrophes (').

When a character string is shorter than the specified field, the string is extended to the value length by adding blanks on the right. When a character string is longer than the specified field, the string is truncated.

Values are searched according to the exact characters you specified. In other words, when your specification consists only of uppercase characters, only uppercase character strings are returned. Similarly, when the specification consists only lowercase characters, only lowercase character strings are returned.

A character string can also be specified in hexadecimal format. In this case, enter X. Then, enter the character string, enclosed in apostrophes, using EBCDIC hexadecimal representation. For example:

X'D1D6C8D5'

If the character string contains any characters that cannot be represented, hexadecimal representation can be used. A character string can also be specified using DBCS representation, enclosed in apostrophes (DBCS mixed, DBCS exclusive, or DBCS alternative). In this case, first enter G. Then, enter the DBCS string, enclosed in apostrophes. For example:

G' D B C S'

A character string can also be specified using DBCS graphic representation. In this case, first enter N. Then, enter the DBCS string, enclosed in apostrophes. An example is given below.

N' D B C S'

Using Numeric Values

A numeric value can contain an optional sign (+ or –) and optional decimal point. Either a period (.) or comma (,) can be used to represent a decimal point. For example:

.5
-. 5
1 .
+5.

Decimal alignment is performed prior to numeric field comparison. Zeros are added where numeric values are missing.

Using Expressions

An expression can contain numeric field names, numeric constants, parentheses, and the following arithmetic operators:

+ Plus sign (addition)

– Minus sign (subtraction)

* Multiplication

/ Division

For instance, the following expression searches for those records for which the number of products in stock (**ONHAND**) is at least 500 greater than the number of ordered products (**ONORDER**).

ONHAND > ONORDER + 5

The following expression searches for those records for which the price is 1 000.

PRICE = (1 . 1)

HAVING (Advanced)

This item is optional. It specifies which summary record is transferred.

Pay particular attention to the difference between **HAVING** and **WHERE**. **WHERE** operates on each record within a certain group. **HAVING**, on the other hand, operates only on summary records (records that contain summary information for each group).

With this item, you can specify one or more conditions that a summary record must satisfy prior to being transferred.

As the conditions, specify the tests that should be applied to the summary records. The specified test conditions are applied to all summary records, only those summary records that pass the tests are transferred. To transfer all summary records, leave the **HAVING** item blank.

The format of the conditions is as follows:

function (field-name) test value

This indicates the following:

function
This is a function supported for **SELECT**. See the description of **SELECT** in this section for details of these functions.

field-name
This is the field defined by the record format specified in **FROM**. A field name is acceptable even when it has not been specified in **SELECT**.

Test
This is the comparison type for functions. The types are listed below.

=	Equal to
<> or ><	Not equal
>	Greater than
>=	Greater than or equal to
<	Less than
<=	Less than or equal to

value
This is a function operating on certain fields or a constant. See “WHERE (Advanced)” on page 17-26 for details of constants, expressions, and tests.

Note: A comma is treated as a decimal point. Therefore, do not separate numbers with commas.

Test conditions can be combined by using logical **AND** or logical **OR**. When both **AND** and **OR** are specified, **AND** comparison is performed first. Up to 50 tests can be specified. By using parentheses, the operation order can be modified, or a description can be added to an operation. For example, you can specify the following:

COUNT( ) >=2 AND MAX(PRICE) > 1

In this case, the following conditions are applied concurrently: groups to be transferred must contain more than one record, and the summary records in such groups are transferred only when the maximum price is greater than 100.

If the desired field cannot be found, selecting **Browse** displays a list of the names of all fields in the record.

The type, length, digit, and number of decimal places of the value returned for each function are listed below.

	Type	Length	Digit	Decimal Places
SUM	Packed	16	31	(Same as tested field)
AVG	Packed	16	31	31 (Total of the digit and decimal places of the field)
COUNT	Binary	4	1	
MAX	(Same as tested field)			
MIN	(Same as tested field)			

ORDER BY (Advanced)

This item is optional. It specifies the order in which the requested records are grouped. When **ORDER BY** is not specified, record transfer is not done according to a certain order.

Records are grouped according to the field specified first. Those records having the same value in each field specified first are grouped by the field specified second, and so on. Records containing null values are grouped after all records without null values have been grouped.

For example, you can specify the following:

```
DEPT,NAME,PHONE
```

In this case, records are first grouped according to **DEPT**. Then, the records having the same value for **DEPT** are grouped by **NAME**. The records with the same **DEPT** and **NAME** values are finally grouped by **PHONE**.

When a field name is specified in **ORDER BY**, it must also have been specified in **SELECT**, or **SELECT*** must have been specified.

Fields can be grouped in ascending or descending order. To do this, specify one blank after a field name then enter **ASC** or **DESC**. The default value is **ASC**. For example, specify the following:

```
DEPT DESC, NAME ASC
```

This indicates that the **DEPT** fields are to be grouped in descending order, after which the **NAME** fields are to be grouped in ascending (alphabetic) order.

Absolute values (**ABS**) can be specified for numeric fields. To do this, add a blank after a field name then enter **ABS**. For those fields having negative values, the negative signs are ignored and the absolute values are used.

The total length of the fields to be specified must not exceed 120 digits.

Return Record at Missing Field Value (Advanced)

When joining records from several files, joining might fail because a record is missing. This item specifies whether records with missing fields are transferred.

When you specify that records with missing fields are to be transferred, the alternative values for the missing fields are transferred. These values are normally blanks for character fields and zeros for numeric fields.

When you do not specify transfer of records with missing fields, those records are not transferred.

Specify this item to transfer data records that have alternative values for missing fields.

Do not specify this item if data records that have alternative values for missing fields are not to be specified. In this case, only those data records created from those records that exist in all files specified in **FROM** are transferred.

TO

Output device

This item specifies where received data is to be sent.

Display The received data is displayed on the screen.

Disk The received data is written to a workstation diskette or hard disk file.

Printer The received data is printed on the printer.

When **Disk** is selected as the output device, also specify the following items.

PC file

This item specifies the name of the workstation disk file or diskette file to which the data is to be written.

Replace old file

This item is always required. It specifies whether the records in the file specified by **PC File** are to be replaced with the transferred records.

The default value is **Replace old file**.

Workstation file type

This item is always required. It specifies the type of the workstation disk file or diskette file to which the transferred records are written.

The system default is PC code test.

Save transfer description

This item is always required. It specifies whether the workstation file description is written to a workstation file. This file description describes the transferred data and it is required to subsequently return data to the AS/400.

The system default is **Save**.

Description file name

This item is always required. It appears only when **Save Transfer Description** is selected. The **File Description File Name** specifies the name of the workstation disk file or diskette file to which the file description is written.

This item automatically sets the desired file name. This file name is the same as that specified by the user for **TO**, but to which extension **.FDF** has been added. Extension **.FDF** indicates that this file is a file description file.

The use of extension **.FDF** is recommended when using a unique file name. To specify a file name in this item, use the same format as that in **TO**. (Items inside brackets [ ] can be omitted.)

[*d*:][*path-name*]*file-name*[*.ext*]

After **Save File Description File** is specified or a name is specified for **File Description File Name**, the AS/400→PC Transfer Request window

reappears after the **Return** key is pressed. Using this screen, a transfer request can be changed, saved, or executed.

Saving, Opening, Changing, and Executing a Transfer Request

The following section explains how to save, open, change, and execute, as a file, the information (transfer request) on the data to be transferred.

Saving a Transfer Request

You should save a transfer request, especially when the request will be executed repeatedly. This eliminates the need to create a transfer request every time a request is executed. To save a transfer request, do the following.

1. Specify the information needed for transfer, using the AS/400→PC Transfer window. See “Creating an AS/400-to-Workstation Transfer Request” on page 17-17 for an explanation of how to specify the required data.
2. After specifying the necessary data, select **Save** or **Save As** from the **File** menu of the menu bar.

   The Save Transfer Request File As window appears.
3. Specify each item, referring to the following explanation, then select **OK**.

   File Name Disk to which data is to be saved. Specify a file name or diskette file name. The default extension is TTO. Extension TTO identifies a file as a transfer request file.

   Description This item can be used to add a short explanation of a transfer request, as required. The explanation can be up to 40 characters in length. This explanation is saved with the transfer request, and displayed in the list of transfer request names. It is useful, therefore, for identifying a transfer request.
4. The system asks whether the saved transfer request is to be registered in the PC400 folder.

   When **OK** is selected, the transfer request is registered as an icon. Subsequently selecting this icon transfers data according to the registered data transfer request.

Opening and Changing a Saved Transfer Request

The following explains how to open and change a saved transfer request.

1. Display the AS/400→PC Transfer window.
2. Select **Open** from the **File** menu of the menu bar.

   The Open Transfer Request File window appears.
3. Specify the name of the file to be opened using the Open Transfer Request File window, Then select **OK**.

   The AS/400→PC Transfer window reappears, with the information specified for each item for the transfer request displayed. This completes opening of the saved transfer request.
4. Change the contents, as necessary.
5. To save the changed contents, follow the procedure given in “Saving a Transfer Request.”

Executing a Transfer Request

A transfer request can be executed in one of the following three ways:

By using the OS/2 command prompt

By selecting the icon with which the transfer request has been registered

By using the AS/400→PC Transfer window of the Data Transfer icon

The following describes each method:

Using the OS/2 Command Prompt:

By referring to "Data Transfer Program" on page 17-6, execute the program **PCSFT5.EXE**, specifying the saved transfer request file name as a parameter.

Selecting the Icon with Which the Transfer Request Has Been Registered:

This method can be used only when a transfer request has been saved as an icon by using the AS/400→PC Transfer window.

Data transfer starts as soon as you select the icon with which a transfer request has been registered.

Using the* AS/400→PC Transfer *Window:

1. Before attempting to execute a transfer request, all operations such as creating, opening, and changing a transfer request must have been completed.

   Note: When data is transferred from a workstation to an existing member in an AS/400 file, the transferred data replaces the existing data in the member.

2. Select **Receive** from the AS/400→PC Transfer window.

   Data transfer starts.

3. After the transfer has been completed, select the **Cancel** pushbutton, or select **Exit** from the menu bar **File** menu.

Status during Transfer

Display can be specified as the **output device**, when the current transfer request is created or changed. This sends the transferred record to the screen. On the screen, each record is displayed on one line.

Each field in a transferred record is converted from the AS/400 data type to workstation code.

Note: The workstation receives the AS/400 records in order and then writes them to a temporary file of the default directory in the default drive (usually, the directory in which PC400 is installed). The maximum number of records that can be transferred is 4096 records, limited by the amount of records that can be stored in free space of the default drive.

When **Disk** is selected as the **output device**, the following is performed:

1. The workstation file description is written to a workstation disk file or diskette file according to the **Save File Description File** specification. (If **Save File Description File** has not been specified, this procedure is not performed.)

2. The transferred records are written to a workstation disk file or diskette file.

Limited Usage of File Names and Field Names

For a transfer request from a workstation to the AS/400, none of the following reserved words can be specified as a file name or field name:

CRTFILE
CRTMBR
FILETEXT
FILETYPE
INTO
MBRTEXT
PUBAUT
RCDLEN
REFFILE

For a transfer request from the AS/400 to a workstation, none of the following reserved words can be used as a file name or field name:

ABS
AND
ASC
AVG
BETWEEN
BY
COLUMNS
COUNT
DESC
EXTRACT
FROM
GROUP
HAVING
IN
INNER
IS
ISNOT
LIKE
MAX
MIN
NOT
OPTIONS
OR
ORDER
PARTOUT
REPLACE
SELECT
SUBSTR
SUM
TABLES
WHERE

To use one of these reserved words as a file name or field name, use the reserved word in uppercase, enclosed in quotation marks. Here is an example:

```
TO MYLIB/"INTO"
```

Examples of Transfer Requests for Receiving

This section provides examples of transfer requests for receiving. The contents of this section provide supplementary information to help you better understand transfer requests for receiving.

This section describes how to transfer data from the AS/400, based on the inventory control file **INVENTORY** and supplier file **SUPPLIERS**.

he **INVENTORY** file contains information about the various parts in stock. Each part has a three-digit identification number, **PARTNUM**. The **INVENTORY** file contains the names of parts (**DESCRIPTION**) and the quantity on hand (**QONHAND**) for each part.

File: INVENTORY

Field name:	PARTNUM	DESCRIPTION	QONHAND
	-------	-----------	-------
Record 1:	2 9	CAM	5
2:	221	BOLT	65
3:	222	BOLT	125
4:	231	NUT	7
5:	232	NUT	11
6:	2 7	GEAR	75
7:	241	WASHER	6
8:	285	WHEEL	35
9:	295	BELT	85

The **SUPPLIERS** file contains information about the suppliers of each part. Each supplier is identified by a two-digit number, **SUPPNO**. The **SUPPLIERS** file contains the number of parts delivered (**PARTNO**), their prices (**PRICE**), times of delivery (**DELIVTIME**), and ordered quantities (**QONORDER**). The parts listed in the **SUPPLIERS** file are the same as those listed in the **INVENTORY** file.

File: SUPPLIERS

Field name:	SUPPNO	PARTNO	PRICE	DELIVTIME	QONORDER
	------	------	-----	---------	--------
Record 1:	51	221	.3	1	5
2:	51	231	.1	1	
3:	53	222	.25	15	
4:	53	232	.1	15	2
5:	53	241	. 8	15	
6:	54	2 9	18.	21	
7:	54	221	.1	3	15
8:	54	231	. 4	3	2
9:	54	241	. 2	3	2
1 :	57	285	21.	14	
11:	57	295	8.5	21	24
12:	61	221	.2	21	
13:	61	222	.2	21	2
14:	61	241	. 5	21	
15:	64	2 7	29.	14	2
16:	64	2 9	19.5	7	7

Receiving Part of an AS/400 File

Specify the following items:

Library/File (Member)	**INVENTORY**
SELECT	**PARTNUM, QONHAND**
WHERE	**QONHAND < 100**
ORDER BY	**PARTNUM**

In this case, only part of the **INVENTORY** file is to be transferred. Specifically, only the part number (**PARTNUM**) and quantity on hand (**QONHAND**) fields of the records for which the number of parts in stock is less than 100 (**QONHAND** < 100) are transferred. Records are transferred in ascending order of parts numbers (**PARTNUM**).

The following data is transferred:

Field:	PARTNUM	QONHAND
Record 1:	2 7	75
2:	2 9	5
3:	295	85

Receiving Records Joined from Several AS/400 Files

Two AS/400 files, **INVENTORY** and **SUPPLIERS**, are assumed. Note that both files contain records including part number fields. The **INVENTORY** file contains inventory information about individual parts. The **SUPPLIERS** file contains information about purchasing and ordering.

The user might want to transfer information on part numbers, part names, and the prices of the parts to be ordered from supplier 51. The desired fields are **PARTNO** (**SUPPLIERS** file), **DESCRIPTION** (**INVENTORY** file), and **PRICE** (**SUPPLIERS** file).

By comparing the data in the **INVENTORY** file and the **SUPPLIERS** file, the user can determine that supplier 51 provides part numbers 221 and 231, called **BOLT** and **NUT**, respectively, and that their prices are 30 cents and 10 cents, respectively. The following summarizes this information:

Field:	PARTNO	DESCRIPTION	PRICE
Record 1:	221	BOLT	.3
2:	231	NUT	.1

The same results are available by joining the data in these two files by using AS/400-to-PC transfer function. To do this, specify both files (**INVENTORY** and **SUPPLIERS**) in the **FROM** item. For **SELECT**, specify which fields are to be transferred (**PARTNO**, **DESCRIPTION**, and **PRICE**). For **WHERE**, specify which records are to be transferred (records for which **SUPPNO** = 51).

Respecify the relationship between the two files in **JOIN BY**. From the above results, the user can determine, by checking the **SUPPLIERS** file, that part number 221 is delivered from supplier 51 at a cost of 30 cents. In addition, to determine the part name, the user must check the **INVENTORY** file for part number 221 and its product name. In other words, the user observes that data is joined from the records in both the **SUPPLIERS** file and the **INVENTORY** file and that those records have the same part number. Therefore, to link the two records in these files, the records must have the same part number.

In short, to obtain the above information, specify the following:

Library/File (Member)	**SUPPLIERS, INVENTORY**
JOIN BY	**PARTNO = PARTNUM**
SELECT	**PARTNO, DESCRIPTION, PRICE**
WHERE	**SUPPNO = 51**
ORDER BY	**PARTNO**

Receiving Records Using File Qualifiers

To join records from several AS/400 files, fields of the same type must be joined.

For example, the part number fields in the **INVENTORY** and **SUPPLIERS** files can have the same name **PARTNO**. To specify the desired **PARTNO** fields, the user must specify which file contains those fields. To do so, File qualifiers are used.

A file qualifier is the character **T** (uppercase or lowercase) followed by a one- or two-digit number. A comma is used to delimit the file qualifier and field name. In the previous example, prefix **T1.** and **T2.** to the **PARTNO** field names. **T1.** indicates the first file of **FROM**, while **T2.** indicates the second.

To obtain the same information as above, specify the following:

Library/File (Member)	**SUPPLIERS, INVENTORY**
JOIN BY	**T1.PARTNO = T2.PARTNO**
SELECT	**T1.PARTNO, DESCRIPTION, PRICE**
WHERE	**SUPPNO = 51**
ORDER BY	**T1.PARTNO**

T1.PARTNO indicates the **PARTNO** fields in the **SUPPLIERS** file, while **T2.PARTNO** indicates the **PARTNO** fields in the **INVENTORY** file.

Qualifiers are not needed for the names of the **DESCRIPTION**, **PRICE**, and **SUPPNO** fields, because they exist in one file only. However, the user can specify the following for clarity:

T2.DESCRIPTION, T1.PRICE, T1.SUPPNO

The following examples of joining several AS/400 files describe more sophisticated techniques. You should now be familiar with the basics of how to join two files. For a more detailed explanation, refer to the following sections.

Receiving with Field Missing Records Joined

The joining of records from several files could fail because one or more records is missing. For example, the record containing part number 221 might not be found in the **INVENTORY** file. This means that the records that can be joined to the 1st, 7th, and 12th records in the **SUPPLIERS** file do not exist in the **INVENTORY** file. In this case, the **PARTNO** field and **PRICE** field for part number 221 can be determined, but the **DESCRIPTION** field cannot be determined. So, the **DESCRIPTION** field is missing.

To transfer field missing records, use **Return Record at Missing Field Value**.

When **Return Record at Missing Field Value** has been specified, the default AS/400 values are transferred instead of the missing field values. The default values for character fields are blanks, while those for numeric fields are zeros. For example, if the **INVENTORY** file does not contain the part number 221 record, the result of the previous example will be as follows:

	Field:	PARTNO	DESCRIPTION	PRICE
		------	----------	-----
Record	1:	221		.3
	2:	231	NUT	.1

If **Return Record at Missing Field Value** has not been specified, the field missing records are not transferred. For example, if the **INVENTORY** file does not contain the part number 221 record, the result of the previous example will be as follows:

Field:	PARTNO	DESCRIPTION	PRICE
Record 1:	231	NUT	.1

Receiving with Records in a Same File Joined

Records in the same file can be joined. In other words, a file can be repeatedly specified in **FROM**. For instance, data in certain records can be compared using this function.

For example, the **SUPPLIERS** file shows that several suppliers provide the same part. The user might want to know which supplier sets a price that is double, or greater than double, that of another. To transfer the necessary information to a workstation, specify the following:

Library/File (Member)	**SUPPLIERS, SUPPLIERS**
JOIN BY	**T1.PARTNO = T2.PARTNO**
SELECT	**T1.PARTNO, T1.SUPPNO**, **T1.PRICE**, **T2.SUPPNO**, **T2.PRICE**
WHERE	**T1.PRICE > 2 * T2.PRICE**
ORDER BY	**T1.PARTNO**

The same file has been specified in **FROM** twice. **JOIN BY** specifies that records having the same part number are joined. This creates a joined record containing information about two suppliers of a single part. The user can spot those records for which the price is double, or greater than double, that of another supplier.

Records in the **SUPPLIERS** file are compared, one by one, with all the records (including itself) in the **SUPPLIERS** file. When the same part number is found, the two corresponding records are linked. This processing is performed for each record in the **SUPPLIERS** file.

For each record, the first supplier's price is compared with the second supplier's price. When the first supplier's price is double, or greater than double, that of the second, only the record containing the first supplier price is kept.

The final result is as follows:

Field:	T1.PARTNO	T1.SUPPNO	T1.PRICE	T2.SUPPNO	T2.PRICE
Record 1:	221	51	.3	54	.1
2:	231	51	.1	54	. 4
3:	241	53	. 8	54	. 2
4:	241	61	. 5	54	. 2

Specifying Records to Be Included in a Group

You might want to limit which records will be included in a group. To do so, use **WHERE**. For example, the following transfers the average and lowest prices of each part for those records for which the delivery time (**DELIVTIME**) is less than 30 days.

Library/File (Member)	**SUPPLIERS**
GROUP BY	**PARTNO**

SELECT	**PARTNO, AVG(PRICE), MIN(PRICE)**
WHERE	**DELIVTIME < 30**

The result is as follows:

Field:	PARTNO	AVG(PRICE)	MIN(PRICE)
Record 1:	221	.25	.2
2:	231	.1	.1
3:	222	.23	.2
4:	232	.1	.1
5:	241	. 7	. 5
6:	2 9	18.75	18.
7:	285	21.	21.
8:	295	8.5	8.5
9:	2 7	29.	29.

Note that the conditions specified in **WHERE** are checked first, then the records that satisfy those conditions are included in the group.

Specifying Summary Records to Be Transferred

In some cases, you might want to transfer only summary records that satisfy certain conditions. The use of **HAVING** enables the selection of which summary records are to be transferred. **WHERE** is applied to certain records in a group, while **HAVING** is applied only to summary records.

The following example transfers the highest and lowest prices for each part. However, the summary records to be transferred are only those for which the highest price exceeds 10.00.

Library/File (Member)	**SUPPLIERS**
GROUP BY	**PARTNO**
SELECT	**PARTNO, MAX(PRICE), MIN(PRICE)**
HAVING	**MAX(PRICE) > 10.00**

The following shows the result of removing unnecessary summary records by using **HAVING**.

Field:	PARTNO	MAX(PRICE)	MIN(PRICE)
Record 1:	2 9	19.5	18.
2:	285	21.	21.
3:	2 7	29.	29.

One summary record for an entire file can be transferred. To do this, specify only the summary function in **SELECT** and nothing in **GROUP BY**. As a result, an entire file can be recognized as one group, while one summary record can be transferred for the group.

You can concurrently use the concept of summarizing groups and that of joining records from several files. To obtain the desired results, do the following.

1. Specify a file in **FROM**, and specify the join conditions to join the records in **JOIN BY**.
2. Specify the conditions in **WHERE** to remove unnecessary records.
3. Specify the fields used for grouping the remaining records in **GROUP BY**.

4. Specify the function in **SELECT**, then create summary records.
5. Specify the conditions in **HAVING** to remove unnecessary records.
6. Specify the items for grouping the final summary records in **ORDER BY**.

Functions Available from Pull-Down Menu

The following provides a simple explanation of the menu bar of the AS/400→PC Transfer window and PC→AS/400 Transfer window.

File

Transfer request files can be processed.

Create
This item creates a transfer request file.

Open
This item displays the contents of an existing transfer request file.

Save, Save As
These items save the current settings to the transfer request file being used or to a new transfer request file, respectively.

Exit
This item terminates the operation started by selecting the **Data Transfer** icon.

Setup (Only for AS/400→PC Transfer)

User options

Time, date, and numeric value format for receiving can be specified. The following describes each item.

Ignore Decimal Data Error
This item specifies whether decimal data errors found in packed or zoned decimal fields upon executing requests are to be ignored. Selecting **Yes** to ignore decimal data errors and using existing indices can considerably reduce the time needed to execute a request. If this item is not specified, the transfer request creates indices again and modifies any detected decimal data errors. This requires extra processing time.

Time Format
This item specifies a desired time format for fields of AS/400 field type having a selected time. If no time format is specified, the default value in the workstation's national information file is assumed when the transfer request starts, and that in an existing transfer request is assumed when the request is called again.

Supported time formats are as follows:

HMS	Hours, minutes, seconds (hh:mm:ss)
ISO	International Standard Organization (hh.mm.ss)
USA	USA Standard (hh:mm AM or PM)
EUR	IBM European Standard (hh.mm.ss)
JIS	Japanese Industrial Standard (hh:mm:ss)
DDS	AS/400 DDS (Format given by AS/400 file attribute)
DFT	AS/400 default format (Host job default is used)

Time separator

This item specifies enabled delimiters when fields of the AS/400 field type for the selected time are of the format type for which delimiters can be specified.

When no delimiters are specified, the default value in the workstation's national information file is assumed when the transfer request starts, and that in an existing transfer request is assumed when the request is called again.

Supported time delimiters are as follows:

Colon (:)
Period (.)
Comma (,)
Blank ( )
Null (NULL) No Separator
Default value
(DFT) AS/400 Default Separator

Date Format

Specifies the date format for fields of AS/400 field type for the selected date.

If this date format is not specified, the default value in the workstation's national information file is assumed.

Supported values are as follows:

MDY Month, day, year (mm/dd/yy)

DMY Day, month ,year (dd/mm/yy)

YMD Year, month, day (yy/mm/dd)

JUL Julian (yy/ddd)

ISO International Standard Organization (yyyy-mm-dd)

USA USA Standards (mm/dd/yyyy)

EUR IBM European Standard (dd.mm.yyyy)

JIS Japanese Industrial Standard (yyyy-mm-dd)

DDS AS/400 DDS (Format given by AS/400 file attribute)

DFT AS/400 default format (Host job default is used)

Date separator

This item specifies delimiters when fields of the AS/400 field type for the selected date are of the format type for which delimiters can be specified.

When no date delimiters are specified, the default value in the workstation's national information file is assumed when the transfer request starts, and that in an existing transfer request is assumed when the request is called again.

Supported date delimiters are as follows:

Slash (/)
Dash (-)
Period (.)
Comma (,)
Blank ( )

Null (Null) Delimiters are not used.
DFT (DFT) AS/400 default separator

Decimal separator
This item specifies the decimal point character in an AS/400 field whose type is packed decimal or zoned decimal.

When decimal points are not specified, the default value in the workstation's national information file is assumed when the transfer request starts, and that in an existing transfer request is assumed when the request is called again.

Supported decimal point delimiters are as follows:

Period (.)
Comma (,)
DFT (DFT) - Default decimal separator

Sort Sequence
Specify which sort sequence should be used for this transfer request.

AS/400 job default
Sort by the table identified on the AS/400 as the job sort table.
Hexadecimal
Sort by the internal hexadecimal representation.
User specified table
Sort by the table identified by the user in a subsequent prompt.
Shared Weight Table
Sort by the shared weight table associated with the language named in a subsequent prompt.
Unique Weight Table
Sort by the shared unique table associated with the language named in a subsequent prompt.

Changing the sort sequence affects the order in which records appear *only* if the **ORDER BY** clause is being used. The sort sequence affects all character comparisons that depend on the order of the alphabet . Such comparisons can occur in the **WHERE** clause, the **GROUP BY** clause, the **HAVING** clause, the **JOIN BY** clause, the **IN** predicate, the **LIKE** predicate, the **BETWEEN** predicate, the **MAX** function, and the **MIN** function. Comparison operations are =, <>, >, >=, and >=.

Sort Sequence Table Name
Type the name of the sort sequence table that you want to use for this transfer request. The format of the table name should be *library/table*. ***LIBL** and ***CURLIB** are allowed for the library name.

Language
AS/400 standard tables provided many languages. Select the user-specified languages to enter the desired language ID. Language IDs shipped with AS/400 are found in the *AS/400 NLS Guide*.

Language ID
Enter the language ID for the desired language.

AS/400 standard tables provided many languages. Language IDs shipped with AS/400 are found in the *AS/400 NLS Guide*.

Translation Table

Translation tables for ASCII-to-EBCDIC translation or for EBCDIC-to-ASCII translation can be specified, created, and customized. The following describes each item.

Current Table

This item specifies whether the IBM default translation or the user-defined translation table is to be used.

Host Code Page

This item specifies the host code page to be used for translation.

Workstation Code Page

This item specifies the workstation code page to be used for translation.

File Name

This item specifies the file name of the user-defined table to be used for translation.

To list all files in your workstation, select **Browse**.
To customize the translation table, select **Customize**.

File Description Files

The file description file is a workstation file that contains all field descriptions of the data in the corresponding workstation data file. Each field descriptor contains the field name, data type, and field length. There is one field descriptor for each field in the workstation file.

A file description file defines the following:

File type of the workstation file to be transferred. For an explanation of each file type, see “File Description Files” for details of how to create.

Field names and order of these fields in each data record.

Data type of each field in the workstation file.

Size and number of decimal places of each field.

The workstation files require field definitions when the files are transferred. The field definitions describe the file as it exists on the workstation. These definitions contain data that is similar to the field definitions (DDS) required by AS/400 system files. The data must be defined for both the AS/400 system and the workstation files, because the field names from each file are needed to send the data to the AS/400 system and the data in each file might be in different formats.

A file description file is created on request during the transfer process of data from an AS/400 file to a workstation file. Therefore, you usually do not need to worry about the contents or the format of the file description file. However, if you transfer data that has not been previously transferred to the system, you must create a file description file.

Creating a File Description File

You can create a file description file using a workstation text editor. The file description file must be an ASCII text file. Therefore, each record must end with a carriage return (CR) character (hex 0D) followed by a line feed (LF) character (hex 0A). All tab characters (hex 09) are treated as ASCII spaces. The last byte of the file must contain an end-of-file (EOF) character (hex 1A). workstation editors that create ASCII text files usually use these special character designators, so normally you do not need to be concerned about them.

File Description File Format

The format of the file description file is as follows:

```
PCFDF [comment]
PCFT file-type-indicator [comment]
PCFO time-format,time-separator, date-format, date-separator, decimal-separator [comment]
PCFL field-name-1 data-type-1 length-1[/decimal-position-1][comment]
    .
    .
    .
PCFL field-name-n data-type-n length-n[/decimal-position-n][comment]
[ comment]
```

Items within brackets are optional. Use either uppercase or lowercase characters anywhere in the file.

PCFDF Entries: PCFDF is a keyword that identifies this file as a workstation file description file. It must appear in the first line of the file, starting in column 1. A comment is the only other entry allowed on the first line. If you type a comment, it must be separated from the PCFDF keyword by a space.

PCFT Entries: PCFT is a keyword that identifies this record as containing the file type indicator. It is followed by an indicator identifying the type of file in which the data is stored. It must appear only once, and must start in column 1, after the PCFDF record and before any PCFL records. An optional comment can follow this file type indicator if separated from the indicator by at least one space.

Following is an example of a PCFT entry:

```
PCFT 4 BASIC RANDOM FILE
```

Table 17-1 shows the valid file type indicators.

Table 17-1 (Page 1 of 2). File Type Indicators

Indicator	File Type
1	ASCII text
2	DOS random
3	BASIC sequential
4	BASIC random
5	Data interchange format (DIF**)
6	No-conversion file
7	Reserved
8	DOS random type 2

Table 17-1 (Page 2 of 2). File Type Indicators

Indicator	File Type
9	BIFF format

PCFO Entry: The PCFO entry is optional. PCFO is a keyword that identifies this record as containing information about the date and time formats, time stamp, and separator characters for applicable formats. It must appear only once and must start in column 1, after the PCFT record and before any PCFL records. If there is no PCFO entry, the information or characters assigned as defaults for the host system are used.

Table 17-2 shows the valid time formats.

Table 17-2. Time Formats

Indicator	Format Name	Time Format
1	HMS	hh:mm:ss
2	ISO - International Standards Organization	hh.mm.ss
3	USA - USA standard	hh:mm AM or PM
4	EUR - European	hh.mm.ss
5	JIS - Japanese Industrial Standard Christian Era	hh:mm:ss
6	DDS	Format given by AS/400 file attribute
7	DFT	Host job default is used
*	Unspecified	Host job default is used

Table 17-3 shows the valid time separators.

Table 17-3. Time Separators

Indicator	Separator
1	Colon (:)
2	Period (.)
3	Comma (,)
4	Blank ( )
5	Null (N)
6	Default (D) (host job default)
*	Unspecified (host job default)

Table 17-4 shows the valid date formats.

Table 17-4 (Page 1 of 2). Date Formats

Indicator	Format Name	Date Format
1	MDY	mm/dd/yy
2	DMY	dd/mm/yy

Table 17-4 (Page 2 of 2). Date Formats

Indicator	Format Name	Date Format
3	YMD	yy/mm/dd
4	Julian	yy/ddd
5	ISO	yyyy-mm-dd
6	USA	mm/dd/yyyy
7	EUR	dd.mm.yyyy
8	JIS	yyyy-mm-dd
9	DDS	Format given by AS/400 file attribute
10	DFT	Host job default is used
*	Unspecified	Host job default is used

Table 17-5 shows the valid date separators.

Table 17-5. Date Separators

Indicator	Separator
1	Slash (/)
2	Dash (–)
3	Period (.)
4	Comma (,)
5	Blank ( )
6	Null (N)
7	Default (D) (host job default)
*	Unspecified (host job default used)

Table 17-6 shows the valid decimal separators.

Table 17-6. Decimal Separators

Indicator	Separator
1	Period (.)
2	Comma (,)
*	Unspecified (workstation default used)

Following is an example of a PCFO entry:

```
PCFO 1,1,1,1,1 OPTIONS SETTINGS
```

PCFL Entries: PCFL identifies a definition for a field. Enter a PCFL entry in the file description file for each field in the data file. The PCFL records must be in the same order as the fields they define in the data file.

Define as many as 256 PCFL records in the file description file and start PCFL records in column 1. If you enter more than 256 PCFL records, you receive an error message. You cannot continue a record on one line, and only the first 80 characters of a record are used.

Following is an example of a PCFL entry:

```
PCFL CUSTNAME 1 2     CUSTOMER NAME
```

Each PCFL entry contains the following things:

The keyword, PCFL, starting in column 1 and followed by a space. This identifies the record as a field description.

The field name, followed by a space. This must match the name that exists in the field definitions on the AS/400 system and can be from 1 to 10 characters.

The indicator for the data type. Table 17-7 shows the indicators that represent the data type of the data that exists in the field. Follow the specified indicator with a space.

The size of the field (in bytes) as it is stored in the workstation file. The length specification can be from 1 to 4 characters.

Table 17-7. Data Type Indicators

Indicator	Data Type
1	ASCII[1]
2	ASCII numeric
3	Hexadecimal
4	Binary
5	Zoned
6	Packed
7	BASIC integer
8	BASIC single-precision floating point
9	BASIC double-precision floating point
10	EBCDIC
11	EBCDIC zoned
12	EBCDIC packed

Note:

1 Includes date, time, and time stamp except for files that are not converted.

The data type indicator you enter must be valid for the file type entered earlier. Any other data types are not valid and are diagnosed as errors during a data transfer to the AS/400 system.

Table 17-8 shows the valid single-byte character set (SBCS) data types for each file.

Table 17-8 (Page 1 of 2). Valid SBCS Data Types for File Types

File Type	Valid Data Type
ASCII text	ASCII ASCII numeric

Table 17-8 (Page 2 of 2). Valid SBCS Data Types for File Types

File Type	Valid Data Type
DOS random	ASCII Binary Hexadecimal Packed Zoned
BASIC sequential	ASCII ASCII numeric
BASIC random	ASCII BASIC double-precision floating point BASIC integer BASIC single-precision floating point Hexadecimal
DIF	ASCII ASCII numeric
No-conversion	Binary EBCDIC EBCDIC packed EBCDIC zoned Hexadecimal
DOS random type 2	ASCII Binary Hexadecimal Packed Zoned
BIFF format	ASCII ASCII numeric

Note: ASCII (SBCS) includes date, time, and time stamp types if converted. EBCDIC includes date, time, and time stamp if not converted.

For numeric fields in BASIC sequential and DIF files, a size specification must be present. However, because the data in these fields is of variable length, the data transfer function assumes a maximum length of 65 characters. This length more than covers the largest possible exponential ASCII numeric value. The size specifications for character fields must be the maximum size of any data item in that field.

Table 17-9 shows the allowed data length limits for each workstation data type. These are the maximum lengths you can specify for size in the PCFL entry.

Table 17-9 (Page 1 of 2). Allowable Data Length Limits for Personal Computer SBCS Data Types

Personal Computer Data Type	Data Length Limit (in Bytes)
ASCII	4093
ASCII numeric	33 (65 for DIF and BASIC sequential)
BASIC double-precision	8 (only allowed length)
BASIC integer	2 (only allowed length)
BASIC single-precision	4 (only allowed length)

Table 17-9 (Page 2 of 2). Allowable Data Length Limits for Personal Computer SBCS Data Types

Personal Computer Data Type	Data Length Limit (in Bytes)
Binary	4
EBCDIC	4093
Hexadecimal	2048
Packed decimal (ASCII and EBCDIC)	16
Zoned decimal (ASCII and EBCDIC)	31
Time	
HMS (see note 1)	8
USA	8
ISO, EUR, and JIS (see note 1)	8
DDS, DFT	8 or 10 (see note 2)
Date	
MDY, DMY, YMD	8
Julian	6 (only allowed length)
ISO, EUR, JIS, USA (see note 1)	10
DDS, DFT	6, 8, or 10 (see note 2)
Time stamp	26

Notes:

1. These abbreviations appear in the time and date parameter sections.

Abbreviation	Description
HMS	Hours Minutes Seconds
EUR	IBM European Standard
JIS	Japanese Industrial Standard Christian Era
ISO	International Standards Organization

2. The length is determined by the format defined in the host file for DDS, or from the AS/400 job default (DFT keyword).

Table 17-10 shows the allowed data length limits for each AS/400 data type.

Table 17-10 (Page 1 of 2). Allowable Data Length Limits for AS/400 Data Types

AS/400 Data Type	Data Length Limit in Bytes (see note 1)
Binary	2 or 4 (only allowed lengths)
EBCDIC	4096
Hexadecimal	2048
Packed decimal (EBCDIC)	16
Zoned decimal (EBCDIC)	31

Table 17-10 (Page 2 of 2). Allowable Data Length Limits for AS/400 Data Types

AS/400 Data Type	Data Length Limit in Bytes (see note 1)
Time	
HMS	8
USA	8
ISO, EUR, and JIS	8
DDS, DFT	8 or 10 (see note 2)
Date	
MDY, DMY, YMD	8
Julian	6 (only allowed length)
ISO, EUR, JIS, USA	10
DDS, DFT	6, 8, or 10 (see note 2)
Time stamp	26

Notes:

1. The data length limits for the workstation and the system data fields are different in some cases. For these cases, the transfer function attempts to fit the workstation data into the system field. If the data does not fit into the field, a message displays. Refer to "Data Conversions" on page 17-53 for more details.
2. The length is determined by the format defined in the host file for DDS, or from the AS/400 job default (DFT keyword).

If there is a decimal position associated with the data in that field, place a forward slash (/) and then the number of decimal positions after the length specification. There are no spaces between the length, slash, and decimal position specifications.

The decimal position specification refers to the number of positions from the right-hand byte of the resulting decimal number. Do not specify a decimal position for floating-point numbers unless the data type is one of the following types:

ASCII numeric
Binary
Packed
Zoned

Note: The number of decimal positions in a field ranges from 0 to 9 or the maximum number of decimal digits in this number, whichever is smaller. The data transfer function might round the number to fit it into the field. Refer to "Data Conversions" on page 17-53 for more details.

Comment Entries: Enter comment lines anywhere in the file description file, observing the following restrictions:

The last element of the field descriptor entry specification is a comment. This is an optional entry for your information only, and must be separated from the size entry by a space. PCFL entries created by the data transfer function (RTOPC) do not contain a comment field.

Precede the comment with an asterisk (*) as the first nonspace character in the line.

Do not exceed 80 characters in length.

Do not make the comment the first record in the file description file.

Following is an example of a comment:

```
This is a comment
```

Example

Following is an example of a file description file for an inventory file:

```
PCFDF
PCFT 3 BASIC SEQUENTIAL FILE
 ITEM INVENTORY FILE
PCFO 1,1,1,2,1 OPTIONS SETTINGS
PCFL ITEMNO 2 8   ITEM NUMBER
PCFL ITEMDESC 1 2   DESCRIPTION OF ITEM
PCFL COLOR 1 8   COLOR
PCFL WEIGHT 2 7/2   ITEM WEIGHT
PCFL PRICE 2 7/2   PRICE PER ITEM
PCFL INSTOCK 2 6   ITEMS IN STOCK
```

Data Conversions

The data transfer function needs data conversions for transferring data from the system to the workstation, and vice versa. For both types of transfers, the necessary conversion depends on the record size, the type of data being transferred, the type of workstation file being used, the system data type, and, in some cases, the data length.

Record Size

Each transferred record contains data indicating whether each field contains a null value. There is a restriction on the maximum data record that can be sent or received from the AS/400 system because of this data.

The following formula determines the maximum record length that can be transferred:

```
4 96 – (number of fields in the record + 2) = (maximum record length)
```

Data Types

The data transfer function supports the following system data types:

- Binary data
- Character data
- Date
- Hexadecimal data
- Packed decimal data
- Time
- Time stamp
- Zoned decimal data

The data transfer function supports the following workstation data types:

- ASCII numeric data
- BASIC numeric data, including:
  - Double-precision data
  - Integer data

- Single-precision data

Binary data
Character data, including:
- ASCII
- EBCDIC

Hexadecimal data
Packed decimal data
Zoned decimal data

ASCII Numeric Data

The data transfer function defines ASCII numeric data to represent any numeric value stored in ASCII format. This is not a valid AS/400 system data type. The number –123.45 in ASCII format is:

2D 31 32 33 2E 34 35

The decimal point and sign are stored explicitly for ASCII numeric data. The character on the left displays the sign (space or plus (+) for positive, minus (–) for negative). Leading zeros to the left of the decimal point change to spaces. The decimal point, if any, is added in the correct position.

BASIC sequential and DIF file types also support another form of ASCII numeric data called exponential numbers.

An exponential number is a decimal number followed by the letter E or D and a signed integer of two or three digits. E represents a single-precision number and D represents a double-precision number. The exponent portion (E or D and the integer) represents “times 10 to the power of the integer specified.”

For example, the number –1.0E+03 (representing -1.0×10^{3} in ASCII numeric format) is:

2D 31 2E 30 45 2B 30 33

For example, the number 9.5D–15 (representing 9.5×10^{-15} in ASCII numeric format) is:

39 2E 35 44 2D 31 35

Binary Data

This data represents signed or unsigned numbers in twos complement form. Binary numbers of 1, 2, 3, or 4 bytes in length are allowed on the workstation, but the AS/400 system allows only numbers 2 or 4 bytes in length. The bit on the left side of the high-order bit determines the sign of the number (0 for positive, 1 for negative). The system stores the data with the high-order byte on the left side of the field, whereas the workstation stores the data with the high-order byte in the right-hand position of the field.

The decimal position, if specified by the file description, represents the number of decimal digits to the right of the decimal point. The file description specifies the presence of a decimal position.

For example, the binary number 3BF5 is equivalent to the decimal number 15349, and the binary number FFB4 is equivalent to the decimal number –76.

Character Data for SBCS

You can think of this data as a string of bits that represents particular characters and symbols.

The tables used to translate characters from ASCII to EBCDIC and from EBCDIC to ASCII contain the following kinds of values:

Values where the workstation ASCII characters and AS/400 EBCDIC characters match exactly

Values where a substitute character is chosen for a character that cannot be translated

The data transfer function uses tables to translate data from ASCII to EBCDIC and EBCDIC to ASCII. You can change these default tables using the translation table utility (TRTABLE).

Note: ASCII (SBCS) data includes date, time, and time stamp types if converted. EBCDIC data includes date, time, and time stamp if not converted.

Double-Precision Data

Double-precision data is defined only for the workstation. The AS/400 system does not support this data type. BASIC applications use double-precision data. This data type is a positive or negative number from $2.938735877055719 \times 10^{-39}$ to $1.701411834604692 \times 10^{38}$. Double-precision numbers are stored in 8 bytes, with 7 bytes representing the mantissa and 1 byte representing the exponent.

Date, Time, and Time-Stamp Data Types

Date, time, and time-stamp values can be used in certain arithmetic and character operations and are compatible with certain character constants, but they are neither characters nor numbers.

A date is a three-part value (year, month, and day) designating a point in time on the calendar. The range of the year is 0001 to 9999. The range of the year for a non-SAA format is 1940 to 9999. The range of the month is 1 to 12. The range of the day is 1 to *x*, where *x* depends on the month.

A time is a three-part value (hour, minute, and second) designating a time of day under a 24-hour clock. The range of the hour is 0 to 24 and the range of the other values is 0 to 59.

A time stamp is a seven-part value (year, month, day, hour, minute, second, and microsecond) that designates a date and time including the specified microseconds. The maximum length of the time stamp is a character string of 26.

Dates, times, and time stamps can be assigned to result fields. A valid character string representation of a date can be compared with a date field, or a valid character string representation of a time can be compared with a time field.

Hexadecimal Data

You can think of this data as a string of bits representing base 16 numbers. For example, you can represent hex 3D with the following string of bits:

0011 1101

Integer Data

Integer data is defined only for the workstation. BASIC applications use integer data. Integer data is stored in 2 bytes and represents a whole number from –32768 to 32767.

Packed Decimal Data

For both the AS/400 system and the workstation, each half-byte represents a value from 0 through 9. The hexadecimal value in the half-byte on the right side of the right-hand byte specifies the sign.

For the AS/400 system, a value of hex B or hex D in this half-byte represents a negative number.

For DOS random files, only the last half-byte (the half-byte that contains the sign) is changed. For the sign half-byte, the workstation uses hex 3 to indicate a positive number or hex B to indicate a negative number.

For example, X'0865431F' appears as X'08654313'.

For DOS random type-2 files, the last half-byte (the half-byte that contains the sign) is not changed. The sign convention used on the workstation and on the host system is the same.

For example, X'0865431C' appears as X'0865431C'.

The decimal position, if specified, represents the number of decimal digits to the right of the decimal point. The presence of a decimal position is specified in the file description.

Single-Precision Data

Single-precision data is defined only for the workstation. The AS/400 system does not support this data type. BASIC applications use single-precision data. This data type is a positive or negative number from 2.938736×10^{-39} to 1.701412×10^{38}. Single-precision numbers are stored in 4 bytes, with 3 bytes representing the mantissa and 1 byte representing the exponent and sign.

Zoned Decimal Data

This data is represented in a form in which each byte corresponds to one decimal digit. Each of these bytes is stored in character form. For example, the digit 7 is stored on the AS/400 system as F7, which is the EBCDIC representation, and is stored on the workstation as 37, which is the ASCII representation.

The size of each digit is determined by its half-byte on the right side. Valid values for the half-bytes are decimal 0 through 9.

The sign in both the AS/400 system and workstation zoned decimal fields is specified by the hexadecimal value in the left half-byte of the right byte of the field. For the AS/400 system, a hex B or hex D in this half-byte represents a negative number (for example, X'F6D2' represents –62).

For DOS random files, zoned decimal fields from the system change from EBCDIC to ASCII, as do character fields, except that the sign half-byte in the workstation field is changed to a hex 3 to indicate a positive number or a hex B to indicate a negative number.

For DOS random type-2 files, zoned decimal fields from the system change from EBCDIC to ASCII, as do character fields, except that the sign half-byte in the workstation field is changed to a hex 3 to indicate a positive number or a hex 7 to indicate a negative number.

The decimal position, if specified, represents the number of decimal digits to the right of the decimal point and is specified by the file description.

Personal Computer File Types

The following workstation file types are supported:

ASCII text files
BASIC random files
BASIC sequential files
DIF files
BIFF files
DOS random files
DOS random type-2 files
No-conversion files

ASCII Text Files

ASCII text files are normally used with programs that work with text (such as editors and print routines). The characteristics of an ASCII text file are as follows:

Records consist of ASCII characters.

A carriage return character (hex 0D) and a line feed character (hex 0A) delimit each record from the next. The character for end-of-file is hex 1A.

PC records in an ASCII file can be variable in length due to truncation of trailing blanks at the end of an AS/400 record.

Transferring Data to ASCII Text Files: When you create an ASCII text file, the data coming from the AS/400 system changes as follows:

Hexadecimal fields change to equivalent ASCII characters for each half-byte. For example, X'D3' expands to ASCII 4433 and is written to the file. When displayed by an editor or printed, the string appears as D3.

EBCDIC character fields change byte by byte and are mapped into ASCII characters as defined by the translation tables.

Date, time, and time-stamp data is mapped into ASCII characters as defined by the translation tables.

Variable-length and null fields are converted to fixed lengths, and trailing blanks (for character, hexadecimal, date, time, and time-stamp data) or zeros (for binary, zoned, and packed,) are added to the maximum length of the field.

Note: Some nondisplayable EBCDIC characters are translated into ASCII control characters on the workstation. If EBCDIC character fields contain nondisplayable data, you might get unexpected results, and your ASCII text file might appear to be corrupted.

For example, X'05' in an EBCDIC field is translated to an ASCII X'09', which is an ASCII control character for horizontal tab. Most workstation text editors process this tab character so that the data in your workstation text file appears to be shifted to the right when viewed. If one of the EBCDIC characters is X'3F', it translates into an ASCII

X'1A', which is interpreted as end-of-file by the workstation text editor. You might not be able to view any of the remaining records that were transferred to your ASCII text file.

One possible solution to this problem is to define these fields on the host system as hexadecimal fields instead of character fields.

Binary fields change to ASCII numeric. For example, X'FFD3' with no decimal position expands to ASCII 20202020202020202D3435. When displayed by an editor or printed, the string appears as –45.

Note: The length of the ASCII field depends on the length of the binary field.

A binary field on the AS/400 system is either 2 or 4 bytes long. The resulting ASCII field length is from 6 to 11 bytes, including the sign. Another byte is added for a decimal point.

Table 17-11 shows the mapping between binary field lengths and their ASCII lengths.

Table 17-11. Binary-to-ASCII Field Length Mapping

Binary Length	ASCII Length	Value Range
2	6	–32768 to 32767
4	11	–2147483648 to 2147483647

Zoned decimal fields are changed to ASCII numeric. For example, EBCDIC F0F0F9F5F2D6 with a field length that indicates two digits to the right of the decimal point expands to ASCII 20202D39352E3236. When displayed by an editor or printed, the string appears as –95.26. The resulting workstation field length is equal to the length of the system field plus 1 for the sign and 1 for the decimal point, if specified.

Packed decimal fields change to ASCII numeric. For example, X'871D' (no decimal point) changes to ASCII 2D383731. When displayed by an editor or printed, the string appears as –871.

Since two decimal digits are packed into 1 byte, the length of the resulting workstation field is equal to two times the length of the AS/400 field, plus 1 for the decimal point (if specified). This length always includes the sign. A minus sign (–) indicates negative, and a space indicates positive.

Transferring Data from ASCII Text Files: When you transfer data from ASCII text files to system files, the data changes as follows:

ASCII character data changes to EBCDIC character, date, time, or time-stamp data (based on the AS/400 field type) on a byte-to-byte basis, or to hexadecimal data by changing 2 ASCII bytes into 1 hexadecimal byte.

ASCII numeric data changes to AS/400 binary, zoned decimal, or packed decimal data, depending on the specified data type.

The field lengths on the AS/400 system and the workstation are different because of the explicit way minus signs and decimal points are stored in ASCII numeric fields. Each field changes individually, to ensure that the resulting field length matches the specifications for that field. The data transfer function tries to fit the workstation data into the system field.

For null-capable AS/400 fields, null values (except date, time, and time stamp) cannot be reliably detected and are not uploaded. For variable-length AS/400 fields, trailing blanks are removed and the field is converted to the variable-length format.

Errors When Transferring Data from ASCII Text Files: When you transfer data from a workstation ASCII text file to an AS/400 file, the following errors can occur:

A data field in the ASCII text file is too long for a field in the AS/400-defined file. In this case, the data is truncated. This occurs when the description file defines the character data as longer than the field length specified for the system file.

If the data transfers to an EBCDIC field, this error occurs only if the extra bytes are not spaces.

If the data transfers to a hexadecimal field, this error occurs only if the extra bytes are not zeros. These extra bytes are truncated so the data fits into the specified field.

The value of numeric data is too large for the system field. The maximum value is used. This error occurs when:

- Numeric data in the field does not fit into the specified number of bytes for the field.
- The decimal value of a numeric field contains more digits than were specified for the field.

The value of the field is set to the maximum value possible for the number of bytes and digits specified by the AS/400 system.

Data in this field has too many decimal positions. The number is rounded. This error occurs when the number of decimal positions in the field is greater than the number of decimal positions specified on the AS/400 system. These extra bytes are significant because the data rounds up if the first extraneous digit is 5 or greater, and rounds down if it is less than 5.

Data in this field is incorrect or does not match the data type. This error occurs when:

- Nonnumeric data is found in a field that the file descriptions defined as numeric. The transfer request ends to prevent transferring incorrect data to the file.
- ASCII numeric data is found that does not match the format the file description specified. An incorrectly positioned decimal point within the field could cause this error.
- A value other than X'30' through X'39', minus, plus, or decimal point is found. A duplicated decimal point or minus is found. The transfer request ends to prevent transferring incorrect data to the file.

Data for this field is missing. The default values are used. This error occurs when a data field is defined, but the data is not in the file. This means that the end of the record is reached before all of the defined data is found.

The field or fields for which data has been defined but not found then fill with default values and transfer to the file. The default values are EBCDIC spaces for character fields, or zeros for numeric and hexadecimal fields.

To supply your own default values, use the default (DFT) keyword in the data description specifications (DDS) for the file.

Extra data is found at the end of this record. The extra data is not transferred. Data found at the end of this record and not defined by the system data definitions or workstation file description file is not transferred to the system file because no definitions exist to define the data and how it should change.

When you transfer data from an ASCII text file to an AS/400 file without using a file description file, any extra data found past the record length specified for the file is not transferred.

BASIC Random Files

BASIC random files are the most general-purpose BASIC file type. They contain fixed-length records with:

No delimiters between fields or records
No end-of-file marks

Transferring Data to BASIC Random Files: When you create a BASIC random file, system data changes as follows:

Hexadecimal fields do not change.

Change from a system binary field depends on the field length:

- Fields of 2 bytes, with no decimal positions to the right of the decimal point, change to 2-byte BASIC integer values. The only change is that the order of the bytes reverses.
- Fields of 2 bytes, with decimal positions to the right of the decimal point, change to BASIC single-precision numbers.
- Fields of 4 bytes change to BASIC double-precision numbers.

EBCDIC character, date, time, and time-stamp fields change byte by byte and are mapped into ASCII characters as defined by the translation tables.

Variable-length and null fields are converted to fixed lengths, and trailing blanks (for character, hexadecimal, date, time, and time-stamp data) or zeros (for binary, zoned, and packed data) are added to the maximum length of the field.

Zoned decimal fields change into one of the following BASIC variables depending on the field length and the number of decimal positions:

- Zoned decimal fields of 4 bytes or less with no positions to the right of the decimal point change to a BASIC integer of an equivalent value.

  A zoned decimal field of 4 bytes or less, but with a decimal point, falls into the following category.

- Zoned decimal fields up to 7 bytes (including those that did not fall into the previous category) change to a BASIC single-precision number of an equivalent value.
- Zoned decimal fields greater than 7 bytes change to a BASIC double-precision number of an equivalent value.

Packed decimal fields change into one of the following BASIC variables depending on the length of the field:

- Packed decimal fields of 2 bytes or less with no positions to the right of the decimal point change to a BASIC integer of an equivalent value.

A packed decimal field of 2 bytes or less, but with a decimal point, falls into the following category (up to 4 bytes).

- Packed decimal fields of up to 4 bytes (including those that did not fall into the previous category) change to a BASIC single-precision number of an equivalent value.
- Packed decimal fields greater than 4 bytes change to a BASIC double-precision number of an equivalent value.

Note: Changes between binary, packed decimal, and zoned decimal numbers with decimal points are not equivalent to their BASIC number counterparts because BASIC uses a binary number format that does not always change into exact decimal fractions.

Transferring Data from BASIC Random Files: When you transfer data from BASIC random files to system files, the data changes as follows:

Hexadecimal fields transfer to the system file as unchanged hexadecimal data. The field lengths as stored on the workstation should be the same as the field lengths as stored on the system.

ASCII character, date, time, and time-stamp data changes to EBCDIC character data byte by byte.

For null-capable AS/400 fields, null values (except date, time, and time stamp) cannot be reliably detected and are not uploaded. For variable-length AS/400 fields, trailing blanks are removed and the field is converted to the variable-length format.

Numeric fields from BASIC random files (BASIC integers, single-precision floating-point numbers, and double-precision floating-point numbers) change to system binary data, zoned decimal data in EBCDIC format, or packed decimal data in EBCDIC format.

Note: Because the change of floating-point numbers into decimal fractions is not always exact, each number automatically changes into the most precise number possible with respect to the system field length. If you want more precision, specify a larger system field size.

Errors When Transferring Data from BASIC Random Files: When you transfer data from a workstation BASIC random file to a system file, the following errors can occur:

Data in this field is too short for the system field. The data is padded. This error occurs when the file contains character or hexadecimal data shorter than the field length specified on the system. This error can occur if the workstation field is defined as shorter than the system, or if the data in the last record of the file is too short. Character fields are padded on the right with EBCDIC spaces, and hexadecimal fields are padded with zeros.

Data in this field is too long for the system field. The data is truncated. This error occurs when the workstation file description file defines character or hexadecimal data as longer than the field length specified on the system.

For character data, this error occurs only if the extra bytes are not spaces. For hexadecimal data, this error occurs only if the extra bytes are not zeros. These extra bytes are then truncated so that the data fits into the specified AS/400 field.

The value of numeric data is too large for the system field. The maximum number is used. This error occurs when:

- Numeric data in the workstation field does not fit into the specified number of bytes for the system field.
- The decimal value of a numeric field contains more digits than are specified for the system field.

Data in this field has too many decimal positions. The number is rounded down to zero. In BASIC random processing, this error occurs if the value of the number is too small to fit into the specified field.

For example, the number 0.00001 does not fit into a system zoned field specified as being 2 bytes in length and 2 decimal positions to the right of the decimal point. In this example, the resulting value is zero.

Data for this field is missing. The default values are used. This error occurs when a data field is defined, but the data is not in the file. This means that the end of the file is reached before all of the defined data is found. For BASIC random files, this error occurs only on the last record in the file, since there are no explicit record delimiters.

When this error occurs, the field or fields for which data is defined, but not found, are filled with default values and are transferred to the AS/400 file. These default values are EBCDIC spaces for character fields and zeros for numeric fields.

To supply your own default values, use the Default (DFT) keyword in the DDS for the file.

When you transfer data from a BASIC random file to an AS/400 file, any data shorter than the record length defined for the system file is padded with EBCDIC spaces.

Because there are no record delimiters in BASIC random files, this error can occur only on the last record of the file. This probably indicates that the record length of the system file does not match the record length of the workstation file.

BASIC Sequential Files

BASIC uses BASIC sequential files for sequential processing (for example, INPUT and WRITE statements). The fields written are considered either character or numeric. Characteristics of BASIC sequential files are as follows:

Both numeric and character fields are written as displayable characters. However, character strings are distinguished from numeric strings by the ASCII double quotation marks (X'22') that surround them.

Therefore, character data in BASIC sequential files cannot contain ASCII double quotation marks, because they are interpreted as the end of the character string.

Fields are delimited by ASCII commas (X'2C'). Therefore, commas are not allowed as date, time, or decimal separators.

Each record is delimited from the next by a carriage return character (X'0D') and a line feed character (X'0A'). The end-of-file character is X'1A'.

Records and fields are variable-length.

Transferring Data to BASIC Sequential Files: The following list describes how AS/400 data created by a BASIC-sequential-file-defined data definition changes:

Hexadecimal fields change to equivalent ASCII characters for each half-byte. Double quotation marks surround them.

For example, X'F3' expands to ASCII 22443322 and is written to the file.

EBCDIC character, date, time, and time stamp fields change byte by byte and are mapped into ASCII characters as defined by the translation tables. ASCII double quotation marks are added before and after the character string.

Null fields are represented by the absence of the field (comma comma, or by a single comma if the null field is the last field of the record).

For null fields, successive commas in the file will result in a null value being sent to the AS/400 system if the field is null-capable.

In variable-length fields, if the AS/400 field is variable length, the field is converted to the AS/400 variable-length format.

Binary fields change to ASCII numeric. Leading zeros to the left of the decimal point and trailing zeros to the right of the decimal point are removed.

For example, X'FFD3' appears as ASCII 2D3435. When displayed on an ASCII device, the string appears as −45.

Zoned decimal fields change to ASCII numeric. Leading zeros to the left of the decimal point and trailing zeros to the right of the decimal point are removed.

For example, EBCDIC F0F0F9F5F2D6 with a field length that indicates two digits to the right of the decimal point expands to ASCII 2D39352E3236. The string appears as −95.26 when an editor displays it or it prints.

Packed decimal fields change to ASCII numeric. Leading zeros to the left of the decimal point and trailing zeros to the right of the decimal point are removed.

For example, X'871F' (no decimal point) changes to ASCII 383731. The string appears as 871 when an editor displays it or it prints.

Transferring Data from BASIC Sequential Files: When you transfer data from BASIC sequential files to AS/400 files, the data changes as follows:

ASCII character, date, time, and time-stamp data changes to EBCDIC character data on a byte-by-byte basis and to hexadecimal by changing 2 ASCII bytes into 1 hexadecimal byte.

ASCII numeric data translates to system binary, zoned decimal, or packed decimal data, depending on the specified data type. The lengths of the system data and the workstation data might be different because the minus signs and decimal points are stored in ASCII numeric fields, and leading and trailing spaces are stripped away.

BASIC might create exponential numbers in these files. The data transfer function also changes these numbers.

Each translated field is individually verified to ensure that the resulting field length matches the specifications for that field. The data transfer function tries to fit the workstation data into the system field.

Errors When Transferring Data from BASIC Sequential Files: When you transfer data from a BASIC sequential file to a AS/400-defined file, the following errors can occur:

Data in this field is too long for the AS/400 field. The data is truncated. The file description file defines character data as longer than the field length specified for the file.

If the data transfers to an EBCDIC field, this error occurs only if the extra bytes are not spaces. If the data transfers to a hexadecimal field, this error occurs only if the extra bytes are not zeros. These extra bytes are truncated so that the data fits into the specified AS/400 field.

The value of numeric data is too large for the system field. The maximum value is used. This error occurs when:

- Numeric data in the workstation field does not fit into the specified number of bytes for the system field.
- The decimal value of a numeric field contains more digits than were specified for the system field.

The value of the field is set to the maximum value possible for the number of bytes and digits specified by the AS/400 system.

Data in this field has too many decimal positions. The number is rounded. This error occurs when the number of decimal positions in the PC field is greater than the number of decimal positions specified on the system. The extra bytes are significant, because the data is rounded up if the first extraneous digit is 5 or greater, and is rounded down if it is less than 5.

Data in this field is incorrect or does not match the workstation data type. This error occurs when a field defined as numeric by the file description contains nonnumeric data. This could also result if a character or hexadecimal field contains a numeric field, or if a numeric (zoned, packed, or binary) field contains a character field.

When this error occurs, the transfer request ends to prevent transferring incorrect data to the system file.

Data for this field is missing. The default values are used. This error occurs when a data field is defined, but the data is not in the file. This means that the end of the record is reached before all of the defined data is found.

When this error occurs, the field or fields for which data has been defined, but not found, are filled with default values and transferred to the AS/400 file. These default values are EBCDIC spaces for character fields, or zeros for numeric fields.

To supply your own default values, use the default (DFT) keyword in the DDS for the file.

Data in this field exceeds workstation field size. The data is lost. This error occurs when extra data, not defined by the file description file, is found at the end of a character field. The extra bytes are truncated and are not transferred to the system file.

Extra data found at the end of the record. The extra data is not transferred. This error occurs when extra data is found at the end of the record, and has not been defined by the system data definitions or workstation file description

file. This extra data is not transferred to the system, because no definitions exist to define the data and describe how it should change.

Data Interchange Format Files

Data Interchange Format (DIF) files represent data in rows and columns. DIF files contain character and numeric data (positive and negative decimal numbers).

DIF is used for data interchange between spreadsheet programs and other application programs.

The data transfer function supports only the following two data types within DIF files:

Character data: The data in a character cell (think of a *cell* as one field in one record) must be enclosed in double quotation marks if there is an embedded space in the string. However, if the string begins with a quotation mark, it must also end with a quotation mark.

Numeric data: The numeric data supported by the data transfer function consists of a decimal number that can contain a minus sign or a decimal point or both. The data transfer function also supports exponential numeric data.

Transferring Data to DIF Files: When creating a DIF file, system data changes as follows:

Hexadecimal fields change to equivalent ASCII characters for each half-byte. Double quotation marks surround them.

EBCDIC character, date, time, and time-stamp data changes byte by byte and is mapped into ASCII characters as defined by the translation tables. ASCII double quotation marks are added before and after the character string.

Binary fields change to ASCII numeric. Leading zeros to the left of the decimal point, and trailing zeros to the right of the decimal point, are removed.

Zoned decimal fields change to ASCII numeric. Leading zeros to the left of the decimal point, and trailing zeros to the right of the decimal point, are removed.

For example, EBCDIC F0F0F9F5F2D6 with a field length that indicates two digits to the right of the decimal point expands to ASCII 2D39352E3236. When displayed or printed, the string appears as –95.26.

Packed decimal fields change to ASCII numeric. Leading zeros to the left of the decimal point, and trailing zeros to the right of the decimal point, are removed.

For example, X'871D' (no decimal point) changes to ASCII 2D383731. When displayed or printed, the string appears as –871.

If untranslatable data is found, the entire field becomes an error cell. An *error cell* results when untranslatable data is found when a DIF file is created or when a not valid calculation is done using the DIF file with a spreadsheet program.

Transferring Data from DIF Files: If an error cell is found when data is transferred from a DIF file to the AS/400 system, one of the following things can occur, depending on the type of data in the file:

If the system field is a character (EBCDIC) field, it is filled with untranslatable characters (hexadecimal zeros) and is transferred to the system. A message appears, telling you how many bytes of untranslatable data have transferred.

If the system field is a hexadecimal, zoned, packed, or binary field, you receive an error message telling you that the data in this cell is incorrect, and that the data was not transferred to the system.

When you transfer data from a system file to a DIF file, the field names are placed in the first record and you can consider them column headings. When you transfer DIF files back to the system, the first row must either be these field names (exactly as they are defined on the system) or data. If the first row does not consist of field names, the file is processed as if it contains only data.

No DIF header information is used when sending the file to the AS/400 system. To correctly transfer a DIF file to the system, ensure that the file is in the correct format (row and column). It is essential that the field names, if present, make up the first row of data. The subsequent records make up the remaining rows of data. Therefore, when you transfer the data to the AS/400 system, the file must be saved in the same format as originally created by the data transfer function.

When you transfer data from DIF files to AS/400 files, the data changes as follows:

ASCII character, date, time, and time-stamp data is changed to EBCDIC character data or to hexadecimal data. ASCII-to-EBCDIC conversion is done byte by byte. ASCII-to-hexadecimal conversion is done by changing 2 ASCII bytes to 1 hexadecimal byte.

ASCII numeric data changes to system binary, zoned decimal, or packed decimal data, depending on the data type the system specifies.

The lengths of the fields on the system and the workstation can be different, because of the explicit way minus signs and decimal points are stored in ASCII numeric fields. This means that each field changes individually, to ensure that the resulting field length matches the system specifications for that field. The data transfer function tries to fit the workstation data into the system field.

In null fields, a NULL DIF character field results in a null value being sent to the AS/400 field if the field is null-capable.

If the AS/400 field is variable-length, the field is converted to the AS/400 variable-length format.

Errors When Transferring Data from DIF Files: When you transfer data from a workstation DIF file to a system file with data definitions, the following errors can occur:

Data in this workstation file is not valid, or the version of this workstation file is not supported. The DIF file does not follow the standard DIF format. Processing ends, and no more records are transferred.

Data in this field is too long for the AS/400 field. The data is truncated. The workstation file description file defines character or numeric data as longer than the field length specified for the system file.

For character data, this error occurs only if the extra bytes are not spaces. For hexadecimal data, this error occurs only if the extra bytes are not zeros. The extra bytes are truncated so that the data fits into the specified AS/400 field.

The value of numeric data is too large for the system field. The maximum value is used. This error occurs when:

- Numeric data in the workstation field does not fit into the specified number of bytes for the AS/400 field.
- The decimal value of a numeric field contains more digits than are specified for the system field.

The value of the field is set to the maximum value possible for the number of bytes and digits the system specifies.

Data in this field has too many decimal positions. The number is rounded. The number of decimal positions in the workstation field is greater than the number of decimal positions specified on the system. The data is rounded up if the first extraneous digit is 5 or greater, and is rounded down if it is less than 5.

Data in this field is incorrect or does not match the workstation data type. One of the following things has occurred:

- A numeric field contains nonnumeric data.
- A character or hexadecimal field contains a numeric field or a numeric (zoned, packed, or binary) field contains a character field.
- An AS/400 hexadecimal or numeric (zoned, packed, or binary) field contains a DIF error cell.

When this error occurs, the transfer request ends to prevent the transfer of incorrect data to the system file.

Data for this field is missing. This occurs when a data field is defined, but the data is not in the file. This means that the end of the record is reached before all of the defined data is found. If the host field is null-capable then a null is inserted; otherwise, the default values are used.

When this error occurs, the field or fields for which data is defined, but not found, are filled with default values and are transferred to the system file. These default values are EBCDIC spaces for character fields, or zeros for numeric fields.

To supply your own default values, use the Default (DFT) keyword in the DDS for the file.

Data in this field exceeds the field size. The data is lost. This error occurs when extra data, not defined by the file description file, is found at the end of a character field. The extra bytes are truncated and are not transferred to the system file.

Extra data is found at the end of this record. The extra data is not transferred. This error occurs when there is extra data at the end of the record, and the AS/400 data definitions or file description file have not defined it. This extra data is not transferred to the system, because no definitions exist to define the data and how it should change.

BIFF Files

In a BIFF file, data is expressed in lines and columns. A BIFF file contains character and numeric data (positive and negative decimal values).

The BIFF file format is used in EXCEL. The supported BIFF version is 4 (EXCEL 4.0).

The transfer facility supports only the following two data types for a BIFF file:

Character data
Numeric data

Transferring Data to BIFF Files: When a BIFF file is created, the system data is converted to equivalent EXCEL cell data.

If untranslatable data is found, the entire field is treated as an error cell.

Transferring Data from BIFF Files: If an error cell is found during data transfer from a BIFF file to the AS/400 system, either of the following things can occur depending on the data type of the file:

If the system field is a character (EBCDIC) field, the error cell containing untranslatable characters (hexadecimal zeros) is transferred to the system. A message indicating how many bytes of untranslatable data were transferred is displayed.

If the system field is a hexadecimal, zoned decimal, packed decimal, or binary field, an error message indicating that the data in this cell is not valid and thus has not been transferred to the system is displayed.

When data is transferred from a system file to a BIFF file, the first record contains field names, which can be treated as column headers.

To return a BIFF file to the system, the first line must contain these field names (as defined in the system) or data. If the first line does not contain field names, the file is regarded as containing data only.

When a file is sent to the AS/400 system, cell information (such as the character size and font information) is ignored. This means that cell information is lost, even if the contents of a BIFF file that have been sent to the AS/400 system are retransmitted to a workstation.

When data is transferred from a BIFF file to an AS/400 file, the data is converted as follows:

ASCII character cell data is converted to EBCDIC character data or hexadecimal data; 1-byte ASCII data is converted to 1-byte EBCDIC data.

ASCII numeric cell data is converted to a binary number, or a zoned or packed decimal number, depending on the data type specified in the system.

When data is transferred from a BIFF file to the AS/400 system, the following specific processing is performed:

When data is transferred to a BIFF file, the first record contains the names of the fields to be transferred, which can be treated as column headers. To return a BIFF file to the AS/400 system, the first line must contain the same field names (as defined in the AS/400 system) or data. If the first line or the first set

does not contain a character field that exactly matches the AS/400 field, the file is treated as being a file with no column headers, and only data is processed.

When a BIFF file is transferred to the AS/400 system, header information is not used.

To ensure correct transfer of a BIFF file to the AS/400 system, the file format must be valid (lines and columns). Data for each set or line must correspond to one record in the AS/400 file.

Errors When Transferring Data from BIFF Files: When data is transferred from a BIFF file on a workstation to the system file with the data definition, the following errors can occur:

Data in this workstation file is not valid, or the version of this workstation file is not supported. The BIFF file does not conform to the standard BIFF format. Processing terminates, and no more records are transferred.

Data in this field is too long for the corresponding AS/400 field. The data is truncated. A file description file defines character or numeric data that is longer than the field specified in the system file.

- For conversion from ASCII to EBCDIC, this error occurs if a file description file defines ASCII data that is longer than the field specified in AS/400 system.

  During conversion from ASCII to hexadecimal, this error will occur if a file description file defines ASCII data that is twice as long as the field specified in AS/400 system. This is because 2-byte ASCII data is converted to one hexadecimal character.

- A truncation error only occurs if excess bytes are other than blanks (X'20') during conversion from ASCII to EBCDIC, or other than zeros (X'30') during conversion from ASCII to hexadecimal. Truncating these excess bytes enables data to fit into the specified AS/400 fields.

Numeric data is too long to fit into the corresponding AS/400 field. The maximum value is assumed. This error occurs under either of the following conditions:

- Numeric data in a workstation field is too long to fit into the number of bytes specified for the AS/400 field.
- The number of decimal digits in a numeric field exceeds the number of digits specified for the AS/400 field.

The field value is set to the maximum value that can be specified for the number of bytes, and that for the number of digits, specified for the AS/400 system.

Data in this field contains too many decimal places. The data is rounded off. The number of decimal places in a workstation field is greater than the number of decimal places specified for the system. If the first excess digit is 5 or more, the data is rounded up. Otherwise, it is rounded down.

Data in this field is not correct, or its type does not match the type of workstation data. One of the following things has occurred:

- A numeric field contains other than numeric data.
- A character field or a hexadecimal field contains a number, or a numeric (zoned or packed decimal, or binary) field contains characters.

– A hexadecimal field or a numeric (zoned or packed decimal, or binary) field for the AS/400 contains a BIFF error cell.

If this error occurs, the transfer request terminates to avoid transferring incorrect data to the system file.

Data for this field is missing. This error occurs if the data field is defined, but the file does not contain any data. This means that the end of the record is reached before all defined data has been found.

If this error occurs—that is, if data is defined for one or more fields, but it is not found there—the fields containing the default value are transferred to the system file. The default value is EBCDIC spaces for a character field, and zeros for a numeric field.

To specify a user-specific default value, use the default value (DFT) keyword in DDS for the file.

Data in this field exceeds the size of a workstation field. Data is lost. This error occurs if excess data, not defined in the workstation file description file, is found at the end of the field. For character data, excess bytes are truncated, and not transferred to the system file. For numeric data, the entire field is converted to zeros and transferred to the system file.

Excess data is found at the end of this record. The excess data is not transferred. This error occurs if such excess data is not defined in the AS/400 data definition or in the workstation file description file. This excess data is not transferred to the system, because the data and the conversion method are not defined.

DOS Random Files

DOS random files are fixed-length files used by the DOS random read and write routines. The characteristics of DOS random files are as follows:

There are no end-of-record or end-of-file markers.

Records are delimited by their constant length, relative positions in the file, and the total length of the file.

Note: DOS random and DOS random type-2 files are identical, except for the way in which the signs are represented for packed decimal and zoned decimal numbers.

Transferring Data to DOS Random Files: When creating DOS random file data definitions, system data changes as follows:

Binary fields on the AS/400 system and the workstation are represented as two complement numbers, so it is unnecessary to change individual bytes. The workstation uses the convention of storing numeric values with the least significant byte in the left-hand byte position. The data transfer function then reverses the order of the bytes in the binary fields.

For example, X'CEF3', coming from the system as a 2-byte binary number (representing the value –12557), appears as X'F3CE'.

EBCDIC character, date, time, and time-stamp data changes byte by byte and is mapped into ASCII characters as defined by the translation tables.

Variable-length and null fields are converted to fixed length, and trailing blanks (for character, hex, date, time, and time stamp) or zeros (for binary, zoned, and packed) are added to the maximum length of the field.

Hexadecimal fields do not change.

Packed decimal fields do not change except for the last half-byte, which contains the sign. The workstation uses X'3' to indicate a positive number and X'B' to indicate a negative number in the sign half-byte.

For example, X'0865431F' appears as X'08654313'.

Zoned decimal fields from the system change from EBCDIC to ASCII, as do character fields, except that the sign half-byte in the workstation changed field is X'3' to indicate a positive number and X'B' to indicate a negative number.

For example, EBCDIC X'F0F1F2F5F2D6' appears as ASCII X'3031323532B6'.

Transferring Data from DOS Random Files: When you transfer data from DOS random files to AS/400 files, the data changes as follows:

ASCII character, date, time, and time stamp data changes to EBCDIC character data on a byte-by-byte basis.

Binary fields in the workstation file are stored in an order reversed from what the system file expects. These bytes reverse and transfer to the system file.

Hexadecimal fields do not change. The field length on the system should be the same as the field length on the workstation.

For packed decimal fields, only the last half-byte (the byte that contains the sign) is changed. The host system uses X'F' to indicate a positive number and X'D' to indicate a negative number for the sign half-byte.

For example, X'08654313' appears as X'0865431F'.

Zoned decimal fields on the workstation change from ASCII to EBCDIC (PC CODE to EBCDIC for DBCS), as do character fields. The last half-byte (the half-byte that contains the sign) in the workstation field is changed to X'F' to indicate a positive number and X'D' to indicate a negative number.

For example, ASCII X'3031323532B6' appears as EBCDIC X'F0F1F2F5F2D6'.

For null-capable AS/400 fields, null values (except date, time, and time stamp) cannot be reliably detected and are not uploaded. For variable-length AS/400 fields, trailing blanks are removed, and the field is converted to the variable-length format.

Errors When Transferring Data from DOS Random Files: When you transfer data from a DOS random file to an AS/400 file, the following errors can occur:

Data in this field is too short for the system field. The data is padded. This error occurs when the workstation file contains character or hexadecimal data shorter than the specified field length. It also occurs if the length of the workstation field is defined as less than the system field, or if the data in the last record of the file is too short. Character fields are padded on the right with EBCDIC spaces. Hexadecimal fields are padded on the right with zeros.

Data in this field is too long for the system field. The data is truncated. This error occurs when the workstation file description file defines character or hexadecimal data as longer than the field length specified for the system file.

For character data, this error occurs only if the extra bytes are not spaces. For hexadecimal data, this error occurs only if the extra bytes are not zeros. These extra bytes are truncated so that the data fits into the specified field.

The value of numeric data is too large for the system field. The maximum value is used. This error occurs when:

- Numeric data in the workstation field does not fit into the specified number of bytes for the AS/400 field.
- The decimal value of a numeric field contains more digits than were specified for the AS/400 field.

The value of the field is set to the maximum value possible for the number of bytes and digits specified by the system.

Data in this field has too many decimal positions. The number is rounded. This occurs when the number of decimal positions in the PC field is greater than the number of decimal positions specified on the system. The extra bytes are significant, since the data rounds up if the first extraneous digit is 5 or greater, and rounds down if it is less than 5.

Data in this field is incorrect or does not match the workstation data type. This error occurs when nonnumeric data appears in a field defined as numeric by the file descriptions. When this occurs, the transfer request ends to prevent transferring incorrect data to the system file.

Data for this field is missing. The default values are used. This error occurs when a data field is defined, but the data is not in the file. This means that the end of the file is reached before all the defined data is found.

When this error occurs, the field or fields for which data has been defined, but not found, fill with default values and transfer to the system file. Default values are EBCDIC spaces for character fields, or zeros for numeric fields.

To supply your own default values, use the default (DFT) keyword in the DDS for the file.

When you transfer data from a DOS random file to a system file without data definitions, any data shorter than the record length defined for the system file is padded with EBCDIC spaces.

Because DOS random files have no record delimiters, this error occurs only on the last record and probably indicates that the record length of the system file does not match that of the workstation file.

DOS Random Type-2 Files

DOS random type-2 files are fixed-length files used by the DOS random read and write routines. The characteristics of DOS random type-2 files are as follows:

There are no end-of-record or end-of-file markers.

Records are delimited by their constant length, relative positions in the file, and the total length of the file.

Note: This workstation file type is identical to the DOS random file type , except that the internal sign representation for packed decimal and zoned decimal data types follow Systems Application Architecture (SAA) standards. Some workstation applications, such as applications written in IBM COBOL/2 programming language, need to have the signs for packed

decimal and zoned decimal data types represented this way. Use the DOS random type-2 file type for those workstation applications.

Transferring Data to DOS Random Type-2 Files: When you create DOS random type-2 file data definitions, system data changes as follows:

Binary fields on the AS/400 system and the workstation are represented as twos complement numbers, so it is unnecessary to change individual bytes. The workstation uses the convention of storing numeric values with the least significant byte in the left-hand byte position. The data transfer function then reverses the order of the bytes in binary fields.

For example, X'CEF3', coming from the system as a 2-byte binary number (representing the value –12557), appears as X'F3CE'.

EBCDIC character, date, time, and time-stamp fields change byte by byte and are mapped into ASCII characters as defined by the translation tables.

Variable-length and null fields are converted to fixed length, and trailing blanks (for character, hex, date, time, and time stamp) or zeros (for binary, zoned, and packed) are added to the maximum length of the field.

Hexadecimal fields do not change.

Packed decimal fields do not change. The sign convention used on the workstation and on the host system is the same.

For example, X'0865431C' appears as X'0865431C'.

Zoned decimal fields from the system change from EBCDIC to ASCII, as do character fields. However, the sign half-byte is changed to a 3 to indicate a positive number or a 7 to indicate a negative number when the data is sent to the workstation.

For example, EBCDIC X'F0F1F2F5F2D6' appears as ASCII X'303132353276'.

Transferring Data from DOS Random Type-2 Files: When you transfer data from DOS random type-2 files to AS/400 files, the data changes as follows:

ASCII character data, date, time, and time-stamp data change to EBCDIC character data on a byte-by-byte basis.

Binary fields in the workstation file are stored in an order reversed from what the system file expects. These bytes reverse and transfer to the system file.

Hexadecimal fields do not change. The field length on the system should be the same as the field length on the workstation.

For packed decimal fields, the last half-byte (the half-byte that contains the sign) is not changed unless the sign half-byte is less than X'A' (represented by values 0 through 9). If the sign half-byte is less than X'A', it is changed to X'F' on the host system.

For example, X'865431D' appears as X'0865431D', but X'08654318' appears as X'0865431F'.

Zoned decimal fields on the workstation change from ASCII to EBCDIC, as do character fields. However, the sign half-byte is changed to a F to indicate a positive number or a D to indicate a negative number when the data is sent to the host system.

For example, ASCII X'303132353276' appears as EBCDIC X'F0F1F2F5F2D6'.

For null-capable AS/400 fields, null values (except date, time, and time stamp) cannot be reliably detected and are not uploaded. For variable-length AS/400 fields, trailing blanks are removed and the field is converted to the variable-length format.

Errors When Transferring Data from DOS Random Type-2 Files: When you transfer data from a DOS random type-2 file to an AS/400 file, the following errors can occur:

Data in this field is too short for the system field. The data is padded. This error occurs when the workstation file contains character or hexadecimal data shorter than the specified field length. It also occurs if the length of the workstation field is defined as less than the system field, or if the data in the last record of the file is too short. Character fields are padded on the right with EBCDIC spaces. Hexadecimal fields are padded on the right with zeros.

Data in this field is too long for the system field. The data is truncated. This error occurs when the workstation file description file defines character or hexadecimal data as longer than the field length specified for the system file.

For character data, this error occurs only if the extra bytes are not spaces. For hexadecimal data, this error occurs only if the extra bytes are not zeros. These extra bytes are truncated so that the data fits into the specified field.

The value of numeric data is too large for the system field. The maximum value is used. This error occurs when:

- Numeric data in the workstation field does not fit into the specified number of bytes for the AS/400 field.
- The decimal value of a numeric field contains more digits than were specified for the AS/400 field.

The value of the field is set to the maximum value possible for the number of bytes and digits specified by the system.

Data in this field has too many decimal positions. The number is rounded. This occurs when the number of decimal positions in the workstation field is greater than the number of decimal positions specified on the system. The extra bytes are significant, since the data rounds up if the first extraneous digit is 5 or greater, and rounds down if it is less than 5.

Data in this field is incorrect or does not match the workstation data type. This error occurs when nonnumeric data appears in a field defined as numeric by the file descriptions. When this occurs, the transfer request ends to prevent transferring incorrect data to the system file.

Data for this field is missing. The default values are used. This error occurs when a data field is defined, but the data is not in the file. This means that the end of the file is reached before all the defined data is found.

When this error occurs, the field or fields for which data has been defined, but not found, fill with default values and transfer to the system file. Default values are EBCDIC spaces for character fields, or zeros for numeric fields.

To supply your own default values, use the default (DFT) keyword in the DDS for the file.

When you transfer data from a DOS random type-2 file to a system file without data definitions, any data shorter than the record length defined for the system file is padded with EBCDIC spaces.

Because DOS random type-2 files have no record delimiters, this error occurs only on the last record and probably indicates that the record length of the system file does not match that of the workstation file.

No-Conversion Files

No-conversion files, defined by the data transfer function, consist of data that has not changed. For example, when data transfers from the system to a workstation no-conversion file, the data transfers exactly as it is stored on the AS/400 system. Date, time, and time-stamp data transfers to EBCDIC character data on the workstation.

Transferring Data to No-Conversion Files: When you transfer data from the AS/400 system to a no-conversion file, the data transfers exactly as it is stored on the system.

Variable-length AS/400 fields are converted to fixed-length fields, and trailing EBCDIC blanks are added to the maximum length of the field.

Date, time, and time-stamp data is converted to EBCDIC character data.

Variable-length and null fields are converted to fixed length, and trailing EBCDIC blanks (for character, hex, date, time, and time stamp) or EBCDIC zeros (for binary, zoned, and packed) are added to the maximum length of the field.

Transferring Data from No-Conversion Files: The data types that exist in a no-conversion file are EBCDIC system data types only. When a no-conversion file transfers to the system, the data transfer function performs no data change or translation. Date, time, and time-stamp data transfers to EBCDIC character data on the workstation.

However, the data transfer function verifies that all numeric data is in the correct EBCDIC format. If any numeric data is found that is not in the correct EBCDIC format, that data and any remaining data does not transfer.

Errors When Transferring Data from No-Conversion Files: When you transfer data from a workstation no-conversion file to a system file, the following errors can occur:

Data sizes are not equal. When you transfer no-conversion files, the length and decimal position specifications for the system and the workstation must match exactly. If not, no records transfer.

Data in this field is too short for system field. The data is padded. This error occurs when the workstation file contains character or hexadecimal data shorter than the field length specified for the system file. This could occur if the data in the last record of the file is too short. Character fields are padded on the right with EBCDIC spaces. Hexadecimal fields are padded with zeros.

Data in this field is incorrect or does not match the workstation data type. The transfer request ends to prevent transferring incorrect data to the system file. This error occurs when a field defined by the file descriptions as numeric contains nonnumeric data.

Note: The data is verified assuming that the data is in EBCDIC format. If you want to transfer data in another format, do not use data definitions or file descriptions, and specify the record lengths defined on the system and the workstation in the same way.

Data for this field is missing. The default values are used. This error occurs when a data field has been defined, but the data is not in the file. This error can occur only in the last record of the file, since no-conversion files have no explicit record delimiters.

When this error occurs, the field or fields for which data has been defined but not found fill with default values and transfer to the system file. These default values are EBCDIC spaces for character fields, or zeros for numeric fields.

To supply your own default values, use the default (DFT) keyword in the DDS for the file.

AS/400 System-to-Personal Computer Performance Considerations

Transferring data from the AS/400 system to the workstation depends on the following performance considerations:

The system workload.

How many records have to be looked at to complete the transfer.

If more than two files are joined. You need extra AS/400 resources to join records from more than one file.

If GROUP BY fields are specified.

If complicated WHERE or HAVING comparisons are specified.

These factors and others influence the time needed to determine which data should be transferred. For example, the time needed to receive the first record of a transfer in which all the records are chosen is less than the time needed to start transferring a smaller group of records based on complicated WHERE or HAVING values. However, transferring all the records in a large file is sometimes impractical or unnecessary.

The AS/400-to-workstation data transfer function uses many functions within the AS/400 system to determine the fastest method of selectively retrieving records. When it selects a smaller group of records to transfer, AS/400-to-workstation data transfer function uses the existing access paths whenever possible to improve performance.

For the AS/400-to-workstation data transfer function to consider using an existing access path (logical file), the access path must meet the following conditions:

It must be defined to the data that transfers.
It must have either *DELAY or *IMMED maintenance.

When you meet these conditions, you must then match the transfer request to the access path. The following considerations might be helpful when you define your transfer request:

The time it takes to select records based on WHERE clause values is less when the following things are true of the WHERE field:

- It is compared with a constant.

- It is the first key field in an existing access path defined to the data to be transferred.

A transfer request containing a GROUP BY or ORDER BY clause or both can work better if the key fields in the access path are in the same order as specified on the GROUP BY or ORDER BY clauses.

A transfer request containing a JOIN BY clause can work better when:

- An access path exists over the file that you are joining to.
- The field you are joining to is a primary key field in the access path.
- You are not returning records with missing fields.

PC400 Data Transfer

Chapter 18. File Transfer for PC400

File transfer is designed so that you can use it in the following cases:

To store a workstation file on the AS/400 system for a backup

To edit a source file of an AS/400 program by a workstation editor, and send the file edited on the workstation to the AS/400 system.

To distribute workstation documents and workstation programs to the AS/400 users

You can easily transfer a file if you know the library name and file name.

File transfer is not suitable for complicated processing, such as the processing of an AS/400 database on a workstation and then returning the results to the AS/400. In that case, use the Data Transfer Function.

Before attempting to use file transfer, review this chapter.

Note: You need to have a program, such as Personal Communications Tool/400, that supports the **APVAFILE** command installed on the host. If you do not, install one or ask your IBM representative how to obtain one.

PC File Transfer with the CRLF Option

If the CRLF option is specified, the transfer program checks for new-line characters. When the record length is reached before a new-line character is found, the record is divided at this point. One sentence of a workstation file will become two or more records. Particularly, specify a sufficiently long record length when retransmitting a workstation file containing 2-byte characters.

By default, the message records segmented. is not displayed. To display the message:

Search the file containing the program information for the session in which the file is transferred. Normally, the file is created in the **\PCOMOS2\PRIVATE** directory under the name *filename***.WS** (*filename* is a user-specified file name).

Use an editor to insert the following sentence into the [Transfer] section. If there is no [Transfer] section, first enter [Transfer]. (Be careful to enter it correctly.)

```
DisplayTruncateMessage=Y
```

or

```
[Transfer]
DisplayTruncateMessage=Y
```

The next time the system is started, this specification becomes valid.

© Copyright IBM Corp. 1989, 1996

Transfer to a Physical Source File

An AS/400 physical source file contains 12-byte information for each record as internal information: 6 bytes are for a record number, and the other 6 bytes are for a date. When you transfer a file from a workstation using file transfer, the date field contains 000000. If the APPEND option is not specified, the record number is incremented by 1, up to a maximum of 9999. Otherwise, it is incremented from the nearest integer, greater than the number of the last record in the original file (for example, 24 for 23.1). If the number of records exceeds 9999, the next and all subsequent record numbers are 9999.

Use the source specifications input utility (SIU) to renumber records when saving the file after editing.

Transfer to a Physical File

A file, such as a workstation program, that does not require the processing of the contents of an AS/400 file or the reading of data, should be transferred to a physical file with the BINARY transfer type. (Because data is not converted, if the data is subsequently retransmitted from the AS/400 system to a workstation, the original workstation file can be re-created exactly. If the data is converted, however, data might not be restored to its original form, depending on the contents of the conversion table.)

For the maximum number of members (MAXMBRS), a physical file attribute, the default value is 1. When a physical file is created during file transfer, MAXMBRS is 1.

When a file is transferred from a workstation to a physical file, the default file name **xxxBIN** is assumed. (**xxx** is a workstation file extension.) At this point, if MAXMBRS of the **xxxBIN** file is 1, an error occurs when the second and subsequent files are transferred. (The TRANS58 file or member cannot be created. File transfer terminates.) ***A file should be created with the expected file attribute before the file is transferred from a workstation to the AS/400 system.***

Use of the DSPMBRLST Command

For file transfer from the AS/400 system to a workstation, the Paste function can be used. If the Library/File(Member) to be transferred is copied with the Copy function of the Edit menu, it can be displayed as the host file candidate to be transferred on the transfer request screen by clicking the **Paste** button. This is particularly convenient when transferring more than one file at a time.

Use the DSPMBRLST command to list AS/400 files or members for Paste. The command format is as follows:

DSPMBRLST LIB(lib-name) FILE(file-name)

LIB parameter

The LIB parameter contains the target library name. The default value is ***USRLIBL**. Extensive specification, such as ***ALL**, ***** for generic name, is possible, but is time consuming. AS/400 files or members are listed more efficiently if a specific name is specified.

FILE parameter

The FILE parameter contains the target file name. There is no default value. The parameter must be specified. ***ALL** and * for generic name can be specified.

Executing this command lists Library/File(Member) on the screen. If they cannot be listed on one screen, **MORE...** is displayed in the lower right corner of the screen. Use the preceding page or next page key to scroll the screen. Create data for Paste with the Copy or the CopyAppend function of the Edit menu, as required.

Restrictions for Transferred File Size

A file that is more than 1,040,000 bytes cannot be transferred correctly.

PC400 File Transfer

Chapter 19. ODBC Driver for PC400 Database Access

PC400 Database Access is a query tool that lets you access the host or PC database and get data using ODBC drivers. See the online helps for extensive information on using Database Access with the Personal Communications ODBC driver.

Supported CCSIDs

The Personal Communications ODBC driver translates host EBCDIC characters into the corresponding Windows character according to the server Job CCSID or Column CCSID. The server Job CCSID is determined by the user profile CCSID or the user profile language ID at the initial connection to the database. The Column CCSID labels each column of tables specified when the table is created.

The Personal Communications ODBC driver does not support all of the CCSIDs that are supported by the AS/400 database. If target data is labeled with a non-supported CCSID, it may not be translated correctly. The following table shows the CCSIDs supported by the Personal Communications ODBC driver.

CCSID	Description
37	USA, Netherlands, Portugal, Brazil, Australia, New Zealand
273	Austria, Germany
277	Denmark, Norway
278	Finland, Sweden
28	Italy
284	Spain, Latin America (Spanish)
285	United Kingdom
297	France
5	Belgium, Canada, Switzerland, Latin 1 EBCDIC Multilingual
87	Latin 2 EBCDIC Multilingual
871	Iceland
875	Greek
1 25	Cyrillic Multilingual
1 26	Turkey Latin 5
29	Japanese Katakana Host Extended
1 27	Japanese Latin Host Extended
3	Japanese Latin Host Double-Byte including 437 UDC
4396	Japanese Latin Host Double-Byte including 188 UDC
93	Japanese Katakana-Kanji Host Mixed including 437 UDC, Extended SBCS
939	Japanese Latin-Kanji Host Mixed including 437 UDC, Extended SBCS
5 26	Japanese Katakana-Kanji Host Mixed including 188 UDC, Extended SBCS
5 35	Japanese Latin-Kanji Host Mixed including 188 UDC, Extended SBCS

© Copyright IBM Corp. 1989, 1996

Connecting With Earlier Versions of AS/400

There is no mode description (QSERVER) on an AS/400 system earlier than Version 3, Release 1. If you use such an AS/400 system as the intermediate node to access the database in the desired AS/400, you must create the mode description (QSERVER) by issuing the command below:

```
CRTMODD MODD(QSERVER)
        MAXSSN(64)
        MAXCNV(64)
        LCLCTLSSN( )
        PREESTSSN( )
        DTACPR( ALLOW)
        INDTACPR( LZ1 )
        OUTDTACPR( LZ1 )
```

Notes:

1. Without this mode description, connecting an AS/400 database stops the session, and SNA sense code 0821 0002 is issued.
2. The number of maximum sessions or conversations depends on your system administration.

APPC Data Compression

The ODBC driver for AS/400 Database supports APPC data compression as the default option to improve performance of the data exchange.

To disable the APPC data compression, add the following string to the target data source definition in ODBC.INI:

```
Compression=
```

Attribute Keywords for SQLDriverConnect()

The ODBC driver for AS/400 database supports the following IBM ODBC driver-unique attribute keywords for SQLDriverConnect(). The attributes specified in the input string of SQLDriverConnect() override the data source definition in ODBC.INI:

Keyword	Attribute value description
DESC	Data Source description
PROFILE	A full path and file name of connection user profile
NAMECONV	Naming Convention : SQL naming convention (COLLECTION.TABLE) 1 : System naming convention (Library/File)
LIB	Default Library List

attribute-value ::= lib1 lib2 lib3

DATEFMT Date format

: Julian (YY/DDD)
1 : Month, day, year (MM/DD/YY)
2 : Day, month, year (DD/MM/YY)
3 : Year, month, day (YY/MM/DD)
4 : United States (MM/DD/YYYY)
5 : ISO (YYYY-MM-DD)
6 : Europe (DD.MM.YYYY)
7 : JIS (YYYY-MM-DD)

DATESEP Date separator

: Slash (/)
1 : Period (.)
2 : Dash (-)
3 : Comma (,)
4 : Blank ( )

TIMEFMT Time format

: Hours, minutes, seconds (HH:MM:SS)
1 : United States (HH:MMxx) xx is AM for a.m. or PM for p.m..
2 : ISO (HH.MM.SS)
3 : Europe (HH.MM.SS)
4 : JIS (HH:MM:SS)

TIMESEP Time separator

: Colon (:)
1 : Period (.)
2 : Comma (,)
3 : Blank ( )

DECP Decimal point

: Period (.)
1 : Comma (,)

Considerations and Limitations

Auto Logon

When you use the Personal Communications ODBC driver, specify **Auto Logon** in the workstation profile **(*.WS)**.

Note: If you specify an incorrect user ID or password for **Auto Logon**, the Logon panel appears when you establish the connection to the AS/400 database.

Logon Timeout

If the Logon panel appears when you establish the connection to the AS/400 database with the Personal Communications ODBC driver, the specified logon timeout value is inactivated.

Using Lotus 1-2-3

When you access a database with the Personal Communications ODBC driver using Lotus 1-2-3, add the following line to the registration file **LOTUS.BCF** \LOTUS\DATALENS subdirectory of the Windows directory.

```
DN="ODBC" DL="DLODBC" DD="ALL ODBC Sources";
```

Using Microsoft Access

The default logon timeout value is set to 20 seconds for Microsoft Access. If the logon timeout occurs before you establish the connection to the AS/400 database, specify a larger value for the logon timeout in the **.INI** file of Microsoft Access.

Maximum Number of Columns in a Table

When you use the Personal Communications ODBC driver, you can access the database with a table containing up to 800 columns.

Chapter 20. Considerations for Installation and Use of PC400 Sessions

This chapter describes considerations and restrictions for PC400 functions. First-time users of PC400 or users who want only to perform simple operations using the PC400-supplied default values need not read this chapter.

Refer to this chapter:

If a problem occurs during operation

When you want to obtain more detailed information about the system

When you want to know the restrictions imposed on the system's use

General Workstation Window Operations: Scroll Bar

While you select **Font Size** from the Appearance menu in the session window, then select **Fixed Size** from the Select Display Font window, the entire operator information area might not fit onto the screen if you have specified **With Scroll-Bar** in the Window Setup window.

Print Processing

Printing GDI Fonts

Some printer drivers do not support fixed-pitch GDI fonts.

CPI/LPI of Device Fonts

If the printer driver cannot print device fonts associated with the user-specified CPI/LPI, the print output can be generated with incorrect CPI/LPI values.

Simultaneous Print Requirement

Some printer drivers cannot process requirements for multiple printing and therefore may cause an unrecoverable application error in the print execution module.

PCSERR999 Error Messages

Message PCSERR999 - An internal error of the Personal Communications. might appear if there is insufficient memory. If any print jobs are queued in the print manager, delete those print jobs.

Printable Area

Depending on the printer driver used, it might not be possible to use the entire surface of the paper for printing.

If the printing position is over the printable area, the page is automatically changed. When using a printer driver that allows you to set the margins, specify the minimum margins, thus maximizing the printable area.

© Copyright IBM Corp. 1989, 1996

Notes on Using a Printer Session

If you are printing without using the Windows print manager, and the printer is temporarily disabled (for example, paper runs out, or the power is not turned on), a message window appears on the Windows screen. (The host system is not notified.)

If you select **Cancel** from the window, PC400 sends the **Cancel Printing** command to the host system, and printing is canceled.

PDT Mode

Printing using the PDT file is restricted as follows:

Only the fonts specific to the printer being used are supported.

Graphic print is printed via the Windows printer driver selected in **Printer Setting**, regardless of the PDT mode.

Postscript printers are not supported. (There are no PDF files for Postscript printers.)

Printing Using the Windows Printer Drivers

The SCS control codes may not always work correctly, depending on the printer drivers and fonts being used.

Setting the Code Page

The host code page, which is set in the Configuration panel, is used as the default. The Set Initial Condition (SIC) command is used to set the host code page.

You can change the code page by using Set GCGID Through GCID (SCG) command or Set CGCS Through Local ID (SCGL) command. The same code pages for the display session are available.

For considerations and restrictions on the use of PC400, information supplementary to the items described in this appendix is stored, as a file, on the installation diskette. To access this information, refer to the README.TXT file that is saved in the directory where PC400 is installed.

Glossary

A

adapter. A hardware component that must be installed in the PC to connect to the SDLC, LAN, asynchronous, DFT, or other communications attachment (possibly connecting through a modem).

American National Standard Code for Information Interchange (ASCII). The standard code, using a coded character set consisting of 7-bit coded characters (8 bits including parity check), that is used for information interchange among data processing systems, data communication systems, and associated equipment. The ASCII set consists of control characters and graphic characters. See also *Extended Binary-Coded Decimal Interchange Code*.

attachment. A communications link used by Personal Communications to connect a PC to a host system, consisting of an adapter and controlling software.

B

backup diskette. A diskette that contains information copied from a Personal Communications diskette.

binary. Pertaining to the base two system of numbers. The binary digits are 0 and 1. Executable files are generally in binary format rather than the character string format that text files are composed of.

C

Caps Lock. The PC keyboard mode entered after the Caps Lock key is pressed. This mode is indicated by a capital A in the operator information area (OIA). When the Shift key is pressed while in this mode, Caps Lock is temporarily discontinued and the OIA indicator changes. Pressing the Shift key again returns the Caps Lock mode.

character set. A finite group of characters defined for a keyboard or output device.

configuration. (1) The arrangement of a computer system or network as defined by the nature, number and chief characteristics of its functional units.
(2) In Personal Communications, the arrangement of PCs connected to one or more host systems by one or more attachment types.

continuous carrier. A characteristic of the modem used in an SDLC type of attachment; frequency capable of being modulated or impressed with a second (informative carrier) signal.

customization. The process of configuring one or more PCs connected to a host system by the SDLC, LAN, ASYNCH, TDLC or other attachment. Customization precedes Personal Communications installation and includes the definition of the sessions to be carried out by Personal Communications.

D

default. A value, attribute, or option that is assumed when no differing selection is made.

dial-up line. See *switched line*.

directory. A named hierarchical grouping of files in a file system.

downloading. The transfer of a file from a host system to a PC.

E

EBCDIC. See *extended binary-coded decimal interchange code*.

enhanced graphics adapter (EGA). An adapter, such as the IBM Enhanced Graphics Adapter, that provides high-resolution graphics, allowing the use of a color display for text processing as well as graphics applications.

Extended Binary-Coded Decimal Interchange Code (EBCDIC). The standard code, using a character set consisting of 8-bit coded characters, used by Personal Communications for information interchange between PCs and a host system. See also *American National Standard Code for Information Interchange*.

F

field. (1) An area in a record or panel used to contain data.
(2) In the IBM 3270 or 5250 data stream, a group of consecutive positions on a presentation space having similar characteristics, which are defined by a field attribute byte at the beginning of the field.

© Copyright IBM Corp. 1989, 1996

H

hard disk. A rigid-magnetic disk such as the internal disks used in the system units of PCs and in external hard disk drives (also known as a fixed disk).

I

International Telecommunication Union - Telecommunication Standardization Sector. A telephonic media communications standards committee.

interrupt level. A number assigned to an interrupt to indicate priority. The interrupt with the lowest number has the highest priority.

ITU-T. See *International Telecommunication Union - Telecommunication Standardization Sector*.

L

LAN. See *local area network*.

leased line. Synonym for *nonswitched line*.

line speed. The speed at which data is transferred over an analog (telephone) line. Line speeds depend on the quality of the line.

local area network (LAN). A data network in which communications are limited to a moderate-sized geographic area such as a single office building, warehouse, or campus, and which do not generally extend across public rights-of-way.

logical unit (LU). A port that provides user access to the host and to the SNA network in order to communicate with another user.

logon. The process of accessing a domain and assuming a user ID.

LU. See *logical unit*.

LU 6.2. A type of LU that supports sessions between two applications in a distributed data processing environment using the SNA general data stream, which is a structured-field data stream, or a user-defined data stream.

N

network. A configuration of terminals connected to a host system for information interchange.

nonswitched line. (1) A connection between systems or devices that does not have to be made by dialing. Contrast with *switched line*. (2) A telecommunication line on which connections do not have to be established by dialing. Synonymous with *leased line*.

Num Lock. The keyboard mode entered after the Num Lock key is pressed. This mode is indicated by NUM in the operator information area (OIA). When the Shift key is pressed while in this mode, Num Lock is temporarily discontinued and the OIA indication changes. Pressing the Shift key again returns to Num Lock mode.

O

OIA. See *operator information area*.

OIA indicator. Characters or symbol in the operator information area providing information about network, workstation, gateway, or interface status. See also *operator information area*.

operator information area (OIA). In Personal Communications, the bottom line of a PC screen, which shows information on status and Personal Communications connections.

P

PC Network. A local area network providing peer-to-peer communication among IBM personal computers, allowing them to share resources. It utilizes carrier sense multiple access/collision detect (CSMA/CD) protocol and supports a data transmission rate of 2 million bits per second. Broadband and baseband versions are available.

permanent virtual circuit (PVC). In X.25 and frame-relay communications, a virtual circuit that has a logical channel permanently assigned to it at each data terminal (DTE). Call-establishment protocols are not required. Contrast with *switched virtual circuit (SVC)*.

personal computer. A microcomputer primarily intended for stand-alone use by an individual, but may be connected to mainframes or networks.

presentation space. The entire window of data, which can exceed the boundaries of a display screen's viewing area.

public application. An application shared among users on a network.

S

SAP. See *service access point*.

SDLC. See *Synchronous Data Link Control*.

service access point (SAP). The gateway address of the controller. This provides a point to link the controller to the host system.

session ID. An alphabetic ID (**a** through **h**) assigned by Personal Communications to each session or screen. This applies to all types of host sessions and is used in file transfers. See also *short name*.

Shift Lock. The PC keyboard mode entered after the Shift Lock key is pressed. In this mode, the keyboard performs the function printed on the upper half of the keytop. Press the Shift key to cancel the Shift Lock mode.

short name. In Personal Communications, a character displayed in column 7 of the operator information area that shows the session ID. See also *session ID* and *operator information area*.

SNA. See *Systems Network Architecture*.

SNA network. The part of a user-application network that conforms to the formats and protocols of Systems Network Architecture. It enables reliable transfer of data among end users and provides protocols for controlling the resources of various network configurations. The SNA network consists of network addressable units (NAUs), boundary-function components, and the path control network.

source diskette. In a diskette copying procedure, the diskette from which information is read.

SVC. See *switched virtual circuit*.

switched line. A telephonic communication line on which connections are established by dialing. See also *switched virtual circuit*. Contrast with *nonswitched line*.

switched virtual circuit (SVC). (1) An X.25 circuit that is dynamically established when needed. The X.25 equivalent of a switched line. (2) A virtual circuit that is requested by a virtual call. It is released when the virtual circuit is cleared. Contrast with *permanent virtual circuit (PVC)*.

Synchronous Data Link Control (SDLC). A discipline for managing synchronous, code-transparent, serial-by-bit information transfer over a line connection. Transmission exchanges may be duplex (in both directions at the same time) or half-duplex (in either direction, one direction at a time) over switched lines or direct lines.

Systems Network Architecture (SNA). A set of rules for controlling the transfer of information in a layered protocol structure communications network. The logical structure, formats, protocols, and operating sequences for transmitting data and controlling network configuration and operation are defined.

T

token-ring network. (1) A ring network that allows unidirectional data transmission between data stations, by a token passing procedure, such that the transmitted data return to the transmitting station. (2) A network that uses a ring topology, in which tokens are passed in a circuit from node to node. A node that is ready to send can capture the token and insert data fir transmission.

transferring files. Sending files from a PC to a host system or vice versa. See *downloading* and *uploading*.

U

uploading. The transfer of a file from a PC to a host system.

V

video graphics adapter (VGA). A computer adapter that provides high-resolution graphics and a total of 256 colors. See *enhanced graphics adapter (EGA)*.

W

WAN. See *wide area network*.

wide area network (WAN). A network that provides data communication capability in geographic areas larger than those serviced by local networks.

Glossary

Index

Numerics

3270 data stream (printing) 10-14

A

adding a file to the list 5-4
adding templates 5-5
additional options 5-9
AS/400
  file 17-7
AS/400 files 17-7
ASCII text files 17-57
asynchronous modem 6-1

B

BASIC random files 17-60
BASIC sequential files 17-62
BETWEEN test 17-27
BIFF files 17-68

C

changing miscellaneous items 5-11
changing the contents of a list 5-4
changing the packet size 12-5
changing translation tables 5-11
character sets 7-1, 7-5
clearing sessions before transfer 5-10
code pages 7-1, 7-5
color mixing, printer 10-13
command and indication 6-1
command syntax special characters xvii
commands
  MVS/TSO send 11-9
commands, VM/CMS
  VM/CMS RECEIVE 11-6
  VM/CMS SEND 11-3
compiler (printer table)
  printer definition file format 14-1, 14-21
compiler, printer table
  description of 10-1
  explanation 14-1
  invoking 10-1
  printer color mixing 10-13
  printer definition file format 10-1
conditions, specifying WHERE 17-24
considerations
  installation 12-1
considerations and restrictions
  PC400 20-1
  ZipPrint 12-13
contacting IBM 3-1, 3-3
conversion errors that can occur during transfer 17-16
country 7-1
country codes 7-1
CPI/LPI of device font 12-12
creating a template 5-5
creating a transfer request
  receiving data from the host 17-17
  transferring data to the host 17-8
creating IDP Files 5-13
creating list files 5-4
cursor color 12-1
customize translation window 5-12
customizing a display translation table 12-3
customizing printer definition table 10-1
customizing translation tables 5-12

D

data conversions
  data types
    ASCII numeric 17-54
    binary 17-54
    character 17-55
    double-precision 17-55
    hexadecimal 17-55
    integer 17-56
    packed decimal 17-56
    single-precision 17-56
    zoned decimal 17-56
  record size 17-53
  workstation file types
    ASCII text 17-57
    BASIC random 17-60
    BASIC sequential 17-62
    BIFF 17-68
    data interchange format (DIF) 17-65
    DOS random 17-70
    DOS random type-2 17-72
    no-conversion 17-75
data description specifications (DDS) 17-45, 17-62
data interchange format files (DIF) 17-65
data stream 14-35
data stream support, printer
  3270 10-14
  SCS 10-15
data transfer function 17-1
data types
  ASCII numeric 17-54
  binary 17-54
  character 17-55
  double-precision 17-55

© Copyright IBM Corp. 1989, 1996

data types *(continued)*
hexadecimal 17-55
integer 17-56
packed decimal 17-56
single-precision 17-56
zoned decimal 17-56
database file 17-7
DDM
transfer function 17-7
DDM (distributed data management) 17-2
DDS (data description specifications) 17-45, 17-62
default (DFT) keyword 17-62
defining the Windows printer for a session 4-1
defining transfer types 5-9
deleting a file from the list 5-4
delimiting print jobs 10-17
DFT (default) keyword 17-62
dial character 6-2
distributed data management
file concept 17-7
distributed data management (DDM) 17-2
DOS commands
RECEIVE.EXE 11-2
SEND.EXE 11-2
DOS random files 17-70
DOS random type-2 files 17-72
drawing buffer size 12-7

E

easy mouse operation 5-2
edit-copy buffer 12-8
edit-function restrictions with CUT attachment 12-4
edit-function restrictions with Home3270 attachment 12-4
editing lists 5-4
enhanced 7-1
enhanced protocol 5-11
explaining a file description file 17-45
extension for list-files 5-10

F

field attribute code 15-1
file
AS/400 17-7
database 17-7
joining 17-7
logical 17-7
physical 17-7
file description file 17-7, 17-45
file description file entries
comment lines 17-52
example 17-53
format 17-46
PCFDF 17-46
file description file entries *(continued)*
PCFL 17-48
PCFO 17-47
PCFT 17-46
File Option 5-7, 5-8
APPEND 5-7, 5-8
ASCII 5-7, 5-8
BLANK 5-7, 5-8
CRLF 5-7, 5-8
file transfer 18-1
CICS receive 11-20
CICS send 11-17
host 11-1
MVS/TSO receive 11-14
MVS/TSO send 11-9
VM/CMS receive 11-6
VM/CMS send 11-3
file transfer directory 5-11
file-transfer code translation 11-22
file-transfer timeout 5-10

G

graphic protocol 12-6
advanced protocol 12-6
native protocol 12-6

H

highlighting conventions xvi
Hitachi high-speed hybrid telephone 6-2
hole in screen caused by clearing a graphic character 12-9
host code page 7-1, 7-6
host command 5-11
host file transfer
IND$FILE 11-1
host-connected keyboard 7-1
host-directed print 10-14
how to handle errors caused by insufficient memory 12-7
how to use this book xv

I

IBM ASYNC/SDLC V.32 modem 6-1
IDP file 5-13
ignoring blank pages 12-11
import/export 5-7, 12-5
IN test 17-27
IND$FILE 11-1
information, where to get more 2-1
installation
considerations 12-1
IS test 17-28

ISNOT test 17-28
ISPF 11-9

K

keyboard 7-1
keyboard country ID 7-3
keyboard layouts 8-1
keyboard type

L

library 17-7
licensing agreement xiii
LIKE test 17-26
list file 5-4
logical database file 17-7
logical record length (LRECL) 5-8

M

member 17-8
messages 9-1
modem information
  asynchronous 6-1
  IBM ASYNC/SDLC V.32 6-1
  synchronous 6-1
  US Robotics Sportster 6-1
MVS/TSO
  ISPF 11-9

N

NEC ITM2400mkII Modem 6-2
no-conversion files 17-75
notes on using a printer session 12-12, 20-2
numeric values, specifying WHERE 17-30

O

ODBC driver 19-1
online help 2-1
organization xv

P

packet size 5-10
PC code page 5-10, 7-1
PC/3270 messages 9-1
PC400 Database Access 19-1
PC400 messages 9-1
PCFDF entries 17-46
PCFL entries 17-48
PCFO entry 17-47
PCFT entries 17-46
PCOMM forum 3-4
PCSERR999 error messages 12-12, 20-1
PCSPTC program 10-1, 14-1
PDF 4-2
PDT file
  creating and changing 14-1
  customizing 10-1
PDT files 4-2
PDT mode 12-12, 20-2
Personal Communications highlights 1-1
Personal Communications library 2-2
PFT 14-38
PFT migration utility 14-38
physical database file 17-7
plotter 12-9
print buffer size 12-8
print job control by using SNA timeout 12-10
print jobs, delimiting 10-17
printable area 12-12, 20-1
printer
printer color mixing 10-13
printer control codes
  format 14-29
  list 14-31
  restrictions 14-35
printer control parameter 4-5
printer data stream support
  3270 10-14
  SCS 10-15
printer definition file 4-2
printer definition file format 10-1, 14-1, 14-21
printer definition table 4-2, 10-1, 14-1
  creating and changing 14-1
  description of 10-1
  explanation 14-1
printer function table (PFT) 14-38
printer parameter 14-35
Printer Table Compiler
  invoking 10-1
  printer color mixing 10-13
  printer definition file format 10-1, 14-1, 14-21
printing 4-1
printing APL 12-11
printing reverse-display character with GDI font 12-12
printing reverse-display characters with device font 12-12
printing to disk 4-9
problem determination and reporting 3-1
  problem determination (PD)
    environment 3-1
    problem area 3-2
    problem re-creation 3-2
    problem type 3-1
    symptom 3-1
  problem reporting (PR) 3-3
  problem source identification (PSI) 3-2

program, host
IND$FILE 11-1

R

README information 12-1
RECEIVE command 11-2
receiving files from a host 11-2
receiving files from the host system 5-3
record
format 17-8
record format 5-8
record length limit 17-53
record size
record length limit 17-53
related publications xvii
releasing insert mode 12-1
replacing and deleting templates 5-6
request, transfer 17-7
reserved word 17-36

S

saving a transfer request 17-15
screen-size control 12-2
scroll bar 12-1, 20-1
scroll-lock key 12-2
SCS 10-14
SCS SPD/SLD command (LU 1) 12-11
SCS TRN command (LU 1) 12-11
SEND command 11-2
sending files to a host 11-2
sending files to the host system 5-2
setting the printer control parameter 4-5
setting transfer options 5-10
setting up the printer 4-1
shift support 7-3
simultaneous printing request 12-12
SNA character string 10-14
Software Solutions Center 3-5
source file
transferring data to 17-4
space saving 7-1
status window 5-10
structured fields 10-17
SVF control code 12-12
synchronous modem 6-1

T

technical assistance 3-3
template 5-5
test
combination 17-28
logical AND and logical OR 17-28
testing templates
source file 5-6
templates 5-6
test mode 5-6
trademarks xiv
transfer function 17-5
transfer request
definition 17-7
transfer requests for receiving (example) 17-36
transfer types 5-7
transferring data to AS/400 17-2
transferring data to the host 17-2
transferring files 11-1
transferring files using import/export 5-7
transparent (SCS control code) 10-15
TSO allocation parameter (MVS/TSO) 5-9
allocation amounts 5-9
allocation units 5-9
AVBLOCK 5-9
CYLINDERS 5-9
TRACKS 5-9
block size 5-9

U

US Robotics Sportster modem 6-1
use
considerations 12-1
using a printer in non-SNA coaxial-cable attachment 12-10
using bitmaps for drawing 12-7
using constants 17-29
using expressions 17-30
using list files 5-2, 5-3
using PDT files 4-2
using the Load button 5-3
using the Paste button 5-3

V

virtual printers 13-1
VM/CMS command
SEND 11-3

W

who should read this book xv
workstation file types 17-57

Communicating Your Comments to IBM

Personal Communications
AS/400 and 3270 for Windows
Reference
Version 4.1

Publication No. SC31-8264-00

If you especially like or dislike anything about this book, please use one of the methods listed below to send your comments to IBM. Whichever method you choose, make sure you send your name, address, and telephone number if you would like a reply.

Feel free to comment on specific errors or omissions, accuracy, organization, subject matter, or completeness of this book. However, the comments you send should pertain to only the information in this manual and the way in which the information is presented. To request additional publications, or to ask questions or make comments about the functions of IBM products or systems, you should talk to your IBM representative or to your IBM authorized remarketer.

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

If you are mailing a readers' comment form (RCF) from a country other than the United States, you can give the RCF to the local IBM branch office or IBM representative for postage-paid mailing.

If you prefer to send comments by mail, use the RCF at the back of this book.

If you prefer to send comments by FAX, use this number:

United States and Canada: **1-800-227-5088**

If you prefer to send comments electronically, use this network ID:

- IBM Mail Exchange: **USIB2HPD at IBMMAIL**
- IBMLink: **CIBMORCF at RALVM13**
- Internet: **USIB2HPD@VNET.IBM.COM**

Make sure to include the following in your note:

Title and publication number of this book
Page number or topic to which your comment applies.

Help us help you!

Personal Communications
AS/400 and 3270 for Windows
Reference
Version 4.1

Publication No. SC31-8264-00

We hope you find this publication useful, readable and technically accurate, but only you can tell us! Your comments and suggestions will help us improve our technical publications. Please take a few minutes to let us know what you think by completing this form.

Overall, how satisfied are you with the information in this book?	Satisfied	Dissatisfied

How satisfied are you that the information in this book is:	Satisfied	Dissatisfied
Accurate		
Complete		
Easy to find		
Easy to understand		
Well organized		
Applicable to your task		

Specific Comments or Problems:

Please tell us how we can improve this book:

Thank you for your response. When you send information to IBM, you grant IBM the right to use or distribute the information without incurring any obligation to you. You of course retain the right to use the information in any way you choose.

Your Internet Address: _____

Name

Address

Company or Organization

Phone No.

Help us help you!
SC31-8264-00

Cut or Fold
Along Line

IBM®

Fold and Tape **Please do not staple** Fold and Tape

NO POSTAGE
NECESSARY
IF MAILED IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

Information Development
Department CGMD
International Business Machines Corporation
PO BOX 12195
RESEARCH TRIANGLE PARK NC 27709-9990

Fold and Tape **Please do not staple** Fold and Tape

SC31-8264-00

Cut or Fold
Along Line

IBM®

Part Number: 39H0506

Printed in the United States of America
on recycled paper containing 10%
recovered post-consumer fiber.

39H 5 6

SC31-8264-